# 恢復叢集組態
## ONTAP 9

NetApp
May 13, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/ontap/system-admin/find-config-recover-cluster-task.html on May 13, 2022. Always check docs.netapp.com for the latest.

# 目錄

恢復叢集組態 . . . . . 1
尋找用於還原叢集的組態 . . . . . 1
從現有組態還原叢集組態 . . . . . 1

# 恢復叢集組態

## 尋找用於還原叢集的組態

您可以使用叢集中節點或叢集組態備份檔案的組態來還原叢集。

步驟

1. 選擇要恢復叢集的組態類型。

   - 叢集中的節點

     如果叢集由多個節點組成、而其中一個節點在叢集處於所需組態時具有叢集組態、則您可以使用儲存在該節點上的組態來還原叢集。

     在大多數情況下、包含複寫環的節點、以及最新的交易ID、是還原叢集組態的最佳節點。進階權限層級的「叢集環show」命令可讓您檢視叢集中每個節點上可用的複寫環清單。

   - 叢集組態備份檔案

     如果您無法識別具有正確叢集組態的節點、或叢集是由單一節點所組成、則可以使用叢集組態備份檔案來還原叢集。

   從組態備份檔案還原叢集時、可能需要使用診斷工具來解決備份與還原節點上的叢集組態之間的差異。因此、如果您使用組態備份檔案、應計畫聯絡技術支援部門。

2. 如果您選擇使用叢集組態備份檔案、請將檔案提供給您打算用來還原叢集的節點。

| 如果組態備份檔案位於... | 然後... |
|---|---|
| 位於遠端URL | 使用進階權限層級的「系統組態備份下載」命令、將其下載至恢復節點。 |
| 在叢集中的節點上 | a. 使用進階權限層級的「系統組態備份show」命令、尋找叢集處於所需組態時所建立的叢集組態備份檔案。<br>b. 如果叢集組態備份檔案不在您打算用來還原叢集的節點上、請使用「系統組態備份複本」命令將其複製到還原節點。 |

## 從現有組態還原叢集組態

若要在叢集故障後從現有組態還原叢集組態、請使用您選擇的叢集組態重新建立叢集、並將其提供給恢復節點、然後將每個額外節點重新加入新叢集。

您只能執行此工作、從導致叢集組態遺失的災難中恢復。

如果您是從組態備份檔案重新建立叢集、則必須聯絡技術支援部門、以解決組態備份檔案與叢集中現有組態之間的任何差異。

步驟

1. 停用每個HA配對的儲存容錯移轉：

   hy*儲存容錯移轉修改-node_node_name_-enabled_fal*

   您只需針對每個HA配對停用一次儲存容錯移轉。當您停用節點的儲存容錯移轉時、節點的合作夥伴也會停用儲存容錯移轉。

2. 停止每個節點（恢復節點除外）：

   '系統節點**halt -node_node_name_-**理由**"text"**

   ```
   cluster1::*> system node halt -node node0 -reason "recovering cluster"

   Warning: Are you sure you want to halt the node? {y|n}: y
   ```

3. 將權限層級設為進階：

   「設定-權限進階」

4. 在恢復節點上、使用「系統組態恢復叢集**recreflex**」命令重新建立叢集。

   此範例使用儲存在恢復節點上的組態資訊重新建立叢集：

   ```
   cluster1::*> configuration recovery cluster recreate -from node

   Warning: This command will destroy your existing cluster. It will
            rebuild a new single-node cluster consisting of this node
            and its current configuration. This feature should only be
            used to recover from a disaster. Do not perform any other
            recovery operations while this operation is in progress.
   Do you want to continue? {y|n}: y
   ```

   在恢復節點上建立新的叢集。

5. 如果您是從組態備份檔案重新建立叢集、請確認叢集還原仍在進行中：

   系統組態恢復叢集show *

   如果您是從正常節點重新建立叢集、則不需要驗證叢集還原狀態。

```
cluster1::*> system configuration recovery cluster show
 Recovery Status: in-progress
 Is Recovery Status Persisted: false
```

6. 引導需要重新加入重新建立叢集的每個節點。

   您必須一次重新啟動一個節點。

7. 針對需要加入重新建立叢集的每個節點、執行下列步驟：

   a. 從重新建立的叢集上健全的節點、重新加入目標節點：

      系統組態恢復叢集重新加入節點_norme_name_*

      此範例將「'node2'」目標節點重新加入重新建立的叢集：

```
cluster1::*> system configuration recovery cluster rejoin -node node2

Warning: This command will rejoin node "node2" into the local
         cluster, potentially overwriting critical cluster
         configuration files. This command should only be used
         to recover from a disaster. Do not perform any other
         recovery operations while this operation is in progress.
         This command will cause node "node2" to reboot.
Do you want to continue? {y|n}: y
```

      目標節點會重新開機、然後加入叢集。

   b. 驗證目標節點是否正常、並已與叢集中的其他節點形成仲裁：

      '*叢集顯示-合格資格為true *

      目標節點必須重新加入重新建立的叢集、才能重新加入其他節點。

```
cluster1::*> cluster show -eligibility true
Node                 Health  Eligibility   Epsilon
-------------------- ------- ------------  ------------
node0                true    true          false
node1                true    true          false
2 entries were displayed.
```

8. 如果您是從組態備份檔案重新建立叢集、請將恢復狀態設為「完成」：

   系統組態恢復叢集修改恢復狀態完成*

9. 返回管理權限層級：

   「設定-權限管理」

10. 如果叢集僅包含兩個節點、請使用「叢集**HA modify**」命令重新啟用叢集HA。
11. 使用「儲存容錯移轉**modify**」命令、為每個HA配對重新啟用儲存容錯移轉。

如果叢集具有SnapMirror對等關係、您也需要重新建立這些關係。如需詳細資訊、請參閱 "資料保護"。

**Copyright Information**

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

**Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.