# 在SVM上建立檔案和目錄稽核組態

ONTAP 9

NetApp
May 18, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/ontap/nas-audit/create-auditing-config-task.html on May 18, 2022. Always check docs.netapp.com for the latest.

# 目錄

在SVM上建立檔案和目錄稽核組態 . . . . . 1
建立稽核組態 . . . . . 1
在SVM上啟用稽核 . . . . . 2
驗證稽核組態 . . . . . 2

# 在SVM上建立檔案和目錄稽核組態

## 建立稽核組態

在儲存虛擬機器（SVM）上建立檔案和目錄稽核組態、包括瞭解可用的組態選項、規劃組態、然後設定和啟用組態。然後您可以顯示稽核組態的相關資訊、以確認所產生的組態為所需的組態。

在開始稽核檔案和目錄事件之前、您必須先在儲存虛擬機器（SVM）上建立稽核組態。

如果您打算建立稽核組態以進行集中存取原則暫存、則SVM上必須有SMB伺服器。

- 雖然您可以在稽核組態中啟用集中存取原則接移功能、但不會在SMB伺服器上啟用動態存取控制、但只有啟用動態存取控制時、才會產生集中存取原則接移事件。

  動態存取控制是透過SMB伺服器選項來啟用。預設不會啟用此功能。

- 如果命令中某個欄位的引數無效、例如欄位的輸入無效、項目重複、以及項目不存在、則命令會在稽核階段之前失敗。

  此類失敗不會產生稽核記錄。

如果SVM是SVM災難恢復來源、則目的地路徑無法位於根磁碟區上。

步驟

1. 使用規劃工作表中的資訊、建立稽核組態、根據記錄大小或排程來旋轉稽核記錄：

| 如果您想要以下列方式來旋轉稽核記錄… | 輸入… |
|---|---|
| 記錄檔大小 | 「vserver稽核建立-vserver vserver_name -目的地路徑-events [{file-ops |
| cs-logon-log註 銷 | cap-stage |
| file-share | nap-police-changes |
| user-account | 資訊安全組 |
| 授權-原則變更｝][-format {XML | evtx}][-rotation-limit integer][-size-size {leger[TB_bap][TB[TB |
| 排程 | 「vserver稽核建立-vserver vserver_name -目的地路徑-事件[{file-ops |
| cs-login-log註 銷 | cap-stived}][-format {XML |

下列範例會建立稽核組態、以大小為基礎的旋轉方式來稽核檔案作業和SMB登入及登出事件（預設值）。記錄格式為「evtx」（預設）。這些記錄儲存在「/Audit記錄檔」目錄中。記錄檔大小上限為「200 MB」。當記錄大小達到200 MB時、就會進行旋轉：

```
cluster1::> vserver audit create -vserver vs1 -destination /audit_log
-rotate-size 200MB
```

下列範例會建立稽核組態、以大小為基礎的旋轉方式來稽核檔案作業和SMB登入及登出事件（預設值）。記錄格式為「evtx」（預設）。記錄檔大小上限為「100 MB」（預設值）、記錄檔旋轉上限為「5」：

```
cluster1::> vserver audit create -vserver vs1 -destination /audit_log
-rotate-limit 5
```

下列範例建立稽核組態、以稽核檔案作業、CIFS登入和登出事件、以及使用時間型輪調的集中存取原則暫存事件。記錄格式為「evtx」（預設）。稽核記錄會每月於下午12：30循環一次一週中的所有天。日誌旋轉限制為「5」：

```
cluster1::> vserver audit create -vserver vs1 -destination /audit_log
-events file-ops,cifs-logon-logoff,file-share,audit-policy-change,user-
account,security-group,authorization-policy-change,cap-staging -rotate
-schedule-month all -rotate-schedule-dayofweek all -rotate-schedule-hour
12 -rotate-schedule-minute 30 -rotate-limit 5
```

# 在SVM上啟用稽核

## 完成稽核組態的設定之後、您必須在儲存虛擬機器（SVM）上啟用稽核。

SVM稽核組態必須已經存在。

當SVM災難恢復ID捨棄組態第一次啟動（完成SnapMirror初始化之後）且SVM具有稽核組態時ONTAP 、無法自動停用稽核組態。在唯讀SVM上停用稽核、以防止執行磁碟區填滿。只有在SnapMirror關係中斷且SVM為讀寫時、才能啟用稽核。

步驟

1. 在SVM上啟用稽核：

   「vserver稽核啟用-vserver vserver_name」

   「vserver稽核啟用-vserver VS1」

# 驗證稽核組態

## 完成稽核組態之後、您應該確認稽核設定正確且已啟用。

步驟

1. 驗證稽核組態：

   「vserver稽核show -instance -vserver vserver_name」

下列命令會以清單形式顯示儲存虛擬機器（SVM）VS1的所有稽核組態資訊：

「vserver稽核show -instance -vserver VS1」

```
                              Vserver: vs1
                      Auditing state: true
                Log Destination Path: /audit_log
      Categories of Events to Audit: file-ops
                         Log Format: evtx
                 Log File Size Limit: 200MB
       Log Rotation Schedule: Month: -
Log Rotation Schedule: Day of Week: -
         Log Rotation Schedule: Day: -
        Log Rotation Schedule: Hour: -
      Log Rotation Schedule: Minute: -
                  Rotation Schedules: -
            Log Files Rotation Limit: 0
```

**Copyright Information**

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

**Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.