Plug-in information required to configure Snap Creator

Snap Creator Framework

Aksel Davis, Zachary Wambold
April 01, 2021

This PDF was generated from https://docs.netapp.com/us-en/snap-creator-framework/administration/reference_information_required_to_configure_snap_creator.html on August 04, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Plug-in information required to configure Snap Creator 1

Plug-in information required to configure Snap Creator

Snap Creator supports the following built-in (or native) plug-ins: Oracle, DB2, MySQL, Sybase ASE, Domino, SnapManager for Microsoft SQL Server, SnapManager for Microsoft Exchange, MaxDB, VMware (vSphere and vCloud Director), Red Hat KVM, Citrix XenServer, and SAP HANA. Community plug-ins are not included in the package and must be downloaded separately.

The following table lists and describes the plug-in parameters and settings:

Parameters	Setting	Description
APP_NAME	oracle	db2
mysql	domino	vibe
smsql	sme	sybase
maxdb	kvm	xen
hana<plug-in>	Determines which application is being backed up. Snap Creator has built-in support for the listed applications. You can either use APP_NAME or configure APP_QUIESCE_CMDXX, APP_UNQUIESCE_CMDXX, and PRE_EXIT_CMDXX. If the application is not directly supported in Snap Creator, you can use a plug-in or run your own application quiesce or unquiesce commands or scripts. <PLUG-IN>: Copy the plug-in to the /path_to_scServer	scAgent/plug-ins directory and specify the plug-in in the APP_NAME parameter. Commands or Scripts: ---- APP_QUIESCE_CMD01=path_to_quiesceCMD APP_UNQUIESCE_CMD01=path_to_unquiesceCMD PRE_EXIT_CMD01=path_to_unquiesceCMD ----
APP_IGNORE_ERROR	(Y	N)
Determines whether Snap Creator should ignore errors from application plug-ins. This is useful when you want to back up multiple databases and do not want to stop the backup if the quiesce or unquiesce operations of one database fails.	APP_DEFINED_BACKUP	(Y

Parameters	Setting	Description
N)	The application plug-in is expected to perform the entire backup operation including quiescing, creating a Snapshot copy, and unquiescing. The built-in plug-ins do not support this kind of backup.	APP_DEFINED_RESTORE
(Y	N)	Enables application-based restore operations. In the event of a restore operation, Snap Creator sends a request to the application plug-in and the plug-in handles the request.
APP_DEFINED_MOUNT	(Y	N)
The built-in mount abilities of Snap Creator are ignored. Instead, the plug-in is responsible for all mount activities including volume or LUN clone creation. The built-in plug-ins do not support this type of mount.	APP_DEFINED_UMOUNT	(Y
N)	The built-in unmount abilities of Snap Creator are ignored. Instead, the plug-in is responsible for handling all unmount activities including volume or LUN clone deletion. The built-in plug-ins do not support this type of unmount operation.	APP_AUTO_DISCOVERY
(Y	N)	Enables application automatic discovery. Snap Creator sends a discover request to the application plug-in and the plug-in is then responsible for the discovery of the storage configuration. This can be done dynamically or made persistent using the APP_CONF_PERSISTENCE parameter, if the information is to be saved to the configuration file.
APP_CONF_PERSISTENCE	(Y	N)

Parameters	Setting	Description
Enables automatic discovery to be persistent, which means changes are dynamically updated in configuration file.	APP_DEFINED_CLONE	(Y
N)	The built-in cloning abilities of Snap Creator are ignored. Instead, the plug-in is responsible for handling all clone activities, including volume or LUN clone creation and deletion. The built-in plug-ins do not support this type of clone.	FS_NAME
plug-in	Determines which plug-in is being used for file system operations.	JAVA_HOME
Text	This setting points to the Java Virtual Machine (JVM) that should be used for executing .class and .jar files.	JVM_ARGS
Text	This setting controls the JVM settings when native Java .class or .jar files are executed. The default setting is -Xms32M -Xmx128M.	JAVA_CLASSPATH
Text	This setting defines the Java classpath. By default, plug-ins/native is configured and can be completed using this environment variable, which is appended to the default.	META_DATA_VOLUME
	Enables a Snapshot copy of the specified volume to be created after the unquiesce operation. This can be valuable for certain plug-ins for which the Snapshot copy of data must be created at different times. The parameter must not only specify the volume but the controller as well (for example, `controller1:volume1,volume2;controller2:volume3,volume4;controller3:volume5,volume6`).	PERL_HOME

Parameters	Setting	Description
Text	This setting points to the Perl interpreter that should be used for executing .pl files.	PERL_OPTS
Text	This setting controls the PERL interpreter settings when native Perl files are executed. Options for additional settings include directories (-I) that can be passed to the Perl interpreter.	PYTHON_HOME
Text	This setting points to the Python interpreter that should be used for executing .py files.	PYTHON_OPTS
Text	This setting controls the Python interpreter settings when native Python files are executed.	VALIDATE_VOLUMES

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.