Creating a configuration file

Snap Creator Framework

Aksel Davis, Zachary Wambold
January 19, 2021

This PDF was generated from https://docs.netapp.com/us-en/snap-creator-framework/domino-ops/task_using_the_gui_to_create_a_configuration_file.html on August 04, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Creating a configuration file 1

Creating a configuration file

Before you can back up IBM Domino databases, you need to create a configuration file. The configuration file is the input for Snap Creator backup and restore operations.

Only alphanumeric and underscore characters are allowed in configuration and profile names. Names cannot start with a number.

> Many sites use a profile-wide or site-wide global configuration file to apply storage system or VMware credential information to backup and restore configurations. For details about how to create a global configuration file, see the Snap Creator Framework 4.1.2 Administration Guide.

1. In the Profiles and Configurations pane, click **Add Profile**.
2. In the New Profile dialog box, enter the name of the profile, and then click **OK**.

   Creating a new profile automatically launches the Snap Creator Framework Configuration wizard. To add a new configuration to an existing profile, right-click the profile, and then select **New Configuration**.

   Throughout the Configuration wizard, click **Next** to advance to the next page and click **Back** to return to the previous page.

3. On the Configuration page, enter the name of the configuration, and then specify whether you want to enable password encryption.

   Password encryption is enabled by default to prevent passwords from being displayed in clear text in the configuration file.

   > Hover over a field in the wizard to display a tool tip.

4. On the Plug-in Type page, select **Application plug-in**.
5. On the Application Plug-ins page, select **IBM Domino**.
6. On the Plug-in parameters page, specify IBM Domino backup configuration details:

   > The examples in the following table are for UNIX environments. You can view examples of the settings for Windows in the screenshot that follows the table.

GUI parameter	CLI parameter	Description
Domino Data Directory	DOMINO_DATA_ PATH	The path to the Domino data directory. For example, /Domino/data.
notes.ini Path	DOMINO_INI_PATH	The path to the notes.ini file. For example, /Domino/data/notes.ini.

GUI parameter	CLI parameter	Description
Change info Directory	DOMINO_CHANGE_ INFO_PATH	The path to changeinfo files. For example, /changeinfo. **Important:** Make sure that you store changeinfo files on a volume other than the Domino data volume.
Backup Type	DOMINO_ DATABASE_TYPE	The database files to be backed up. Select a value from the GUI drop-down, or specify the corresponding number in the CLI command: • Everything (recommended) (CLI = 0) • *.box files (CLI= 1) • *.nsf, *.nsg, and *.nsh files (CLI = 2) • *.ntf files (CLI = 3)
IBM Domino installation directory	LOTUS	The path to the directory where Domino binary files are installed. In Linux, for example, /opt/ibm/domino (assuming the default installation path). In Windows, the parent of the Domino Shared Objects directory. **Note:** This is not the path to IBM Notes, formerly Lotus Notes.
Path to Domino shared objects	Notes_ExecDirectory	The path that contains Domino shared object files (.so or .dll). For example, /opt/ibm/domino/notes/latest/linux.
Data Restore Directory	DOMINO_ RESTORE_DATA_ PATH	For volume restores (assuming you are restoring to the same location from which you took the backup), the Domino data directory path. For single-file restores (NFS only), a location on the same volume as the Domino Data Directory. For example, /Domino/data/restore.

GUI parameter	CLI parameter	Description
Validate Domino Data Directory	VALIDATE_ DOMINO_DATA_ PATH	If the Domino environment has multiple mount points, some mount points might be on NetApp storage, while others might not be. Select a value from the GUI drop-down, or specify the corresponding value in the CLI command: • Yes backs up files on the Domino data directory path only. • No backs up all files in the Domino environment regardless of their location on disk.

The following example shows how you might complete the fields in a Windows environment:



7. On the Agent Configuration page, specify Snap Creator Agent connection information:

For this field…	Do this…
IP/DNS	Enter the IP address or DNS host name of the Snap Creator Agent host.
Port	If you are not using the default port for the Snap Creator Agent (9090), enter the port number.
Timeout (secs)	Leave the default.

8. When you are satisfied with your entries, click **Test agent connection** to verify the connection to the Agent.

If the Agent is not responding, verify the Agent details and confirm that host name resolution is working correctly.

9. On the Storage Connection settings page, specify connection information for the Storage Virtual Machine (SVM, formerly known as Vserver) on the primary storage system:

For this field…	Do this…
Transport	Select the transport protocol for communications with the SVM: HTTP or HTTPS.
Controller/Vserver Port	If you are not using the default port for the SVM (80 for HTTP, 443 for HTTPS), enter the port number.

Note: For information about how to use an OnCommand proxy, see the Snap Creator Framework 4.1.2 Administration Guide.

10. On the Controller/Vserver Credentials page, specify the credentials for the SVM on the primary storage system:

For this field…	Do this…
Controller/Vserver IP or Name	Enter the IP address or DNS host name of the SVM host.
Controller/Vserver User	Enter the user name for the SVM host.
Controller/Vserver Password	Enter the password for the SVM host.

Important: If you are planning to replicate Snapshot copies to a SnapMirrror or SnapVault destination, the name of the SVM you enter in this step must match exactly the name of the SVM you used when you created the SnapMirrror or SnapVault relationship. If you specified a fully qualified domain name when you created the relationship, you must specify a fully qualified domain name in this step, regardless of whether SnapCreator can find the SVM with the information you provide. Case is significant.

You can use the snapmirror show command to check the name of the SVM on the primary storage system:snapmirror show -destination-path destination_SVM:destination_volume where destination_SVM_name is the name of the SVM on the destination system and destination_volume is the volume. For more information about creating SnapMirrror and SnapVault relationships, see SnapMirror and SnapVault setup.

When you click **Next**, the Controller/Vserver Volumes window is displayed.

11. In the Controller/Vserver Volumes window, specify the volumes to be backed up by dragging and dropping from the list of available volumes in the left pane to the list of volumes to be backed up in the right pane, and then click **Save**.

The specified volumes are displayed on the Controller/Vserver Credentials page.

If you plan to back up the changeinfo directory, you must configure the volume containing the directory as a metadata volume, as described in Backing up the changeinfo directory. This option tells the IBM Domino plug-in to create a Snapshot copy of the changeinfo volume *after* creating the Snapshot copy for database files.

12. On the Controller/Vserver Credentials page, click **Add** if you want to specify SVM details and volumes to be backed up for another primary storage system.
13. On the Snapshot details page, specify Snapshot configuration information:

For this field…	Do this…
Snapshot Copy Name	Enter the name of the Snapshot copy. **Tip:** Click **Allow Duplicate Snapshot Copy Name** if you want to reuse Snapshot copy names across configuration files.
Snapshot Copy Label	Enter descriptive text for the Snapshot copy.
Policy Type	Click **Use Policy**, and then select the built-in backup policies you want to make available for this configuration. After you select a policy, click in the **Retention** cell to specify how many Snapshot copies with that policy type you want to retain. **Note:** For information about how to use policy objects, see the Snap Creator Framework 4.1.2 Administration Guide.
Prevent Snapshot Copy Deletion	Specify Yes only if you do not want Snap Creator to automatically delete Snapshot copies that exceed the number of copies to be retained. **Note:** Specifying Yes might cause you to exceed the number of supported Snapshot copies per volume.
Policy Retention Age	Specify the number of days you want to retain Snapshot copies that exceed the number of copies to be retained. You can specify a retention age per policy type by entering policy type:age, for example, daily:15.
Naming Convention	Leave the default.

The configuration specified in the following example performs a daily backup and retains four Snapshot copies:



14. On the Snapshot details continued page, set **Ignore Application Errors** to Yes if you want to force the backup operation to proceed even if one or more databases are in an inconsistent or corrupted state.

    You should ignore the remaining fields.

    > A Domino environment might consist of hundreds or thousands of databases. If even a single database is in an inconsistent or corrupted state, the backup will fail. Enabling **Ignore Application Errors** allows the backup to continue.

15. On the Data Protection page, specify whether you want to perform optional Snapshot copy replication to secondary storage:
    a. Click **SnapMirror** to mirror Snapshot copies.

       The policy for mirrored Snapshot copies is the same as the policy for primary Snapshot copies.

    b. Click **SnapVault** to archive Snapshot copies.
    c. Specify the policy for archived Snapshot copies.
    d. The instructions are in the following step13.
    e. In **SnapVault wait time**, enter the number of minutes you want Snap Creator to wait for the SnapVault operation to complete.
    f. You need to have set up SnapMirror and SnapVault relationships before performing replication to secondary storage. For more information, see SnapMirror and SnapVault setup.
16. On the Data Protection Volumes page, click **Add**, and then select the SVM for the primary storage system.

    When you click **Next**, the Data Protection Volume Selection window is displayed.

17. In the Data Protection Volume Selection window, specify the source volumes to be replicated by dragging and dropping from the list of available volumes in the left pane to the list of volumes in the SnapMirror and/or SnapVault areas in the right pane, and then click **Save**.

    The specified volumes are displayed on the Data Protection Volumes page.

18. On the Data Protection Volumes page, click **Add** if you want to specify SVM details and volumes to be replicated for another primary storage system.
19. On the Data protection relationships page, specify the credentials for the SVM on the SnapMirrror and/or SnapVault destination systems.
20. If you prefer to use NetAppOnCommand Unified Manager APIs instead of Data ONTAP APIs for Snapshot copies and SnapMirror/SnapVault updates, complete the fields on the DFM/OnCommand Settings page:
    a. Click **Operations Manager Console Alert** if you want to receive Unified Manager alerts, and then enter the required connection information for the Unified Manager virtual machine.
    b. Click **NetApp Management Console data protection capability** if you are using the NetApp Management Console data protection feature for 7-Mode SnapVault replication, and then enter the required connection information for the Unified Manager virtual machine.
21. Review the summary, and then click **Finish**.

Snap Creator lists the configuration file below the specified profile in the Profiles and Configurations pane. You can edit the configuration by selecting the configuration file and clicking the appropriate tab in the Configuration Content pane. You can rename the configuration by clicking **Rename** in the right-click menu. You can delete the configuration by clicking **Delete** in the right-click menu.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.