如果存在多个 SAN 路径，但禁用了多路径，SnapDrive storage create 命令将失

Snapdrive for Unix

Ivana Devine
August 06, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapdrive-unix/aix/concept_snapdrive_storage_create_command_fails_when_multiple_san_paths_are_present.html on October 26, 2021. Always check docs.netapp.com for the latest.

目□

如果存在多个 SAN 路径，但禁用了多路径，□ SnapDrive storage create 命令将失□ 1

如果存在多个 SAN 路径，但禁用了多路径，□ SnapDrive storage create 命令将失□

如果存在多个 SnapDrive 路径，但禁用了多路径，□ storage `create` 命令将失□。

例如，□于 SVM 的□个 iSCSI LIF ：

```
[root@scspr0189449001 etc]# iscsiadm --mode session --rescan
Rescanning session [sid: 1, target: iqn.1992-
08.com.netapp:sn.f7335762b23e11e695360050569c153a:vs.3, portal:
10.224.70.253,3260]
Rescanning session [sid: 2, target: iqn.1992-
08.com.netapp:sn.f7335762b23e11e695360050569c153a:vs.3, portal:
10.224.70.254,3260]
```

如果在 SnapDrive.conf 文件中将 `multipathing-type` □置□ `none` 且禁用了多路径服□，□□□使用 LVM □建存□□，将返回以下□□：

```
root@scspr0189449001 etc]# snapdrive storage create -fs /mnt/test -lun
rgvsim:/vol/asmvol/test -lunsize 500m
        LUN rgvsim:/vol/asmvol/test ... created
        mapping new lun(s) ... done
        discovering new lun(s) ... *failed*
        Cleaning up ...
         - LUN rgvsim:/vol/asmvol/test ... deleted
         0001-422 Admin error: LVM initialization of luns failed:
        Device /dev/sdb,/dev/sdc not found (or ignored by filtering).
```

之所以出□□□情况，是因□ `pvcreate` 命令会使用以逗号分隔的□□作□□个□□ `pvcreate /dev/sdb , /dev/sdc` 和一个名□ ` /dev/sdb ， /dev/sdc` 的□□，而□□□不存在。

如果要使用多个存□路径，并且需要使用 LVM ， □必□□用多路径。

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.