置控制限

Snapdrive for Unix

NetApp
August 06, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapdrive-unix/linux-administration/task_setting_up_access_control_permission.html on October 26, 2021. Always check docs.netapp.com for the latest.

目□

□置□□控制□限 1

□置□□控制□限

□可以通□在存□系□的根卷中□建特殊目□和文件来在 SnapDrive for UNIX 中□置□□控制□限。

□保以 root 用□身□登□。

□□

1. 在目□存□系□的根卷中□建目□ `sdprbac` 。

   要使根卷可□□，一□方法是使用 NFS 挂□此卷。

2. 在 `sdprbac` 目□中□建□限文件。□保以下□述正□无□：

   - 此文件必□名□ `sDHost-name.prbac` ，其中 host-name 是要□其指定□□□限的主机的名称。
   - 此文件必□□只□文件，以□保 SnapDrive for UNIX 可以□取它，但无法修改它。

   要□名□ dev-sund1 的主机授予□□□限，□□在存□系□上□建以下文件：` /vol/vol1/sdprbac/sddev-sund1.prbac`

3. 在文件中□置□主机的□限。

   □必□□文件使用以下格式：

   - □只能指定一个□限□□。要□主机授予□所有操作的完全□□□限，□□入字符串 all access 。
   - □限字符串必□是文件中的第一□。如果□限字符串不在第一行中，□文件格式无效。
   - □限字符串不区分大小写。
   - □限字符串前面不能有空格。
   - 不允□添加任何注□。

     □些有效□限字符串允□以下□□□□：

   - 无—主机无法□□存□系□。
   - snap create —主机可以□建 Snapshot 副本。
   - snap use —主机可以□除和重命名 Snapshot 副本。
   - snap all —主机可以□建，□原，□除和重命名 Snapshot 副本。
   - storage create delete —主机可以□建存□，□整存□大小和□除存□。
   - 存□使用—主机可以□接和断□存□□接，□可以在存□上□行克隆拆分估□和克隆拆分□始。
   - 存□全部—主机可以□建，□除，□接和断□存□□接，□可以在存□上□行克隆拆分估□和克隆拆分□□。
   - 所有□□—主机可以□□上述所有 SnapDrive for UNIX 操作。

     其中□个□限字符串都是□散的。如果指定快照使用，□主机可以□除或重命名 Snapshot 副本，但不能□建 Snapshot 副本，□原或□行任何存□配置操作。

   无□□□置的□限如何，主机都可以□行 show 和 list 操作。

4. □入以下命令以□□□□□限：

   ` * SnapDrive 配置□□ show filer_name*`

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.