断□ Snapshot 副本与存□□体的□接

Snapdrive for Unix

NetApp
August 06, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapdrive-unix/solaris/task_disconnectingsnapshot_copy_withstorage_entities.html on October 26, 2021.
Always check docs.netapp.com for the latest.

目□

断□ Snapshot 副本与存□□体的□接 1

断□ Snapshot 副本与存□□体的□接

□可以使用 SnapDrive snap disconnect` 命令断□包含存□□体的 Snapshot 副本的□接。

□□

1. □入以下命令：

   ` * SnapDrive snap disconnect ｛ -dg _ -fs _ -hostvol ｝ *file_spec* [*file_spec…*] （ -dg _ -fs _ -hostvol ｝ *file_spec* （ *file_spec…*） ] （ -full] ） （ -DeviceType ｛ shared _ dedicated ｝ ） ） ] （ -fstype □型）【 -vmtype □型□型 * 】（ -split` □型）

   此命令必□始□以存□□体□□，例如， ` -lun` ， ` -dg` ， ` -hostvol` ， 或 ` -FS` 。

   - 如果指定 LUN （` -lun` ），□必□□入□ LUN 名称。□不能在与其他存□□体（` -vg` ， ` -dg` ， ` -fs` ， ` -lvol` 或 ` -hostvol` options ）相同的命令行上使用 ` -lun` □□指定 LUN 。
   - 如果指定 RDM LUN （` -lun` ），□必□□入□ RDM LUN 名称。□不能在与其他存□□体（` -vg` ， ` -dg` ， ` -fs` ， ` -lvol` 或 ` -hostvol` options ）相同的命令行上使用 ` -lun` □□指定 RDM LUN 。
   - 如果指定 NFS 挂□点，□不能在同一命令行上指定非 NFS □体（` -vg` ， ` -DG` ， ` -FS` ， ` -lvol` 或 ` -hostvol` ）。□必□使用□独的命令来指定 NFS 挂□点。

   > 如果主机□体使用的 LUN 不属于 Snapshot 副本，□会出□□□消息。如果指定□个目□磁□□中包含的一个子集主机卷和 / 或文件系□，□也会□生□□。

SnapDrive for UNIX 将□除命令行中指定的存□□体的映射。

此命令行会□除与主机卷 dg5/myvolume 下的所有 LUN 的映射。它会□除通□ Snapshot □接操作□建的任何□□ LUN ：

```
# snapdrive snap disconnect -hostvol dg5/myvolume
```

此命令行会□除与主机卷 dg5/myvolume 下的所有 LUN 的映射。它会□除通□ Snapshot □接操作□建的任何□□ LUN ：

```
# snapdrive snap disconnect -hostvol dg5/myvolume
```

此命令将断□与磁□□ 1 （ dg1 ）和底□ LUN 的映射。它□会□除通□ Snapshot □接操作□建的任何□□ LUN ：

```
# snapdrive snap disconnect -lun toaster:/vol/vol1/luna -dg dg1
```

此命令行将□除与文件系□ fs1 及其下的 RDM LUN 的映射。它□会□除通□ Snapshot □接操作□建的任何□□ RDM LUN ：

```
# snapdrive snap disconnect -fs mnt/RDMNew
```

此命令行将□除与文件系□ fs1 及其所在 LUN 的映射。它□会□除通□ Snapshot □接操作□建的任何□□ LUN ：

```
# snapdrive snap disconnect -fs mnt/fs1
```

此命令行将□除磁□□ dg1， dG2 和 dg3 的映射。它会□除通□ Snapshot □接操作□建的任何□□ LUN ：

```
# snapdrive snap disconnect -dg dg1 dg2 dg3
```

以下示例将断□ Snapshot 副本与 Veritas 堆□上的文件系□磁□□的□接：

```
# snapdrive snap disconnect -fs /mnt/fs1_clone -fstype vxfs
delete file system /mnt/fs1_clone
- fs /mnt/fs1_clone ... deleted
- hostvol vxvm1_0/fs1_SdHv_0 ... deleted
- dg vxvm1_0 ... deleted
- LUN snoopy:/vol/vol1/lunVxvm1_0 ... deleted
```

以下示例将断□ LVM 堆□上文件系□磁□□的 Snapshot 副本的□接：

```
# snapdrive snap disconnect -fs /mnt/fs1_clone -fstype
                    ufs
delete file system /mnt/fs1_clone
- fs /mnt/fs1_clone ... deleted
- hostvol lvm1_0/fs1_SdHv_0 ... deleted
- dg lvm1_0 ... deleted
- LUN snoopy:/vol/vol1/lunLvm1_0 ... deleted
```

此示例将断□ Snapshot 副本与文件系□的□接：

```
# snapdrive snap disconnect -fs /mnt/fs1
delete file system /mnt/fs1
- fs /mnt/fs1 ... deleted
- LUN lech:/vol/vol1/lun1_0 ... deleted
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.