从二□存□□原□□

SnapManager Oracle

NetApp
August 06, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapmanager-oracle/unix-administration/task_restoring_backups_from_secondary_storage.html on October 26, 2021.
Always check docs.netapp.com for the latest.

目□

从二□存□□原□□ 1
示例 1

从二□存□□原□□

□可以从二□存□□原受保□的□□，并□□将数据□制回主存□的方式。

□可以使用□有 -from-secondary □□的 backup restore 命令从二□存□□原数据。如果未指定 -from-secondary □□，□ SnapManager 将从主存□上的 Snapshot 副本□原数据。

如果□□位于主存□上，□不能使用 -from-secondary □□；必□先□放主□□，然后才能从二□存□□原□□。如果使用□□卷，□必□使用 -temp-volume □□指定此卷。

□当指定 -from-secondary □□□，都必□指定 -copy-id □□。如果二□存□系□上有多个□□，□使用 -copy-id □□指定二□存□上的□个□□副本□用于□原操作。

> 如果□使用的是在 7- 模式下□行的 Data ONTAP ，□必□□ -copy-id □□指定有效□。但是，如果使用的是集群模式 Data ONTAP ，□不需要 -copy-id □□。

从二□存□□原数据□， SnapManager 会首先□□将数据直接从二□存□系□□原到主存□系□（而不□及主机）。如果 SnapManager 无法□行此□□原（例如，如果文件不属于文件系□），□ SnapManager 将回退到主机端文件副本□原。SnapManager 可通□□□方法从二□存□□行主机端文件副本□原。SnapManager □□的方法在 SMO.config 文件中□行配置。

- 如果 restore.secondaryAccessPolicy = Direct ，□ SnapManager 会克隆二□存□上的数据，将克隆的数据从二□存□系□挂□到主机，然后将数据从克隆□制到活□□境。

  □是默□的二□□□策略。

- 如果 restore.secondaryAccessPolicy = □接，□ SnapManager 会首先将数据□制到主存□上的□□卷，将数据从□□卷挂□到主机，然后将数据从□□卷□制到活□□境。

  只有当主机无法直接□□二□存□系□□，才□使用此策略。使用□接方法恢□所需□□是直接方法的□倍，因□会□建□个数据副本。

  a. □行以下操作之一：

如果□要 ...	那□ ...
如果□定□□位于主存□上，□□原完整的数据□	□入以下命令： smo backup restore -profileprofile_name-labelLabel-complete-recover -alllogs[-copy-idi]
如果□定□□不在主存□上，□□原完整的数据□	□入以下命令： smo backup restore -profileprofileprofile_name-labelLabel-complete -recover -alllogs-from-secondary （ -temp-volume <temp_volume>] ）（ -copy-ididid ）

示例

以下命令将从二□存□系□□原受保□的□□：

```
smo backup restore -profile PAYDB -label daily_monday -complete
-recover alllogs -from-secondary -copy-id 3042 -temp-volume
smo_scratch_restore_volume
Operation Id [8abc011215d385920115d38599470001] succeeded.
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.