看件脚本示例

SnapManager Oracle

NetApp
August 06, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapmanager-oracle/windows/task_viewing_sample_plugin_scripts.html on October 26, 2021. Always check docs.netapp.com for the latest.

目□

□看□件脚本示例 1
示例脚本 2

□看□件脚本示例

SnapManager 提供了一些脚本，□可以使用□些脚本作□示例来□建自己的脚本，也可以作□自定□脚本的基□。

□可以在以下位置□到□件脚本示例：

- <default_install_directory>\plugins\examples\backup\create
- <default_install_directory>\plugins\examples\clone\create
- <default_install_directory>\plugins\windows\examples\backup\create\post

包含示例□件脚本的目□包含以下子目□：

- 策略：包含配置后始□在克隆操作上□行的脚本。
- PRE ：包含配置后在克隆操作之前□行的脚本。
- POST ：包含配置后在克隆操作之后□行的脚本。

下表介□了示例脚本：

脚本名称	Description	脚本□型
validate_sid.sh	包含□目□系□上使用的 SID 的其他□□。□脚本将□□ SID 是否具有以下特征： • 包含三个字母数字字符 • 以字母□□	策略
cleanup.sh	清理目□系□，以便准□好存□新□建的克隆。根据需要保留或□除文件和目□。	□□求
mirror_the_backup.cmd	在使用 7- 模式 Data ONTAP 的 Windows □境中□行□□操作后，□卷□行□像。	任□后
vault_the_backup.cmd	如果□使用的是在 7- 模式下□行的任一 Data ONTAP ，□在 Windows □境中□行□□操作后存□ qtree 。	任□后
mirror_the_backup_cDOT.cmd	在使用集群模式 Data ONTAP 的 Windows □境中□行□□操作后□卷□行□像。	任□后

vault_the_backup_cDOT.cmd	在使用集群模式 Data ONTAP 的 Windows □境中□行□□操作后，将存□ qtree 。	任□后

默□情况下，随 SnapManager 提供的脚本使用 bash shell 。在□□□行任何示例脚本之前，□必□□保操作系□上已安装□ bash shell 的支持。

1. 要□□是否正在使用 bash shell ，□在命令提示符□□入以下命令： bash

   如果未看到□□，□表示 bash shell □行正常。

   或者，□也可以在命令提示符□□入 which — bash 命令。

2. 在以下目□中□到此脚本：

   <installdir>\plugins\examples\clone\create

3. 在 vi 等脚本□□器中打□此脚本。

示例脚本

以下示例自定□脚本将□□数据□ SID 名称，并防止克隆的数据□中使用无效名称。它包括三个操作（□□，描述和□行），□些操作是在□行脚本后□用的。□脚本□包括□□消息□理，代□□ 0， 4 和 >4 。

```
@echo off
REM $Id:
//depot/prod/capstan/Rcapstan_ganges/src/plugins/windows/examples/clone/cr
eate/policy/validate_sid.cmd#1 $
REM $Revision: #1 $ $Date: 2011/12/06 $
REM
REM

set /a EXIT=0

set name="Validate SID"
set description="Validate SID used on the target system"
set parameter=()

rem reserved system IDs
set INVALID_SIDS=("ADD" "ALL" "AND" "ANY" "ASC" "COM" "DBA" "END" "EPS"
"FOR" "GID" "IBM" "INT" "KEY" "LOG" "MON" "NIX" "NOT" "OFF" "OMS" "RAW"
"ROW" "SAP" "SET" "SGA" "SHG" "SID" "SQL" "SYS" "TMP" "UID" "USR" "VAR")

if /i "%1" == "-check" goto :check
if /i "%1" == "-execute" goto :execute
if /i "%1" == "-describe" goto :describe
```

```
:usage:
    echo usage: %0 "{ -check | -describe | -execute }"
    set /a EXIT=99
    goto :exit

:check
    set /a EXIT=0
    goto :exit

:describe
    echo SM_PI_NAME:%name%
    echo SM_PI_DESCRIPTION:%description%
    set /a EXIT=0
    goto :exit

:execute
    set /a EXIT=0

    rem SM_TARGET_SID must be set
    if "%SM_TARGET_SID%" == "" (
        set /a EXIT=4
        echo SM_TARGET_SID not set
        goto :exit
    )

    rem exactly three alphanumeric characters, with starting with a letter
    echo %SM_TARGET_SID% | findstr "\<[a-zA-Z][a-zA-Z0-9][a-zA-Z0-9]\>"
>nul
    if %ERRORLEVEL% == 1 (
        set /a EXIT=4
        echo SID is defined as a 3 digit value starting with a letter.
[%SM_TARGET_SID%] is not valid.
        goto :exit
    )

    rem not a SAP reserved SID
    echo %INVALID_SIDS% | findstr /i \"%SM_TARGET_SID%\" >nul
    if %ERRORLEVEL% == 0 (
        set /a EXIT=4
        echo SID [%SM_TARGET_SID%] is reserved by SAP
        goto :exit
    )

    goto :exit
```

```
:exit
    echo Command complete.
    exit /b %EXIT%
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.