Creating pretask, post-task, and policy scripts

SnapManager Oracle

Aksel Davis, Zachary Wambold
February 24, 2021

This PDF was generated from https://docs.netapp.com/us-en/snapmanager-oracle/windows/task_creating_pretask_post_task_and_policy_scripts.html on August 06, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Creating pretask, post-task, and policy scripts 1
Sample script 2

Creating pretask, post-task, and policy scripts

SnapManager enables you to create the scripts for the preprocessing activity, the post-processing activity, and policy tasks of the backup, restore, and clone operations. You must place the scripts in the correct installation directory to execute the preprocessing activity, post-processing activity, and policy tasks of the SnapManager operation.

Pretask and post-task script content

All scripts must include the following:

- Specific operations (check, describe, and execute)
- (Optional) Predefined environment variables
- Specific error handling code (return code (rc))

> You must include correct error handling code to validate the script.

You can use the pretask scripts for many purposes, for example, cleaning up a disk space before the SnapManager operation starts. You can also use the post-task scripts, for instance, to estimate whether SnapManager has enough disk space to complete the operation.

Policy task script content

You can execute the policy script without using specific operations such as check, describe, and execute. The script includes the predefined environmental variables (optional) and specific error handling code.

The policy script is executed before the backup, restore, and clone operations.

Supported format

A command file with a .cmd extension can be used as the prescript and post-script.

> If you select the shell script file, the SnapManager operation does not respond. To resolve this, you must provide the command file in the plug-in directory, and perform the SnapManager operation again.

Script installation directory

The directory in which you install the script affects how it is used. You can place the scripts in the directory and execute the script before or after the backup, restore, or clone operation takes place. You must place the script in the directory specified in the table and use it on an optional basis when you specify the backup, restore, or clone operation.

> You must ensure that the plugins directory has the executable permission before using the scripts for the SnapManager operation.

Activity	Backup	Restore	Clone

Preprocessing	<default_installation_directory>\plugins\backup\create\pre	<default_installation_directory>\plugins\restore\create\pre	<default_installation_directory>\plugins\clone\create\pre
Post-processing	<default_installation_directory>\plugins\backup\create\post	<default_installation_directory>\plugins\restore\create\post	<default_installation_directory>\plugins\clone\create\post
Policy-based	<default_installation_directory>\plugins\backup\create\policy	<default_installation_directory>\plugins\restore\create\policy	<default_installation_directory>\plugins\clone\create\policy

Sample scripts locations

The following are some samples of the pretask and post-task scripts for the backup and clone operations available in the installation directory path:

- <default_installation_directory>\plugins\examples\backup\create\pre
- <default_installation_directory>\plugins\examples\backup\create\post
- <default_installation_directory>\plugins\examples\clone\create\pre
- <default_installation_directory>\plugins\examples\clone\create\post

What you can change in the script

If you are creating a new script, you can change only the describe and execute operations. Each script must contain the following variables: context, timeout, and parameter.

The variables you have described in the describe function of the script must be declared at the start of the script. You can add new parameter values in parameter=() and then use the parameters in the execute function.

Sample script

The following is a sample script with a user-specified return code for estimating the space in the SnapManager host:

```
@echo off
REM $Id:
//depot/prod/capstan/Rcapstan_ganges/src/plugins/windows/examples/clone/cr
eate/policy/validate_sid.cmd#1 $
REM $Revision: #1 $ $Date: 2011/12/06 $
REM
REM

set /a EXIT=0

set name="Validate SID"
set description="Validate SID used on the target system"
```

```
set parameter=()

rem reserved system IDs
set INVALID_SIDS=("ADD" "ALL" "AND" "ANY" "ASC" "COM" "DBA" "END" "EPS"
"FOR" "GID" "IBM" "INT" "KEY" "LOG" "MON" "NIX" "NOT" "OFF" "OMS" "RAW"
"ROW" "SAP" "SET" "SGA" "SHG" "SID" "SQL" "SYS" "TMP" "UID" "USR" "VAR")

if /i "%1" == "-check" goto :check
if /i "%1" == "-execute" goto :execute
if /i "%1" == "-describe" goto :describe

:usage:
    echo usage: %0 "{ -check | -describe | -execute }"
    set /a EXIT=99
    goto :exit

:check
    set /a EXIT=0
    goto :exit

:describe
    echo SM_PI_NAME:%name%
    echo SM_PI_DESCRIPTION:%description%
    set /a EXIT=0
    goto :exit

:execute
    set /a EXIT=0

    rem SM_TARGET_SID must be set
    if "%SM_TARGET_SID%" == "" (
        set /a EXIT=4
        echo SM_TARGET_SID not set
        goto :exit
    )

    rem exactly three alphanumeric characters, with starting with a letter
    echo %SM_TARGET_SID% | findstr "\<[a-zA-Z][a-zA-Z0-9][a-zA-Z0-9]\>"
>nul
    if %ERRORLEVEL% == 1 (
        set /a EXIT=4
        echo SID is defined as a 3 digit value starting with a letter.
[%SM_TARGET_SID%] is not valid.
        goto :exit
    )
```

```
    rem not a SAP reserved SID
    echo %INVALID_SIDS% | findstr /i \"%SM_TARGET_SID%\" >nul
    if %ERRORLEVEL% == 0 (
        set /a EXIT=4
        echo SID [%SM_TARGET_SID%] is reserved by SAP
        goto :exit
    )

    goto :exit



:exit
    echo Command complete.
    exit /b %EXIT%
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.