設定DNS伺服器

StorageGRID

NetApp
May 17, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/storagegrid-116/maintain/modifying-dns-configuration-for-single-grid-node.html on May 17, 2022. Always check docs.netapp.com for the latest.

目錄

設定DNS伺服器 1
修改單一網格節點的DNS組態 1

設定DNS伺服器

您可以新增、移除及更新網域名稱系統（DNS）伺服器、以便使用完整網域名稱（FQDN）主機名稱、而非IP位址。

您需要的是 **#8217** ；需要的是什麼

- 您必須使用登入Grid Manager 支援的網頁瀏覽器。
- 您必須具有維護或根存取權限。
- 您必須擁有DNS伺服器的IP位址才能進行設定。

指定DNS伺服器資訊可讓您使用完整網域名稱（FQDN）主機名稱、而非使用IP位址來接收電子郵件或SNMP通知及AutoSupport 進行支援。建議至少指定兩個DNS伺服器。

> 為DNS伺服器提供二到六個IP位址。一般而言、在網路斷線的情況下、選取每個站台可在本機存取的DNS伺服器。這是為了確保isLanded站台繼續存取DNS服務。設定整個網格的DNS伺服器清單之後、您可以 進一步自訂每個節點的DNS伺服器清單。

如果DNS伺服器資訊被省略或設定不正確、則會在每個網格節點的SSM服務上觸發DNST警示。當DNS設定正確、且新的伺服器資訊已到達所有網格節點時、警示就會清除。

步驟

1. 選擇*維護*>*網路*>* DNS伺服器*。
2. 視需要在「伺服器」區段中新增更新或移除DNS伺服器項目。

   最佳做法是每個站台至少指定兩部DNS伺服器。您最多可以指定六個DNS伺服器。

3. 按一下「 * 儲存 * 」。

修改單一網格節點的DNS組態

您可以執行指令碼、針對每個網格節點以不同的方式設定DNS、而非針對整個部署全域設定網域名稱系統（DNS）。

一般而言、您應該使用Grid Manager上的* maintenance **>** Network **>** DNS servers （*維護>*網路*>* DNS伺服器*）選項來設定DNS伺服器。只有當您需要針對不同的網格節點使用不同的DNS伺服器時、才可使用下列指令碼。

1. 登入主要管理節點：
   a. 輸入下列命令：「sh admin@_primary管理節點IP」
   b. 輸入「passwords.txt」檔案中所列的密碼。
   c. 輸入下列命令以切換至root：「u -」
   d. 輸入「passwords.txt」檔案中所列的密碼。

      以root登入時、提示會從「$」變更為「#」。

e. 將SSH私密金鑰新增至SSH代理程式。輸入：「sh-add」

f. 輸入列在「P密碼」檔案中的SSH存取密碼。

2. [Log_in_to節點]使用自訂DNS組態登入您要更新的節點：「sh *norme_ip_address*」

3. 執行DNS設定指令碼：「etup_resolv.rb.」

   指令碼會以支援的命令清單回應。

```
Tool to modify external name servers

available commands:
  add search <domain>
               add a specified domain to search list
               e.g.> add search netapp.com
  remove search <domain>
               remove a specified domain from list
               e.g.> remove search netapp.com
  add nameserver <ip>
               add a specified IP address to the name server list
               e.g.> add nameserver 192.0.2.65
  remove nameserver <ip>
               remove a specified IP address from list
               e.g.> remove nameserver 192.0.2.65
  remove nameserver all
               remove all nameservers from list
  save         write configuration to disk and quit
  abort        quit without saving changes
  help         display this help message


Current list of name servers:
    192.0.2.64
Name servers inherited from global DNS configuration:
    192.0.2.126
    192.0.2.127
Current list of search entries:
    netapp.com

Enter command [`add search <domain>|remove search <domain>|add
nameserver <ip>`]
              [`remove nameserver <ip>|remove nameserver
all|save|abort|help`]
```

4. 新增為您的網路提供網域名稱服務的伺服器的IPV4位址：「add <nameserverip_address>（新增<名稱伺服器IP位址>）」

5. 重複執行「add nameserver'」命令以新增名稱伺服器。
6. 請依照提示輸入其他命令的指示進行。
7. 儲存變更並結束應用程式：「Save（儲存）」
8. [[close _cmd _Shell]關閉伺服器上的命令Shell：「exit」
9. 針對每個網格節點、重複中的步驟 登入節點 透過 關閉命令Shell。
10. 當您不再需要無密碼存取其他伺服器時、請從SSH代理程式移除私密金鑰。輸入：「sh-add -D」

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.