■ NetApp

Change Data Layer

Virtual Desktop Service

NetApp July 20, 2021

This PDF was generated from https://docs.netapp.com/us-en/virtual-desktop-service/Architectural.change_data_layer.Azure_Files.html on July 20, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Redirecting Storage Platform	 	. 1								
Overview	 	. 1								
Redirecting Storage Platform to Azure Files										

Redirecting Storage Platform

Overview

Virtual Desktop Service deployment technologies allow for a variety of storage options depending on the underlying infrastructure, this guide addresses how to make a change post-deployment.


Virtual desktop performance depends on a variety of key resources, storage performance is one of the primary variables. As requirements change and workloads evolve, the need to change the storage infrastructure is a common task. In nearly all cases this involves migrating from a file server platform to NetApp storage technology (such as Azure NetApp Files, NetApp Cloud Volumes Service in Google or NetApp Cloud Volumes ONTAP in AWS) since these technologies typically offer the best performance profile for end user computing environments.

Creating the new storage layer


Due to the wide variety of potential storage services across a wide variety of cloud and HCI infrastructure providers, this guide assumes a new storage service has already been established and with the SMB path(s) known.

Create storage folders

- 1. In the new storage service, create three folders:
 - ∘ /Data
 - /Home
 - · /Pro



- 2. Set Folder Permissions
 - a. On Folder Properties, select Security, >Advanced > Disable Inheritance



b. Adjust the remaining settings to match the settings on the original storage layer as originally created by the deployment automation.

Moving data

The directories, data, files and security settings can be moved a variety of ways. The following robocopy syntax will achieve the necessary changes. The paths need to be changed to match your environment.


```
robocopy c:\data\zucd \\uyy-1c37.deskapps.mobi\zucd-data /xd ~snapshot
/MIR /CopyAll /R:1 /W:1 /tee /log:C:\temp\roboitD.txt
```

Redirecting the SMB path at cutover


When the time for cutover comes, a few changes will redirect all the storage functionality across the VDS environment.

Update GPOs

1. The Users GPO (named <company-code>-users) needs to be updated with the new share path. Select User Configuration > Windows Settings > Preferences > Drive Maps



2. Right Click on *H*:, select Properties > Edit > Action: Replace and enter the new Path



3. With Classic or Hybrid AD update the share defined in ADUC in the company OU. This is reflected in VDS folder management.




Update FSLogix profile paths

1. Open Regedit on the original file server and any other provisioned Session Hosts.




2. Edit the *VHDLocations* value with the new value. This should be the new SMB path plus *pro/profilecontainers* as shown in the screenshot below.



Update the folder redirection settings for the home directories

- 1. Open Group Policy Management, select Users GPO linked to DC=domain,DC=mobi/Cloud Workspace/Cloud Workspace Companies/<company-code>/<company-code>-desktop users.
- 2. Edit folder redirection paths under User Configuration>Policies>Windows Settings>Folder Redirection.
- 3. Only Desktop and Documents needs updated and the paths should match the new SMB path mount point for Home volume.




Update the VDS SQL database with Command Center


CWMGR1 contains a helper utility applications called Command Center which can bulk update the VDS database.

To make the final database updates:

1. Connect to CWMGR1, navigate and run CommandCenter.exe



2. Navigate to the *Operations* tab, click *Load Data* to populate the Company Code drop down, select the company code, and enter the new storage paths(s) for the storage layer then click *Execute Command*.



Redirecting Storage Platform to Azure Files

Overview


Virtual Desktop Service deployment technologies allow for a variety of storage options depending on the underlying infrastructure. This guide addresses how to make a change to using Azure Files post-deployment.

Pre-requisites


- · AD Connect installed and set up
- · Azure global admin account
- AZFilesHybrid PowerShell module https://github.com/Azure-Samples/azure-files-samples/releases
- AZ PowerShell module
- · ActiveDirectory PowerShell module

Create the new storage layer

- 1. Log in to Azure with the global admin account
- 2. Create a new Storage Account in the same location and resource group as the workspace




3. Create the data, home, and pro file shares under the storage account



Set Up Active Directory


Create a new Organization Unit named "Storage Account" under the Cloud Workspace > Cloud Workspace > Service Accounts OU




- 2. Enable AD DS authentication (must be done using PowerShell) https://docs.microsoft.com/en-us/azure/storage/files/storage-files-identity-ad-ds-enable
 - a. DomainAccountType should be "ServiceLogonAccount"
 - b. OraganizationalUnitDistinguishedName is the distinguished name of the OU created in the previous step (ie "OU=Storage Account,OU=Cloud Workspace Service Accounts,OU=Cloud Workspace, DC=TrainingKrisG, DC=onmicrosoft, DC=com")

Set the Roles for the Shares

1. In the Azure portal, give "`Storage File Data SMB Share Elevated Contributor`" role to CloudWorkspaceSVC and Level3 Technicians




2. Give "Storage File Data SMB Share Contributor" role to the "<company code>-all users" group




Create the directories

1. Create a directory in each share (data, home, pro) using the company code as the name (In this example, the company code is "kift")




2. In the <company code> directory of the pro share, create a "ProfileContainers" directory




Set the NTFS Permissions

- 1. Connect to the shares
 - a. Navigate to the share under the storage account in the Azure portal, click the three dots, then click Connect




b. Choose Active Directory for Authentication method and click the Copy to clipboard icon in the lower right corner of the code



- c. Log in to the CWMGR1 server with an account that is a member of the Level3 Technicians group
- d. Run the copied code in PowerShell to map the drive
- e. Do the same for each share while choosing a different drive letter for each


- 2. Disable inheritance on the <company code> directories
- 3. System and the AD Group ClientDHPAccess should have Full Control to the <company code> directories
- 4. Domain Computers should have Full Control to the <company code> directory in the pro share as well as the ProfileContainers directory within
- 5. The <company code>-all users AD group should have List folder/read data permissons to the <company code> directories in the home and pro shares
- 6. The <company code>-all users AD group should have the below Special permissions for the directory in the data share




7. The <company code>-all users AD group should have the Modify permission on the ProfileContainers directory


Update Group Policy Objects

- 1. Update the GPO <company code> users located under Cloud Workspace > Cloud Workspace Companies > <company code> > <company code> desktop users
 - a. Change the Home drive mapping to point the new home share




b. Change the Folder Redirection to point the home share for Desktop and Documents






Update the share in Active Directory Users and Computers

1. With classic or hybrid AD, the share in the company code OU needs to be updated to the new location




Update Data/Home/Pro paths in VDS

- 1. Log in to CWMGR1 with an account in the Level3 Technicians group and launch Command Center
- 2. In the Command drop down, select Change Data/Home/Pro Folders
- 3. Click the Load Data button, then be sure the proper company code is selected from the drop down
- 4. Enter the new patsh for the data, home, and pro locations
- 5. Uncheck the Is Windows Server box
- 6. Click the Execute Command button



Update FSLogix profile paths

- 1. Open registry editory on the session hosts
- 2. Edit the VHDLoccations entry at HKLM\SOFTWARE\FSLogix\Profiles to be the UNC path to the new ProfileContainers directory



Configure Backups

- 1. It is recommended to set up and configure a backup policy for the new shares
- 2. Create a new Recovery Services Vault in the same resource group
- 3. Navigate to the vault and select Backup under Getting Started
- 4. Choose Azure for where the workload is running and Azure file share for what you want to back up then click Backukp
- 5. Select the storage account used to create the shares
- 6. Add the shares to back up
- 7. Edit and Create a backup policy that fits your needs

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.