# 管理OnCommand Workflow Automation功能SSL憑證

OnCommand Workflow Automation 5.1

NetApp
May 03, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/workflow-automation/windows-install/task-replace-the-default-workflow-automation-ssl-certificate.html on May 03, 2022. Always check docs.netapp.com for the latest.

# 目錄

管理OnCommand Workflow Automation 功能SSL憑證 . . . . . 1
取代預設的Workflow Automation SSL憑證 . . . . . 1
建立Workflow Automation的憑證簽署要求 . . . . . 2

# 管理OnCommand Workflow Automation 功能SSL憑證

## 您可以使用OnCommand Workflow Automation 自我簽署的憑證或由憑證授權單位（CA）簽署的憑證來取代預設的WFA（WFA）SSL憑證。

預設的自我簽署WFA SSL憑證會在安裝WFA期間產生。升級時、先前安裝的憑證會被新的憑證取代。如果您使用非預設的自我簽署憑證或由CA簽署的憑證、則必須以憑證取代預設的WFA SSL憑證。

# 取代預設的Workflow Automation SSL憑證

## 如果憑證已過期、或您想要延長憑證的有效期間、您可以取代預設的Workflow Automation（WFA）SSL憑證。

您必須在WFA伺服器上擁有Windows管理員權限。

此程序使用預設的WFA安裝路徑。如果您在安裝期間變更了預設位置、則必須使用自訂的WFA安裝路徑。

步驟

1. 以管理使用者身分登入WFA主機機器。
2. 使用Windows服務主控台停止下列WFA服務：
   - NetApp WFA資料庫
   - NetApp WFA伺服器
3. 從下列位置刪除WFA-keystore檔案：

   「<wfa_install_location >\wfa\jboss\s獨立 式\configuration \keystore」

4. 在WFA伺服器上開啟命令提示字元、並將目錄變更為下列位置：<OpenJDK_install_LOD>\bin
5. 取得資料庫金鑰：

   「keytool-keysize 2048-genkey -alias "SSL Keystore」-keyalg RSA -keystore「<wfa_install_location ）>\wfa\jboss\s獨立 式\configuration \keystore \wfa.keystore」-validity xxxx'

   XXXX是新憑證有效日期的天數。

6. 出現提示時、請提供密碼（預設或新的）。

   changeit是預設密碼。如果您不想使用預設密碼、則必須從下列位置變更standalone-full.xml檔案中SSL元素的密碼屬性：<WFA_install_location>\WFA\jboss\s獨立\組態\

   ```
   <ssl name="ssl" password="new_password" certificate-key-
   file="${jboss.server.config.dir}/keystore/wfa.keystore"
   ```

7. 輸入憑證的必要詳細資料。

8. 檢閱顯示的資訊、然後輸入「Yes（是）」。
9. 出現下列訊息時、請按* Enter *鍵：輸入<SSL Keystore（<SSL Keystore）>的金鑰密碼（如果與Keystore密碼相同則返回）>。
10. 使用Windows服務主控台重新啟動WFA服務。

# 建立Workflow Automation的憑證簽署要求

## 您可以在Windows中建立憑證簽署要求（CSR）、以便使用由憑證授權單位（CA）簽署的SSL憑證、而非Workflow Automation（WFA）的預設SSL憑證。

- 您必須在WFA伺服器上擁有Windows管理員權限。
- 您必須更換WFA提供的預設SSL憑證。

此程序使用預設的WFA安裝路徑。如果您在安裝期間變更了預設路徑、則必須使用自訂的WFA安裝路徑。

步驟

1. 以管理使用者身分登入WFA主機機器。
2. 在WFA伺服器上開啟命令提示字元、然後將目錄變更為下列位置：+<OpenJDK_install_location>\bin
3. 建立CSR：

   「keytool-certreq -keystore wfa_install_location \wfa\jboss\s獨立 式\configuration \keystore \wfa.keystore -alias "SSL keystore」-file C：\file_name.csr

   file_name是CSR檔案的名稱。

4. 出現提示時、請提供密碼（預設或新的）。

   changeit是預設密碼。如果您不想使用預設密碼、則必須從WFA_install_location \WFA \jboss\s獨立\組態\位置、變更standalone-full.xml檔案中SSL元素的密碼屬性。

   ```
   <ssl name="ssl" password="new_password" certificate-key-
   file="${jboss.server.config.dir}/keystore/wfa.keystore"
   ```

5. 將file_name.csr檔案傳送至CA以取得簽署的憑證。

   如需詳細資料、請參閱CA網站。

6. 從CA下載鏈結憑證、然後將鏈結憑證匯入至Keystore：「keytool-import -alias "SSL keystore CA certe"-keystore「wfa_install_portion\wfa\jboss\s獨立 式\configuration \keystore \wfa.keystore」-cacerts -file C：\chlune_cert.cer

   C：\chain /cert.cer是從CA接收的鏈結憑證檔案。檔案必須為X・509格式。

7. 匯入您從CA收到的已簽署憑證：

   「keytool-import-alias "SSL Keystore」-keystore「wfa_install_portion\wfa\jbjboss\s獨立 式\configuration \keystore \wfa.keystore」-file C：\Certificate .cer

C：\Certificate .cer是從CA接收的鏈結憑證檔案。

8. 啟動下列WFA服務：
   - NetApp WFA資料庫
   - NetApp WFA伺服器

**Copyright Information**

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

**Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.