

NEUROKORE

Tester Feedback

Compiled 2026-08-16 · Sources: Google Sheet, existing one-page dump, screenshots, WhatsApp notes, routing spec.

This file replaces the unreadable single-page dump. Original wording is kept. Status is against 0.4.4 / 0.4.5-alpha.

1. Sources

Google Sheet: <https://docs.google.com/spreadsheets/d/1h563IKFO4HYXzPjPXmb3i6-MfG5yKxGL1WGqjKhIOE0>

Existing dump: feedback/NeuroKore Feedback.pdf (one page, text too small).

Local media: feedback/ screenshots + WhatsApp videos; screenshots/ board captures.

Routing spec: tester text 2026-08-16 plus Screenshot 204457 (wrap-in-gutter).

2. Sheet - UI

What	Reality	Expected	Status
Functions / Stages / Settings	Opens all windows on top of each other	Close the previous one; only the current visible. Second click closes.	Done 0.4.4 exclusive overlay + toggle
Help / User Manual	Only via Settings	Button in the top bar with ?	Done 0.4.4 ? in toolbar
Bottom info bar moving around	Studio/Live offset OK; Buffer, BPM, HOST, OS jump	Everything has its own space. Videos: BottomBarMoving.mp4	Partial: brighter footer, less squash. Fixed slots still open.
Hover then bottom bar	Repeats last hover info; empty if nothing hovered first	Don't show anything. Video: HoverBottomBar.mp4	Open - footer still one label
Mix UI	Cut off	Not cut off	Done 0.4.4 Mix % min width
Mix percentage	4 digits after the dot	1 or 2 decimals	Done - integer percent
Right-click a node	Opens the node editor	Menu: delete, duplicate, etc. Double-click = settings (already)	Done 0.4.4
Adding a new node	Always links into the existing path	On a line = insert on that cable. Empty space = not connected.	Partial: cable splice works. Empty space still joins the chain.
Connections	Hard to see where they land	Short stub away from the jack before any turn	Done - east/west stubs + wrap gutter
Knob host menu	Own menu only	VST3 host menu like Melda, then our items	Done 0.4.4
Hard to read texts	Grey on black, tiny at 125% host scale	Also white text maybe. Snap setting unreadable.	Partial: brighter footer/labels. Scale still needs work.
Routing	If something is connected to the output, no way to change it	Change routing by hand	Partial: grab cable to unplug. OUT jacks still awkward.
IR Preview	No preview play button	Play the IR	Done 0.4.4 Play mixes a short quiet preview
Misaligned UI	Functions title and X feel off-centre	Centered	Done 0.4.4 overlay title centered

3. Sheet - Function lookup, shortcuts, nodes


What	Reality	Expected	Status
Functions / Stages / Settings click again	Opens, lights up, does not close	Toggle closed when already open	Done 0.4.4
Functions	No copy button	Copy as well as insert at caret	Done 0.4.4 Copy
Functions > Nodes	Missing	Look up nodes: what they do, jacks, args	Done 0.4.4 Nodes category
Functions I/O animation	Octaver, widen, vocoder all look like OTT	Only show I/O where it matters. Distinct glyphs.	Partial: Nodes text distinguishes them. Shared plot still generic.
CTRL+Z	Does not undo positioning	Undo chip moves	Done 0.4.4 layout-only undo
XOVER	Creates weird artifacts	No clicks / zipper	Partial: slower coeff updates

Node visual at host scale != 100%	Misaligned	Stay aligned	Open
Moving nodes	Forces path recalculation / playback artifact	Do nothing if nothing in the graph changed	Done 0.4.4 layout-only setFormula
Plugin CPU	~12% with nothing happening	Smart idle if no input - do not kill the next transient	Partial: backdrop skips when Motion=Off or silent. DSP stays warm.
Crash	Save on British Plexi Bark after validate	Never crash	Done 0.4.4 SafePointer + icon bounds
British Plexi Bark copy	How it sounds: ... no Marshall name.	Sounds like an AI prompt leak; has the Marshall name anyway	Done 0.4.4 copy rewritten
Min/Max	Random numbers bottom left/right	Label MIN / MAX	Done 0.4.4

4. Feature request - Stages Window

From the original PDF (the sheet row was empty in CSV export):
Should have a way to re-order the stages, so you can click on one, move/position with arrow keys or a button, or drag and drop. That would add another layer of patch feeling.
Status: OPEN. Not built. Circuit already lets you drag chips; this asks for an ordered stage list as well.

5. Screenshots - board and chrome




183757 - MS ENC/DEC labels on pins, OUT in the middle, knob cables stacked, chips overlapping the story. Fixed in 0.4.4 (title row, no overlap, OUT to the right, curved knobs).



174608 - cables must enter jacks orthogonally, never diagonally through DRIVE.




180407 - no mini stair-jogs on LFO/IN traces. Horizontal stub before any turn.



204457 - RULE for a wrap between two stacked chips: leave the right jack, run in the gutter, enter the left jack. Not through the body.



161455 - earlier board capture (reference).



161727 - earlier board capture (reference).

6. WhatsApp / scale (feedback/)


there is a snap setting, but I can't really read it.

try 125% scaling for main gui - footer 48000 BUF 2048 BPM 130.0 HOST is tiny.


NK lockup / version string extremely small, super hard to read.

animations settings apply when after the window was closed, I would expect directly.


Status: motion-live done 0.4.4. Readability at 125% host scale still OPEN.



163548 - Playback FFT / Heavy Audio Filter style reference (jacks + labels).



163606 - WhatsApp: Snap + 125% footer unreadable.



163630 - WhatsApp: motion should apply while Settings is still open.

7. Routing rules (binding)

7.1 Grid and alignment

The whole board is a fixed 16 px grid. Every port and every wire segment snaps to that grid. Jacks sit on the grid line of their row (not the cell centre). Opposite chips share jack Y if they share the same slot.

7.2 Obstacle avoidance

Each module registers its outer box as blocked cells. The router must not walk through those cells.

7.3 Ports

Every wire leaves a port in a straight line for a fixed number of grid cells (one cell stub). The first turn is only allowed after that stub. Outputs face +X, inputs face -X.

7.4 Cost function

Only axis-aligned moves (X or Y). Each bend gets a high penalty so the path prefers long straight runs. The chosen path is the cheapest mix of distance and turns.

7.5 Channel routing

A segment marks its cells used. Another signal in the same direction takes the next free parallel track. Crossings only at exact 90 degrees.

7.6 Signal flow and layout

IN has the lowest rank, far left. OUT has the highest rank, far right. Nodes in between sit in columns by their connections. Reading order: top-left, left-to-right, then the next row, until OUT bottom-right.

7.7 Wrap between two rows (Screenshot 204457)

When the next block is on the row below: stub east out of the upper-right jack, drop into the gutter BETWEEN the two chips, run left in that gutter, enter the lower-left jack from the west. Never route through a chip body. Row gap is 32 px so a grid line exists in the gutter.

7.8 Bus splits and multi-target

A bus / bundled mix uses a thicker stroke (and mix/bus ports are squares). A splitter turns the thick line into thin singles. If one output feeds several destinations, one line leaves the port and branches at the first free grid point. If several cables share one input, they merge one cell before the plug and enter as one line.

7.9 Fold / expand

A module has two fixed bounding boxes. Folding or expanding changes the obstacle and the whole grid must be routed again. Inner wires of an expanded module stay in their own coordinates and do not pollute the outer grid.

7.10 Module size and port shapes

Chips were too wide (208 px). Compact width is 144 px so horizontal runs stay short. Audio singles = circles. Ports that can take several cables (mix / OUT) = squares.

8. Videos (not embedded)

feedback/WhatsApp Video 2026-08-16 at 16.23.30.mp4 - BottomBarMoving / hover footer.

feedback/WhatsApp Video 2026-08-16 at 16.32.37.mp4 - Settings motion / scale.

9. Still open after 0.4.4 / 0.4.5

1. Footer as real fixed slots (not one shrinking label). Hover must not rewrite the strip.
2. Empty-space add-node stays disconnected.
3. Functions plot glyphs: OTT != widen != octaver != vocoder.
4. Host scale 125%: snap setting, lockup, footer type size.
5. Stages Window reorder list (arrow keys / drag).
6. Idle CPU: backdrop only - do not sleep the DSP.
7. Verify wrap-gutter + 144 px chips in the DAW on 0.4.5.

End of compiled feedback. Keep this file in feedback/ and treat the sheet + this PDF as the source of truth.