## CLIENT CONFIG REFERENCE

client acl type

**Description:** Set the ACL type. Currently, only possible value is "posix\_acl" to enable POSIX ACL, or an empty

string. This option only takes effect when the fuse default permissions is set to false.

**Type:** String

**Default:** "" (no ACL enforcement)

client cache mid

Description: Set client cache midpoint. The midpoint splits the least recently used lists into a hot and warm list.

Type: Float 0.75

client cache size

**Description:** Set the number of inodes that the client keeps in the metadata cache.

Type: Integer Default: 16384

client caps release delay

**Description:** Set the delay between capability releases in seconds. The delay sets how many seconds a client waits

to release capabilities that it no longer needs in case the capabilities are needed for another user space

operation.

Type: Integer

Default: 5 (seconds)

client debug force sync read

**Description:** If set to true, clients read data directly from OSDs instead of using a local page cache.

Type: Boolean Default: false

client dirsize rbytes

**Description:** If set to true, use the recursive size of a directory (that is, total of all descendants).

Type: Boolean Default: true

client max inline size

Description: Set the maximum size of inlined data stored in a file inode rather than in a separate data object in

RADOS. This setting only applies if the inline\_data flag is set on the MDS map.

Type: Integer Default: 4096

client metadata

**Description:** Comma-delimited strings for client metadata sent to each MDS, in addition to the automatically

generated version, host name, and other metadata.

Type: String

**Default:** "" (no additional metadata)

client mount gid

**Description:** Set the group ID of CephFS mount.

Type: Integer
Default: -1

**Description:** Set the timeout for CephFS mount in seconds.

Type: Float 300.0

client mount uid

**Description:** Set the user ID of CephFS mount.

Type: Integer
Default: -1

client mountpoint

Description: Directory to mount on the CephFS file system. An alternative to the -r option of the ceph-fuse

command.

Type: String
Default: "/"

client oc

**Description:** Enable object caching.

Type: Boolean Default: true

client oc max dirty

**Description:** Set the maximum number of dirty bytes in the object cache.

**Type:** Integer

**Default:** 104857600 (100MB)

client oc max dirty age

**Description:** Set the maximum age in seconds of dirty data in the object cache before writeback.

**Type:** Float

**Default:** 5.0 (seconds)

client oc max objects

**Description:** Set the maximum number of objects in the object cache.

Type: Integer Default: 1000

client oc size

**Description:** Set how many bytes of data will the client cache.

Type: Integer

**Default:** 209715200 (200 MB)

client oc target dirty

**Description:** Set the target size of dirty data. We recommend to keep this number low.

**Type:** Integer

**Default:** 8388608 (8MB)

client permissions

**Description:** Check client permissions on all I/O operations.

Type: Boolean Default: true

client quota

**Description:** Enable client quota checking if set to true.

Type: Boolean Default: true client quota df

**Description:** Report root directory quota for the statfs operation.

Type: Boolea Default: true

client readahead max bytes

Description: Set the maximum number of bytes that the client reads ahead for future read operations. Overridden

by the client readahead max periods setting.

Type: Integer

Default: 0 (unlimited)

client readahead max periods

Description: Set the number of file layout periods (object size \* number of stripes) that the client reads ahead.

Overrides the client readahead max bytes setting.

Type: Integer
Default: 4

client readahead min

**Description:** Set the minimum number bytes that the client reads ahead.

**Type:** Integer

**Default:** 131072 (128KB)

client reconnect stale

**Description:** Automatically reconnect stale session.

Type: Boolean Default: false

client snapdir

**Description:** Set the snapshot directory name.

Type: String
Default: ".snap"

client tick interval

**Description:** Set the interval in seconds between capability renewal and other upkeep.

Type: Float

**Default:** 1.0 (seconds)

client use random mds

**Description:** Choose random MDS for each request.

Type: Boolean Default: false

fuse default permissions

**Description:** When set to false, ceph-fuse utility checks does its own permissions checking, instead of relying on

the permissions enforcement in FUSE. Set to false together with the client acl type=posix\_acl

option to enable POSIX ACL.

Type: Boolean Default: true

## **DEVELOPER OPTIONS**

Important: These options are internal. They are listed here only to complete the list of options.

**Description:** Check if the reply from the MDS contains required capabilities.

**Type:** Boolean **Default:** false

client debug inject tick delay

**Description:** Add artificial delay between client ticks.

Type: Integer Default: 0

client inject fixed oldest tid

**Description:** 

Type: Boolean Default: false

client inject release failure

**Description:** 

Type: Boolean Default: false

client trace

**Description:** The path to the trace file for all file operations. The output is designed to be used by the Ceph synthetic

client.

**Type:** String

**Default:** "" (disabled)