## MOUNT CEPH FS IN YOUR FILE SYSTEMS TABLE

If you mount Ceph FS in your file systems table, the Ceph file system will mount automatically on startup.

## **KERNEL DRIVER**

To mount Ceph FS in your file systems table as a kernel driver, add the following to /etc/fstab:

For example:

```
10.10.10.10:6789:/ /mnt/ceph ceph name=admin,secretfile=/etc/ceph/secret.key,noatim
```

**Important:** The name and secret or secretfile options are mandatory when you have Ceph authentication running.

See User Management for details.

## **FUSE**

To mount Ceph FS in your file systems table as a filesystem in user space, add the following to /etc/fstab:

For example:

```
none /mnt/ceph fuse.ceph ceph.id=myuser,_netdev,defaults 0 0
none /mnt/ceph fuse.ceph ceph.id=myuser,ceph.conf=/etc/ceph/foo.conf,_netdev,defaults 0
```

Ensure you use the ID (e.g., admin, not client.admin). You can pass any valid ceph-fuse option to the command line this way.

See User Management for details.