CEPHX CONFIG REFERENCE

To identify users and protect against man-in-the-middle attacks, Ceph provides its cephx authentication system to authenticate users and daemons. See Ceph Authentication & Authorization for an introduction to cephx authentication. See the Cephx Guide for details on enabling/disabling, creating users and setting user capabilities.

ENABLE/DISABLE AUTHENTICATION

Depending on the version, Ceph either enables or disables authentication by default. Use the following settings to expressly enable or disable Ceph. See Ceph Authentication for additional details.

Authentication Enablement Defaults

Ceph version 0.54 and earlier versions disable authentication by default. If you want to use Ceph authentication, you must specifically enable it for version 0.54 and earlier versions.

Ceph version 0.55 and later version enable authentication by default. If you do not want to use Ceph authentication, you must specifically disable it for versions 0.55 and later versions.

Authentication Granularity

Ceph version 0.50 and earlier versions use auth supported to enable or disable authentication between the Ceph Client and the Ceph Storage Cluster. Ceph authentication in earlier versions only authenticates users sending message traffic between the client and the cluster, so it does not have fine-grained control.

Ceph version 0.51 and later versions use fine-grained control, which allows you to require authentication of the client by the cluster (auth service required), authentication of the cluster by the client (auth client required), and authentication of a daemon within the cluster by another daemon within the cluster (auth cluster required).

auth supported

Deprecated since version 0.51.

Description: Indicates whether to use authentication. If not specified, it defaults to none, which means it is disabled.

Type: String
Required: No
Default: none

auth cluster required

New in version 0.51.

Description: If enabled, the Ceph Storage Cluster daemons (i.e., ceph-mon, ceph-osd, and ceph-mds) must authenticate

with each other. Valid settings are cephx or none.

Type: String Required: No

Default: Version 0.54 and earlier none. Version 0.55 and later cephx.

auth service required

New in version 0.51.

Description: If enabled, the Ceph Storage Cluster daemons require Ceph Clients to authenticate with the Ceph Storage

Cluster in order to access Ceph services. Valid settings are cephx or none.

Type: String Required: No

Default: Version 0.54 and earlier none. Version 0.55 and later cephx.

auth client required

New in version 0.51.

Description: If enabled, the Ceph Client requires the Ceph Storage Cluster to authenticate with the Ceph Client. Valid

settings are cephx or none.

Type: String Required: No

Default: Version 0.54 and earlier none. Version 0.55 and later cephx.

KEYS

When you run Ceph with authentication enabled, ceph administrative commands and Ceph Clients require authentication keys to access the Ceph Storage Cluster.

The most common way to provide these keys to the ceph administrative commands and clients is to include a Ceph keyring under the /etc/ceph directory. For Cuttlefish and later releases using ceph-deploy, the filename is usually ceph.client.admin.keyring (or \$cluster.client.admin.keyring). If you include the keyring under the /etc/ceph directory, you don't need to specify a keyring entry in your Ceph configuration file.

We recommend copying the Ceph Storage Cluster's keyring file to nodes where you will run administrative commands, because it contains the client.admin key.

You may use ceph-deploy admin to perform this task. See Create an Admin Host for details. To perform this step manually, execute the following:

sudo scp {user}@{ceph-cluster-host}:/etc/ceph/ceph.client.admin.keyring /etc/ceph/ceph.client.admir

Tip: Ensure the ceph.keyring file has appropriate permissions set (e.g., chmod 644) on your client machine.

You may specify the key itself in the Ceph configuration file using the key setting (not recommended), or a path to a keyfile using the keyfile setting.

keyring

Description: The path to the keyring file.

Type: String Required: No

Default: /etc/ceph/\$cluster.\$name.keyring,/etc/ceph/\$cluster.keyring,/etc/ceph/keyring.bin

keyfile

Description: The path to a key file (i.e,. a file containing only the key).

Type: String
Required: No
Default: None

key

Description: The key (i.e., the text string of the key itself). Not recommended.

Type: String
Required: No
Default: None

SIGNATURES

In Ceph Bobtail and subsequent versions, we prefer that Ceph authenticate all ongoing messages between the entities using the session key set up for that initial authentication. However, Argonaut and earlier Ceph daemons do not know how to perform ongoing message authentication. To maintain backward compatibility (e.g., running both Botbail and Argonaut daemons in the same cluster), message signing is **off** by default. If you are running Bobtail or later daemons exclusively, configure Ceph to require signatures.

Like other parts of Ceph authentication, Ceph provides fine-grained control so you can enable/disable signatures for service messages between the client and Ceph, and you can enable/disable signatures for messages between Ceph daemons.

ceph require signatures

Description: If set to true, Ceph requires signatures on all message traffic between the Ceph Client and the Ceph Storage

Cluster, and between daemons comprising the Ceph Storage Cluster.

Type: Boolean
Required: No
Default: false

cepxh cluster require signatures

Description: If set to true, Ceph requires signatures on all message traffic between Ceph daemons comprising the Ceph

Storage Cluster.

Type: Boolean Required: No Default: false

cepxh service require signatures

Description: If set to true, Ceph requires signatures on all message traffic between Ceph Clients and the Ceph Storage

Cluster.

Type: Boolean Required: No Default: false

cephx sign messages

Description: If the Ceph version supports message signing, Ceph will sign all messages so they cannot be spoofed.

Type: Boolean Default: true

TIME TO LIVE

auth service ticket ttl

Description: When the Ceph Storage Cluster sends a Ceph Client a ticket for authentication, the Ceph Storage Cluster

assigns the ticket a time to live.

Type: Double Default: 60*60