RADOS GATEWAY CONFIGURATION REFERENCE

The following settings may added to the ceph.conf file under the [client.radosgw.gateway] section. The settings may contain default values. If you do not specify each setting in ceph.conf, the default value will be set automatically.

rgw data

Description: Sets the location of the data files for RADOS Gateway.

Type: String

Default: /var/lib/ceph/radosgw/\$cluster-\$id

rgw cache enabled

Description: Whether the RADOS Gateway cache is enabled.

Type: Boolean Default: true

rgw cache lru size

Description: The number of entries in the RADOS Gateway cache.

Type: Integer Default: 10000

rgw socket path

Description: The socket path for the domain socket. FastCgiExternalServer uses this socket. If you do not specify

a socket path, RADOS Gateway will not run as an external server. The path you specify here must be

the same as the path specified in the rgw.conf file.

Type: String
Default: N/A

rgw dns name

Description: The DNS name of the served domain.

Type: String **Default:** None

rgw swift url

Description: The URL for the RADOS Gateway Swift API.

Type: String
Default: None

rgw swift url prefix

Description: The URL prefix for the Swift API.

Default: swift

Example: http://fqdn.com/swift

rgw enforce swift acls

Description: Enforces the Swift Access Control List (ACL) settings.

Type: Boolean Default: true

rgw print continue

Description: Enable 100-continue if it is operational.

Type: Boolean Default: true Description: The remote address parameter. For example, the HTTP field containing the remote address, or the X-

Forwarded-For address if a reverse proxy is operational.

Type: String

Default: REMOTE ADDR

rgw op thread timeout

Description: The timeout in seconds for open threads.

Type: Integer Default: 600

rgw op thread suicide timeout

Description: The time timeout in seconds before a RADOS Gateway process dies. Disbled if set to 0.

Type: Integer
Default: 0

rgw thread pool size

Description: The size of the thread pool.

Type: Integer **Default:** 100 threads.

rgw num control oids

Description: The number of notification objects used for cache synchronization between different rgw instances.

Type: Integer
Default: 8

rgw log nonexistent bucket

Description: Enables RADOS Gateway to log a request for a non-existent bucket.

Type: Boolean **Default:** false

rgw log object name

Description: The logging format for an object name. See manpage *date* for details about format specifiers.

Type: Date

Default: %Y-%m-%d-%H-%i-%n

rgw log object name utc

Description: Whether a logged object name includes a UTC time. If false, it uses the local time.

Type: Boolean Default: false

rgw usage max shards

Description: The maximum number of shards for usage logging.

Type: Integer Default: 32

rgw usage max user shards

Description: The maximum number of shards used for a single user's usage logging.

Type: Integer

Default: 1

rgw enable ops log

Description: Enable logging for RGW operations.

Type: Boolean

Default: false

rgw enable usage log

Description: Enable the usage log.

Type: Boolean **Default:** false

rgw usage log flush threshold

Description: The number of dirty merged entries in the usage log before flushing synchronously.

Type: Integer Default: 1024

rgw usage log tick interval

Description: Flush pending usage log data every n seconds.

Type: Integer Default: 30

rgw intent log object name

Description: The logging format for the intent log object name. See manpage *date* for details about format

specifiers.

Type: Date

Default: %Y-%m-%d-%i-%n

rgw intent log object name utc

Description: Whether the intent log object name includes a UTC time. If false, it uses the local time.

Type: Boolea Default: false

rgw init timeout

Description: The number of seconds before RGW gives up on initialization.

Type: Integer
Default: 30

rgw mime types file

Description: The path and location of the MIME types. Used for Swift auto-detection of object types.

Type: String

Default: /etc/mime.types

rgw resolve cname

Description: Whether rgw should use DNS CNAME record of the request hostname field (if hostname is not equal to

rgw dns name).

Type: Boolean **Default:** false

rgw enable ops log

Description: Whether rgw will log each successful operation

Type: Boolean Default: true

rgw ops log rados

Description: Whether rgw operations logging should be written into the RADOS backend.

Type: Boolean Default: true

rgw ops log socket path

Description: The path of a UNIX domain socket to which operations logging data will be written.

Type: String
Default: N/A

rgw ops log data backlog

Description: Total backlog data size for UNIX domain socket operations logging.

Type: Integer

Default: 5ul << 20

rgw extended http attrs

Description: Add new set of attributes that could be set on an object. These extra attributes can be set through HTTP

header fields when putting the objects. If set, these attributes will return as HTTP fields when doing

GET/HEAD on the object.

Type: String
Default: N/A

Example: "content_foo, content_bar"

rgw cluster root pool

Description: RADOS pool to store radosgw metadata for this instance.

Type: String Required: No

Default: .rgw.root

rgw gc max objs

Description: Number of objects to collect garbage collection data.

Type: 32-bit Integer

Default: 32

rgw gc obj min wait

Description: Minimum time to wait before object's removal and its processing by the garbage collector.

Type: 32-bit Integer

Default: 2 hours. 2*60*60

rgw gc processor max time

Description: Max time for a single garbage collection process run.

Type: 32-bit Integer

Default: 1 hour. 60*60

rgw gc processor max period

Description: Max time between the beginning of two consecutive garbage collection processes run.

Type: 32-bit Integer

Default: 1 hour. 60*60