Class 5 – Logistic Regression

Classification

Pedram Jahangiry

Fall 2019

Jon M. Huntsman School of Business
Utah State University

Credit Card Default



Can we use linear probability model (LPM)?

Suppose for the `Default` classification task that we code

$$Y = \begin{cases} 0 & \text{if } \texttt{No} \\ 1 & \text{if } \texttt{Yes}. \end{cases}$$

Can we simply perform a linear regression of Y on X and classify as `Yes` if $\hat{Y} > 0.5$?

- Since in the population $E(Y|X = x) = \Pr(Y = 1|X = x)$, we might think that regression is perfect for this task.
- However, *linear* regression might produce probabilities less than zero or bigger than one. *Logistic regression* is more appropriate.

Linear versus Logistic Regression



The orange marks indicate the response Y, either 0 or 1. Linear regression does not estimate $\Pr(Y = 1|X)$ well. Logistic regression seems well suited to the task.

Sigmoid Function

The Sigmoid (aka Logistic) function has a range of [0,1]





Logistic Regression

Let's write $p(X) = \Pr(Y = 1|X)$ for short and consider using `balance` to predict `default`. Logistic regression uses the form

$$p(X) = \frac{e^{\beta_0+\beta_1 X}}{1 + e^{\beta_0+\beta_1 X}}.$$

($e \approx 2.71828$ is a mathematical constant [Euler's number.])
It is easy to see that no matter what values β_0, β_1 or X take, $p(X)$ will have values between 0 and 1.

Logistic Regression (cont'd)

$$p(X) = \frac{e^{\beta_0+\beta_1 X}}{1+e^{\beta_0+\beta_1 X}}.$$

A bit of rearrangement gives

$$\log\left(\frac{p(X)}{1-p(X)}\right) = \beta_0 + \beta_1 X.$$

This monotone transformation is called the *log odds* or *logit* transformation of $p(X)$. (by log we mean *natural log*: ln.)

Logistic regression ensures that our estimate for p(X) lies between 0 and 1.

Logistic regression is very popular for classification, especially when K = 2

Maximum Likelihood

We use maximum likelihood to estimate the parameters.

$$\ell(\beta_0, \beta) = \prod_{i:y_i=1} p(x_i) \prod_{i:y_i=0} (1 - p(x_i)).$$

This *likelihood* gives the probability of the observed zeros and ones in the data. We pick β_0 and β_1 to maximize the likelihood of the observed data.

Most statistical packages can fit linear logistic regression models by maximum likelihood. In `R` we use the `glm` function.

	Coefficient	Std. Error	Z-statistic	P-value
`Intercept`	-10.6513	0.3612	-29.5	< 0.0001
`balance`	0.0055	0.0002	24.9	< 0.0001

Predictions

What is our estimated probability of `default` for someone with a balance of \$1000?

$$\hat{p}(X) = \frac{e^{\hat{\beta}_0+\hat{\beta}_1 X}}{1+e^{\hat{\beta}_0+\hat{\beta}_1 X}} = \frac{e^{-10.6513+0.0055\times 1000}}{1+e^{-10.6513+0.0055\times 1000}} = 0.006$$

With a balance of \$2000?

$$\hat{p}(X) = \frac{e^{\hat{\beta}_0+\hat{\beta}_1 X}}{1+e^{\hat{\beta}_0+\hat{\beta}_1 X}} = \frac{e^{-10.6513+0.0055\times 2000}}{1+e^{-10.6513+0.0055\times 2000}} = 0.586$$

Other measures

<table>
<tr><td colspan="2"></td><td colspan="2">True condition</td><td colspan="3"></td></tr>
<tr><td></td><td>Total population</td><td>Condition positive</td><td>Condition negative</td><td>Prevalence $= \frac{\Sigma \text{ Condition positive}}{\Sigma \text{ Total population}}$</td><td colspan="2">Accuracy (ACC) = $\frac{\Sigma \text{ True positive} + \Sigma \text{ True negative}}{\Sigma \text{ Total population}}$</td></tr>
<tr><td rowspan="2">Predicted condition</td><td>Predicted condition positive</td><td>True positive</td><td>False positive, Type I error</td><td>Positive predictive value (PPV), Precision = $\frac{\Sigma \text{ True positive}}{\Sigma \text{ Predicted condition positive}}$</td><td colspan="2">False discovery rate (FDR) = $\frac{\Sigma \text{ False positive}}{\Sigma \text{ Predicted condition positive}}$</td></tr>
<tr><td>Predicted condition negative</td><td>False negative, Type II error</td><td>True negative</td><td>False omission rate (FOR) = $\frac{\Sigma \text{ False negative}}{\Sigma \text{ Predicted condition negative}}$</td><td colspan="2">Negative predictive value (NPV) = $\frac{\Sigma \text{ True negative}}{\Sigma \text{ Predicted condition negative}}$</td></tr>
<tr><td colspan="2" rowspan="2"></td><td>True positive rate (TPR), Recall, Sensitivity, probability of detection, Power = $\frac{\Sigma \text{ True positive}}{\Sigma \text{ Condition positive}}$</td><td>False positive rate (FPR), Fall-out, probability of false alarm $= \frac{\Sigma \text{ False positive}}{\Sigma \text{ Condition negative}}$</td><td>Positive likelihood ratio (LR+) $= \frac{\text{TPR}}{\text{FPR}}$</td><td rowspan="2">Diagnostic odds ratio (DOR) $= \frac{\text{LR+}}{\text{LR−}}$</td><td rowspan="2">$F_1$ score = $2 \cdot \frac{\text{Precision} \cdot \text{Recall}}{\text{Precision} + \text{Recall}}$</td></tr>
<tr><td>False negative rate (FNR), Miss rate $= \frac{\Sigma \text{ False negative}}{\Sigma \text{ Condition positive}}$</td><td>Specificity (SPC), Selectivity, True negative rate (TNR) $= \frac{\Sigma \text{ True negative}}{\Sigma \text{ Condition negative}}$</td><td>Negative likelihood ratio (LR−) $= \frac{\text{FNR}}{\text{TNR}}$</td></tr>
</table>

Types of errors