# Single Character Input

## Single-Character Input and Irvine32 Keyboard Procedures

In console mode on MS-Windows, handling single-character input involves dealing with the keyboard device driver, scan codes, virtual-key codes, and the message queue. Here's an explanation of the process and the relevant Irvine32 keyboard procedures:

#### **Keyboard Input Process:**

MS-Windows provides a device driver for the installed keyboard. When a key is pressed, it sends an 8-bit scan code to the computer's keyboard port.

Upon releasing the key, a second scan code is transmitted. MS-Windows translates these scan codes into 16-bit virtual-key codes, which are device-independent values that identify the key's purpose.

A message containing the scan code, virtual-key code, and related information is created by MS-Windows and placed in the message queue.

The message eventually reaches the currently executing program thread, identified by the console input handle.

## <u>Irvine32 Keyboard Procedures:</u>

The Irvine32 library provides two related procedures for handling keyboard input: ReadChar and ReadKey.

**ReadChar** waits for an ASCII character to be typed at the keyboard and returns the character in the AL register.

**ReadKey** performs a no-wait keyboard check. If no key is waiting in the console input buffer, it sets the Zero flag.

If a key is found, the Zero flag is clear, and AL contains either zero or an ASCII code. The upper halves of EAX and EDX are overwritten.

# Using ReadKey and Control Key State:

In ReadKey, if AL contains zero, the user may have pressed a special key (e.g., function key, cursor arrow).

AH register contains the keyboard scan code, which can be matched to a list of keyboard keys. DX contains the virtual-key code.

EBX contains state information about the states of the keyboard control keys.

#### <u>Control Key State Values:</u>

- CAPSLOCK ON: The CAPS LOCK light is on.
- ENHANCED KEY: The key is enhanced.
- LEFT\_ALT\_PRESSED: The left ALT key is pressed. LEFT\_CTRL\_PRESSED: The left CTRL key is pressed.
- NUMLOCK\_ON: The NUM LOCK light is on.
- RIGHT\_ALT\_PRESSED: The right ALT key is pressed.
- RIGHT\_CTRL\_PRESSED: The right CTRL key is pressed.
- SCROLLLOCK\_ON: The SCROLL LOCK light is on.
- SHIFT\_PRESSED: The SHIFT key is pressed.

You can use these control key state values to determine the state of control keys while processing keyboard input.

The **ReadChar** and **ReadKey** procedures in the Irvine32 library simplify handling keyboard input in your assembly programs, making it easier to respond to user interactions.

# Testing Keyboard Input with ReadKey and GetKeyState

This section covers testing keyboard input using ReadKey and GetKeyState, including a program that reports the state of the CapsLock key and another program that checks the state of the NumLock and Left Shift keys.

#### Testing Keyboard Input with ReadKey:

The program tests ReadKey by waiting for a keypress and then reporting the state of the CapsLock key.

A delay factor is included when calling ReadKey to allow MS-Windows

to process its message loop.

If ReadKey returns a non-zero value (a keypress has occurred), the program tests the value of EBX using the CAPSLOCK\_ON constant to check the state of the CapsLock key.

It then displays a message indicating whether CapsLock is ON or OFF.

#### GetKeyState for Keyboard State Testing:

The GetKeyState API function allows you to test the state of individual keyboard keys. You pass it a virtual key value, like those identified in Table 11-4.

Table 11-4 Testing Keys with GetKeyState.

Key	Virtual Key Symbol	Bit to Test in EAX
NumLock	VK_NUMLOCK	0
Scroll Lock	VK_SCROLL	0
Left Shift	VK_LSHIFT	15
Right Shift	VK_tRSHIFT	15
Left Ctrl	VK_LCONTROL	15
Right Ctrl	VK_RCONTROL	15
Left Menu	VK_LMENU	15
Right Menu	VK_RMENU	15

It returns a value in EAX, and you need to test the value to determine the state of the key.

The program demonstrates using GetKeyState to check the state of the NumLock and Left Shift keys:

It calls GetKeyState with VK\_NUMLOCK and checks if the lowest bit (bit 0) of AL is set.

```
(bit 0) of AL is set.
```

If it is set, it indicates that NumLock is ON.

It then calls GetKeyState with VK\_LSHIFT and checks the high bit (bit 31) of EAX to determine if the Left Shift key is currently pressed.

Depending on the test results, it displays appropriate messages to report the state of the keys.

```
227 ;Testing Keyboard Input with ReadKey (TestReadkey.asm)
228 INCLUDE Irvine32.inc
229 INCLUDE Macros, inc
230
231 .code
232 main PROC
233 L1:
        mov eax, 10 ; Delay for message processing
234
235
        call Delay
        call ReadKey ; Wait for a keypress
236
237
        jz L1
238
239
        test ebx, CAPSLOCK ON
240
        jz L2
        mWrite <"CapsLock is ON", Odh, Oah>
241
242
        jmp L3
243 L2:
        mWrite < "CapsLock is OFF", Odh, Oah>
244
245 L3:
246
        exit
247 main ENDP
248 END main
```

#### Program 2:

```
251 ;GetKeyState
252 INCLUDE Irvine32.inc
253 INCLUDE Macros.inc
254
255 .code
256 main PROC
257
        INVOKE GetKeyState, VK_NUMLOCK
258
        test al, 1
        .IF !Zero?
259
            mWrite <"The NumLock key is ON", Odh, Oah>
260
261
        .ENDIF
262
        INVOKE GetKeyState, VK_LSHIFT
263
       test eax, 80000000h
264
265
        .IF !Zero?
266
            mWrite <"The Left Shift key is currently DOWN", Odh, Oah>
267
        .ENDIF
268
269
       exit
270 main ENDP
271 END main
```