Exception Synchronization

The passage below describes the potential problem of floating-point exceptions in concurrent systems and how to use the WAIT and FWAIT instructions to solve it.

In a concurrent system, two or more tasks can execute at the same time. This can be a problem for floating-point exceptions because the FPU and the CPU are separate units.

If an unmasked **floating-point exception occurs while the CPU is executing an integer or system instruction**, the exception will not be handled until the next floating-point instruction or the FWAIT instruction is executed.

This can lead to problems if the floating-point instruction that caused the exception is followed by an integer or system instruction that modifies the same memory operand as the floating-point instruction.

For example, the following code could cause a problem:

This code loads the integer value stored in intVal into the FPU stack register ST(0) and then increments the integer value by 1.

Please note that in this context, the inc instruction increments the integer value stored in memory at the address specified by intVal.

If an unmasked floating-point exception occurs while the FILD instruction is executing, the exception will not be handled until the INC instruction is executed.

If the INC instruction modifies the same memory operand as the FILD instruction, the exception handler will not be able to access the

correct value of the memory operand.

The WAIT and FWAIT instructions can be used to solve this problem.

Both instructions force the processor to check for pending, unmasked floating-point exceptions before proceeding to the next instruction.

This ensures that the exception handler will have a chance to execute before any integer or system instructions that modify the same memory operand as the floating-point instruction that caused the exception.

To solve the problem in the example code above, you could add a WAIT or FWAIT instruction after the FILD instruction. For example:

```
454 .data
        intVal DWORD 25
455
456
457 .code
458
        ; Load the integer into ST(0)
        fild intVal
459
460
461
        ; Wait for pending exceptions
        fwait
462
463
        ; Increment the integer
464
        inc intVal
465
```

In this version, the comments are placed next to the relevant instructions.

The FILD instruction loads the integer into the FPU stack, followed by the FWAIT instruction to ensure any pending exceptions are handled.

Then, the INC instruction increments the integer value in memory. This sequence of instructions allows for proper exception handling before modifying the shared memory operand.

This would ensure that the exception handler would have a chance to execute before the INC instruction is executed.

EXAMPLE CODE FOR FPU OPERATIONS:

Here's the code for the expression valD = -valA + (valB * valC)

```
468 .data
469
       valA REAL8 1.5
       valB REAL8 2.5
470
       valC REAL8 3.0
471
        valD REAL8 ? ; Initialize valD as a placeholder for the result
472
473
474 .code
475
        ; Load valA on the FPU stack and negate it
476
        fld valA
                     ; ST(0) = valA
       fchs
                        ; Negate the value in ST(0)
477
478
       ; Load valB into ST(0) and multiply by valC
479
       fld valB
                       ; Load valB into ST(0)
480
481
       fmul valC
                        ; Multiply ST(0) by valC, leaving the product in ST(0)
482
      ; Add the two values on the stack (ST(0) and ST(1))
483
        fadd
                        ; Add ST(0) and ST(1), result in ST(0)
484
485
        ; Store the result in valD
486
        fstp valD
                  ; Store the result in valD
487
```

In this code, we calculate valD as the result of the expression -valA + (valB * valC).

We start by loading valA onto the FPU stack and negating it using fchs.

Then, we load valB into ST(0) and multiply it by valC, resulting in the product in ST(0).

Finally, we add the two values on the stack and store the result in valD.

The fstp instruction pops the result from the stack and stores it in valD.

SUM OF ARRAY OF DOUBLE PRECISION NUMBERS

In the code below, you are calculating the sum of an array of double-

precision real numbers.

```
510; Define the size of the array
511 ARRAY_SIZE = 20
512
513 .data
514
       sngArray REAL8 ARRAY_SIZE DUP(?)
515
516 .code
517
                    ; Initialize array index
       mov esi, 0
                         ; Push 0.0 onto the FPU stack
518
       fldz
519
       mov ecx, ARRAY_SIZE; Set the loop counter to ARRAY_SIZE
520
521
       L1:
       fld sngArray[esi] ; Load the current element into ST(0)
522
523
                         ; Add ST(0) to the accumulator (ST(0)), and pop
524
       add esi, TYPE REAL8; Move to the next element
       loop L1
                         ; Continue the loop until all elements are processed
525
526
      call WriteFloat ; Display the sum in ST(0)
527
```

In this code, we are calculating and displaying the sum of an array of double-precision real numbers.

The size of the array is defined by the symbolic constant ARRAY_SIZE, which has a value of 20.

This constant makes the code more maintainable, allowing us to change the array size in a single place if needed.

We initialize a loop counter esi to 0 and push 0.0 onto the FPU stack using fldz. This will be our accumulator for the sum of the array elements.

The loop counter ecx is set to the value of ARRAY_SIZE, which determines the number of elements in the array.

We enter a loop labeled as L1, where we perform the following operations for each element of the array:

Load the current array element into the FPU stack using fld sngArray[esi].

Add the value in the FPU stack to the accumulator (ST(0)) using fadd.

This operation also pops the top of the stack.

Move to the next element by adding the size of a REAL8 (8 bytes) to esi using add esi, TYPE REAL8.

The loop continues until all elements of the array have been processed.

After the loop, we call WriteFloat to display the sum of the array elements in ST(0).

CALCULATING THE SUM OF SQUARES OF TWO NUMBERS

In this code, we are calculating the sum of the square roots of two numbers, valA and valB. Here are the steps involved:

We define two real numbers, valA and valB, which have the values 25.0 and 36.0, respectively.

```
535 .data
536
       valA REAL8 25.0
537
       valB REAL8 36.0
538
539 .code
       fld valA ; Load valA onto the FPU stack
540
                  ; Replace ST(0) with the square root of valA
      fsart
541
                  ; Load valB onto the FPU stack
       fld valB
542
                  ; Replace ST(0) with the square root of valB
543
       fsart
                   ; Add the two square roots and leave the result in ST(0)
       fadd
544
```

We use the FPU instructions to perform the calculation:

fld valA: This instruction loads the value of valA onto the FPU stack, making it the top element (ST(0)) on the stack.

fsqrt: This instruction replaces the value in ST(0) with its square root, so now ST(0) contains the square root of valA.

fld valB: We load the value of valB onto the FPU stack, replacing the previous value in ST(0).

fsqrt: This instruction calculates the square root of the new value

in ST(0), which is the square root of valB.

fadd: Finally, we add the two square roots together, and the result is left in ST(0). This means ST(0) now contains the sum of the square roots of valA and valB.

This code efficiently calculates the sum of the square roots of vala and valB, utilizing the FPU instructions to load, compute square roots, and add the results. The final sum is stored in ST(0).

CALCULATING THE DOT PRODUCT OF TWO PAIRS OF NUMBERS

Here, you have a code snippet that calculates the dot product of two pairs of numbers from an array. The input data contains two pairs of numbers stored in the "array" variable.

```
.data
array REAL4 6.0, 2.0, 4.5, 3.2

552
553 .code
fld dword ptr [array] ; Load the first number of the first pair
fmul dword ptr [array+4] ; Multiply with the second number of the first pair
fld dword ptr [array+8] ; Load the first number of the second pair
fmul dword ptr [array+12] ; Multiply with the second number of the second pair
fadd ; Add the two products in ST(0)
```

fld array: This instruction loads the first number from the "array" into ST(0), which is the top of the FPU stack.

fmul [array+4]: Here, we multiply the value at the memory location array+4 with the value in ST(0). This corresponds to multiplying the first pair (6.0 * 2.0) and leaving the result in ST(0).

fld [array+8]: We load the second number from the second pair (4.5) into ST(0).

fmul [array+12]: This instruction multiplies the value at memory location array+12 (which is 3.2) with the value in ST(0). This is equivalent to multiplying the second pair (4.5 * 3.2) and leaves the result in ST(0).

fadd: Finally, we add the two results in ST(0), which represents the dot product (6.0 * 2.0) + (4.5 * 3.2).