



Part 1: Data Link Layer







Exp 1. Ethernet Messages Sending & Observing


OBJECTIVE: To understand the basic Ethernet message transfer and observe the result.

BRIEF DESCRIPTION: This experiment examines the Ethernet message transfer

using a user-defined protocol. By using MDDL, and GUI tool, students can learn how Ethernet message transfers.

DURATION: 1.5 hrs

TOPOLOGY



TECHNICAL BACKGROUND

It is well known that Ethernet has become the most popular LAN technology and can be regarded as a link level connection in network. Ethernet frames are of variable length, with no frame smaller than 60 octets or larger than 1514 octets (header and data). Figure 1.1 shows that the Ethernet frame format contains the physical source address as well as the destination address. The frame type field contains a 16-bit integer that identifies the type of the data being carried in the frame. Appendix A shows some used Ethernet types.

Ethernet Frame				
	Header		Data	
Destination MAC address	Source MAC address	Туре	46(minimum)-1500(maximum)	
0	6	12	14	1513


Figure 1.1

PROCEDURE

To perform the laboratory experiment, let six students make a group. One student acts Leader and others act Members 1 through 5, respectively. Students play the role of Leader by turns.

Realizing the Network Topology

1. Complete the network connections on HUBOX by referring to Figure 1.2.






Figure 1.2

Creating Ethernet Messages

A. Leader Sends a Broadcast Frame to Members

Leader and Members

- 2. Execute **XCLIENT.BAT** to open the KCodes Network Explorer for ITS window.
- 3. Check the Listening On.
- 4. Choose **Listening Level** from the Listen menu. Check **Interface Frames**.
- Select New Memorized Message Brower from the Listen menu to open the Network Message Browser (see Figure 1.3) that starts to monitor the network transmission.




Figure 1.3

- Open the Network Message Sender by selecting Send Interface Frame from the Send menu.
- In the Network Message Sender dialog box, type "FF:FF:FF:FF:FF" into Destination MAC Address textbox, enter "this is a broadcast from leader" into Data (see Figure 1.4), and click the Send button.




Figure 1.4

Members

8. You should now receive an Ethernet frame as shown in Figure 1.5. Choose this frame by clicking on any field of the frame and press the **Detail** button.




Figure 1.5

9. The Ethernet Frame Viewer appears as shown in Figure 1.6. It shows all details of the frame. Note that the Source Ether Address (00:94:12:15:01:3D) is Leader's address.
Write down this address for use in the next steps.




Figure 1.6

B. Members Send Broadcast Frames to Leader

Members

- 10. Open a new Network Message Sender.
- 11. Type "FF:FF:FF:FF:FF" into Destination MAC Address textbox, enter "this is a broadcast from member<your number>" into Data (see Figure 1.7), and click the Send button.




Figure 1.7

12. After every member has sent their broadcast frames, you should see the other 5 frames in the Network Message Browser as shown in Figure 1.8. Try to look up their MAC Addresses and complete Table 1.1.




Figure 1.8

Table 1.1

Name	MAC Address
Leader	
Member1	
Member2	
Member3	
Member4	<i>y</i>
Member5	

C. Leader Sends a Unicast Frame to Members

Leader

- 13. Open a new Network Message Sender.
- 14. Type < MAC Address of Member1> into Destination MAC Address textbox, enter "hi member1 this is a unicast from leader" into Data (see Figure 1.9), and click the Send button. Member 1 should now receive the frame from Leader.
- 15. Repeat Step 14 for Members 2 through 5.




Figure 1.9

D. Members Send Unicast Frames to Leader

<u>Members</u>

- 16. Open a new Network Message Sender.
- 17. Type <MAC Address of Leader> into Destination MAC Address textbox, enter "hi leader this is a unicast from member<your number>" into Data (see Figure 1.10), and click the Send button. Leader should receive the frames from Members.




Figure 1.10

Sending Ethernet Messages by MDDL Platform

A. Send and Autorespond Broadcast Messages

Leader and Members

- 18. Open the Network Message Browser. Check **Listening On**.
- 19. Open the MDDL Editor by selecting the MDDL Reactor Panel from the Reactor menu.

Members

20. In the MDDL Editor window, click the **Load** button and open the file C: \XClient \Data \Mddl \Tutorial \Ex01 \AutoResponser.mddl (see Figure 1.11). Click the **Upld** button.




Figure 1.11

- 21. In the MDDL Editor window, click the **Load** button and open the file C: \XClient \Data \Mddl \Tutorial \Ex01 \BCastMessages.mddl.
- 22. Click the **UpId** button. Your ITS will continuously send an identical broadcast Ethernet message to Members at intervals of 5 seconds.
- B. Send and Autorespond Unicast Messages

Leader and Members

23. Reset the Network Message Browser. Check **Listening On**.

Members

24. In the MDDL Editor window, click the **Load** button and open the file C: \XClient \Data \Mddl \Tutorial \Ex01 \AutoResponser.mddl. Click the **UpId** button.

- 25. In the MDDL Editor window, click the **Load** button and open the file C: \XClient \Data \Mddl \Tutorial \Ex01 \IUCastMessages.mddl.
- 26. Referring to Table 1.1, add <all the MAC addresses of Members> into the program as shown in Figure 1.12. Finally click the Upld button. Your ITS will continuously send unicast Ethernet messages to Members at intervals of 5 seconds. Members should receive the frames from Leader than auto-responds it.




Figure 1.12

DISCUSSIONS

- 1. What's the difference between broadcast and unicast frame?
- 2. What's the Ethernet Type? Is it important? (refer to Appendix A)
- 3. Try to load the BCastMessages-1.mddl file (path: C: \XClient \Data \Mddl \Tutorial \Ex01) in the MDDL Editor, then compare BCastMessages.mddl and BCastMessages-1.mddl (refer to Appendix B).
- 4. Discuss the programs of BCastMessages.mddl and IUCastMessages.mddl. How we're able to auto-send broadcast and unicast messages together? Can we mix BCastMessages.mddl and IUCastMessages.mddl? Try to mix BCastMessages.mddl and IUCastMessages.mddl, then play again.

REACTOR PROGRAMS

1. BCastMessages.mddl

```
TIMER_WITH_PERIOD 5000

{

SEND_OUT_ETHER_FROM_INTERFACE 1 WITH_DATA

{

T.ETHER_MACADDRDST = CNST_MACADDR_BROADCAST,

T.ETHER_MACADDRSRC = MYMAC(1)

T.ETHER_TYPE = {0xAA,0xAA}

T.[14, ] = "This is a broadcast!"

}

}
```

2. BCastMessages-1.mddl

3. IUCastMessages.mddl

```
TIMER WITH PERIOD 5000
{
  SEND_OUT_ETHER_FROM_INTERFACE 1 WITH_DATA
     T.ETHER MACADDRSRC = MYMAC(1)
     T.ETHER TYPE = \{0x22,0x22\}
           = "This is a unicast!"
     T.[14, ]
  }
}
TIMER WITH PERIOD 5000
  SEND_OUT_ETHER_FROM_INTERFACE 1 WITH_DATA
     T.ETHER_MACADDRSRC = MYMAC(1)
     T.ETHER_TYPE = \{0x33,0x33\}
            = "This is a unicast!"
     T.[14, ]
  }
}
TIMER WITH PERIOD 5000
  SEND_OUT_ETHER_FROM_INTERFACE 1 WITH_DATA
     T.ETHER MACADDRSRC = MYMAC(1)
     T.ETHER TYPE = \{0x44,0x44\}
               = "This is a unicast!"
     T.[14, ]
```

```
}
}
TIMER_WITH_PERIOD 5000
  SEND OUT ETHER FROM INTERFACE 1 WITH DATA
     T.ETHER MACADDRSRC = MYMAC(1)
     T.ETHER TYPE = \{0x55,0x55\}
                = "This is a unicast!"
     T.[14, ]
  }
}
TIMER_WITH_PERIOD 5000
  SEND_OUT_ETHER_FROM_INTERFACE 1 WITH_DATA
     T.ETHER MACADDRSRC = MYMAC(1)
     T.ETHER TYPE = \{0x66,0x66\}
     T.[14, ]
                = "This is a unicast!"
  }
}
```

4. AutoResponser.mddl

```
ETHER_IN_HANDLER ANY
   IF(S.ETHER MACADDRDST==MYMAC(INTERFACE()))
       SEND_OUT_ETHER_FROM_INTERFACE INTERFACE() WITH_DATA
       {
                           = S
          T.ETHER_MACADDRDST = S.ETHER MACADDRSRC
          T.ETHER MACADDRSRC = MYMAC(INTERFACE())
          T.ETHER TYPE
                             = \{0xAA,0xAA\}
          T.[16, ]
                         = "Received your unicast!"
      }
   IF(S.ETHER MACADDRDST==CNST MACADDR BROADCAST)
       SEND_OUT_ETHER_FROM_INTERFACE INTERFACE() WITH_DATA
       {
                           = S
          T.ETHER_MACADDRDST = S.ETHER_MACADDRSRC
          T.ETHER MACADDRSRC = MYMAC(INTERFACE())
          T.ETHER TYPE
                             = \{0xBB,0xBB\}
          T.[16, ]
                         = "Received your broadcast!"
      }
   }
}
```

Exp 2. MAC Address Discovery

OBJECTIVE: To learn how to write a simple reactor handler program, and

compare the experiment results with the ones by using manual


operation.

BRIEF DESCRIPTION: The basic mechanism of network communication, request

and reply.

DURATION: 3 hrs

TOPOLOGY



TECHNICAL BACKGROUND

A simple non-standard communication protocol (depicted as in Figure 2.1) is defined to query the MAC addresses of ITS interfaces. The protocol consists of the two Ethernet types: one (0xA001) is the MAC address request and another (0xA002 or 0xA003) is MAC address response. First the students send the MAC address request to query the desired MAC address of the ITS interfaces, which can be identified by the pair of machine number and interface number. When receiving the above request messages, the students choose one of the two formats: Format 1 and Format 2 to reply the messages to tell the senders MAC address.

MAC Address Request

	Ту	/pe			Data		
	AC	0:01		Queried Machine Number		Queried Interface Number	
1	2 th	13 th	14 th		15 th		byte
				(a)			

MAC Address Responses

Format 1

A0:02	Queried Machine Number	Queried Interface	Queried MAC
7.0.02	Queried Machine Number	Number	Address

Format 2

A0:03	Queried Machine Number	Queried Interface number	
(b)			

Figure 2.1

PROCEDURE

Realize the Network Topology

1. Complete the network connections on HUBOX by referring to Figure 2.2.




Figure 2.2

UTP Cable(RJ 45 Interface)

Manual Request and Response Frames

Leader and Members

- 2. Execute **XCLIENT.BAT** to open the KCodes Network Explorer for ITS window.
- 3. Open the Network Message Browser. Check **Listening On**.

Leader

- Open the Network Message Sender. Type "FF:FF:FF:FF:FF" into Destination MAC Address. Type "A0:01" into Type textbox.
- 5. Refer to Figure 2.1(a). Decide which Member and interface you want to request, then type the value into Data. For example, if you want to request the Interface1 of Member1, just type "02:01" into Data (see Figure 2.3) and press the **Send** button.




Figure 2.3

Members

- Look up the detail when the frame is in. If the frame from Leader matches your ITS
 machine number, open Network Message Sender.
- 7. Type Leader's MAC address into Destination MAC Address and enter "A0:02" or "A0:03" into Type as you like. For example, when Member1 receives a request message from Leader, Member1 must type "00:94:12:15:01:3D" into Destination MAC Address and "A0:02" into Type as shown in Figure 2.4. Then refer to Figure 2.1(b), the protocol of Format 1, type "02,01,00,94,12,15,01,3E" into Data. Finally click the Send

button.




Figure 2.4

Response Frames by MDDL

Leader and Members

8. Open the Network Message Browser window. Check **Listening On**.

Leader

- 9. Open the MDDL Editor by selecting **MDDL Reactor Panel** from the Reactor menu.
- 10. Click the **Load** button. Open the file C: \XClient \Data \Mddl \Tutorial \Ex02 \BCastRequest.mddl and click the **UpId** button. Your ITS will continuously send broadcast Ethernet messages to request all Members at intervals of 5 seconds.

Members

- 11. Open the MDDL Editor by selecting **MDDL Reactor Panel** from the Reactor menu.
- 12. Click the **Load** button. As you like, open the AutoResponserFormat1.mddl or AutoResponserFormat2.mddl file (path: C: \XClient \Data \Mddl \Tutorial \Ex02).
- 13. Add
 // Add
 / A

```
Add your machine number
ETHER IN HANDLER ANY
    IF( S[12]==\{0XA0\} && S[13]==\{0x01\} && S[14]=
                                              && ( S[15]==1 || S[15] ==2 ))
       SEND_OUT_ETHER_FROM_INTERFACE INTERFACE() WITH_DATA
       {
           Т
                              = S,
           T.ETHER_MACADDRDST = S.ETHER_MACADDRSRC,
           T.ETHER_MACADDRSRC = MYMAC(INTERFACE()), //ETHER_MACADDRDST,
                             = \{0xA0\},
           T.[12]
                             = \{0x02\},
           T.[13]
           T.[14]
                             = S.[14],
           T.[15]
                             = S.[15],
           T.[16,21]
                          =MYMAC(S.[15])
       }
   }
}
```

Figure 2.5

```
Add your machine number
ETHER IN HANDLER ANY
    IF( S[12]=={0XA0} && S[13]=={0x01} && S[14]==_
                                              && ( S[15]==1 || S[15] ==2 ))
       SEND_OUT_ETHER_FROM_INTERFACE INTERFACE() WITH_DATA
       {
           Т
                              = S,
           T.ETHER MACADDRDST = S.ETHER MACADDRSRC,
           T.ETHER_MACADDRSRC = MYMAC(INTERFACE()),//ETHER_MACADDRDST,
           T.[12]
                             = \{0xA0\},\
                             = \{0x03\},
           T.[13]
           T.[14]
                             = S.[14],
           T.[15]
                             = S.[15]
   }
}
```

Figure 2.6

14. When Leader requests your MAC address of interface, your ITS will auto-respond with Format 1 or Format 2 depending on which program you chosen.

DISCUSSIONS

1. Discuss the difference between Format 1 and Format 2.

```
(Hint: Try to request interface 2.)
```

2. Discuss with your partners and design a better protocol for Ethernet communication.

REACTOR PROGRAMS

1. AutoResponserFormat1.mddl

```
ETHER IN HANDLER ANY
{
    IF( S[12]=={0XA0} && S[13]=={0x01} && S[14]==01 && ( S[15]==1 || S[15] ==2 ))
       SEND_OUT_ETHER_FROM_INTERFACE INTERFACE() WITH_DATA
       {
                               = S,
           T.ETHER MACADDRDST = S.ETHER MACADDRSRC,
           T.ETHER MACADDRSRC = MYMAC(INTERFACE()),//ETHER MACADDRDST,
           T.[12]
                             = \{0xA0\},\
           T.[13]
                             = \{0x02\},
           T.[14]
                             = S.[14],
           T.[15]
                             = S.[15],
           T.[16,21]
                          =MYMAC(S.[15])
       }
   }
}
```

2. AutoResponserFormat2.mddl

```
ETHER_IN_HANDLER ANY
{
    IF( S[12]=={0XA0} && S[13]=={0x01} && S[14]==01 && ( S[15]==1 || S[15] ==2 ))
       SEND OUT ETHER FROM INTERFACE INTERFACE() WITH DATA
       {
           T.ETHER_MACADDRDST = S.ETHER_MACADDRSRC,
           T.ETHER_MACADDRSRC = MYMAC(INTERFACE()),//ETHER_MACADDRDST,
           T.[12]
                             = \{0xA0\},\
           T.[13]
                             = \{0x03\},
           T.[14]
                             = S.[14],
           T.[15]
                             = S.[15]
       }
   }
}
```

3. BCastRequest.mddl

```
TIMER_WITH_PERIOD 5000
   SEND_OUT_ETHER_FROM_INTERFACE 1 WITH_DATA
   {
      T.ETHER_MACADDRDST = CNST_MACADDR_BROADCAST,
      T.ETHER MACADDRSRC = MYMAC(1)
      T.ETHER_TYPE = \{0xA0,0x01\}
             = \{0x02,0x01\}
      T.[14, ]
   }
}
TIMER_WITH_PERIOD 5000
   SEND OUT ETHER FROM INTERFACE 1 WITH DATA
      T.ETHER_MACADDRDST = CNST_MACADDR_BROADCAST,
      T.ETHER MACADDRSRC = MYMAC(1)
      T.ETHER_TYPE = \{0xA0,0x01\}
T.[14,] = \{0x03,0x01\}
   }
}
TIMER_WITH_PERIOD 5000
{
   SEND OUT ETHER FROM INTERFACE 1 WITH DATA
      T.ETHER MACADDRDST = CNST MACADDR BROADCAST,
      T.ETHER MACADDRSRC = MYMAC(1)
      T.ETHER TYPE = \{0xA0,0x01\}
                = \{0x04,0x01\}
      T.[14, ]
   }
}
TIMER_WITH_PERIOD 5000
{
   SEND OUT ETHER FROM INTERFACE 1 WITH DATA
      T.ETHER MACADDRDST = CNST MACADDR BROADCAST,
      T.ETHER MACADDRSRC = MYMAC(1)
      T.ETHER_TYPE = \{0xA0,0x01\}
      T.[14,] = \{0x05,0x01\}
   }
}
TIMER_WITH_PERIOD 5000
   SEND OUT ETHER FROM INTERFACE 1 WITH DATA
      T.ETHER MACADDRDST = CNST MACADDR BROADCAST,
      T.ETHER MACADDRSRC = MYMAC(1)
      T.ETHER TYPE = \{0xA0,0x01\}
             = \{0x06,0x01\}
      T.[14, ]
   }
}
```