# CS5231: Systems Security

Lecture 3: Type Errors, Code Reuse, and Data-oriented Attacks

# Type Errors (I): Integer Overflow

### A Puzzle: Is this code free from buffer overflow?

```
void bad_function(char *input)
     char dest_buffer[32];
     char input len = strlen(input);
     if (input_len < 32)</pre>
           strcpy(dest_buffer, input);
           printf("The first command line argument is %s.\n", dest_buffer);
     else
           printf("Error - input is too long for buffer.\n");
```

### Integer Overflow

```
void bad_function(char *input)
     char dest_buffer[32];
     char input_len = strlen(input); // Range? [0, 255]
                                               Or [-128, 127]
           -100
     if (input_len < 32)
          strcpy(dest_buffer, input);
          printf("The first command line argument is %s.\n", dest_buffer);
     else
          printf("Error - input is too long for buffer.\n");
```

### Implicit Type Conversions

Operation	Operand Values	Overflow / Underflow?
SUB – 32 Bit signed	-2^31 - 2^31	Underflow
ADD – 32 Bit Unsigned	2^32 + 2^32	Overflow
MUL – 32 Bit Unsigned	2^20 * 2^20	Overflow

The actual range of values for each type is compiler / machine –dependent. When operands of different types widths are used, C99 standard automatically (implicitly) converts types.

### Type Promotions:

bool -> char -> short int -> int -> unsigned int -> long -> unsigned -> long long -> float -> double -> long double


### Signed / Unsigned Coercions:

Defined by the C standard

## Why doesn't hardware complain?

 Hardware: Arithmetic doesn't distinguish signed and unsigned integers --- works for both

Unsigned



$$-x_{n-1}2^{n-1} + \sum_{i=0}^{n-2} x_i 2^i$$

Signed

i=0

An advantage of two's complement is that signed and unsigned addition can be performed using the same operation. The same is true for subtraction and multiplication. Historically, this was advantageous because fewer instructions needed to be implemented. Also, unlike the *ones' complement* and *sign-magnitude* representations, two's complement has only one representation for zero. A drawback of two's complement is that its range,  $-2^{n-1} \dots 2^{n-1} - 1$ , is asymmetric. Thus, there is a representable value,  $-2^{n-1}$ , that does not have a representable additive inverse—a fact that programmers can and do forget.

When an *n*-bit addition or subtraction operation on unsigned or two's complement integers overflows, the result "wraps around," effectively subtracting  $2^n$  from, or adding  $2^n$  to, the true mathematical result. Equivalently, the result can be considered to occupy n + 1 bits; the lower n bits are placed into the result register and the highest-order bit is placed into the processor's carry flag.

## Why doesn't hardware complain?

• In C99 on x64, conversions reinterpret the bit representation!

#### 3.2. The Usual Arithmetic Conversions

Most integer operators in C/C++ require that both operands have the same type and, moreover, that this type is not narrower than an int. The collection of rules that accomplishes this is called the usual arithmetic conversions. The full set of rules encompasses both floating point and integer values; here we will discuss only the integer rules. First, both operands are promoted:

If an int can represent all values of the original type, the value is converted to an int; otherwise, it is converted to an unsigned int. These are called the integer promotions. All other types are unchanged by the integer promotions.

If the promoted operands have the same type, the usual arithmetic conversions are finished. If the operands have different types, but either both are signed or both are unsigned, the narrower operand is converted to the type of the wider one.

If the operands have different types and one is signed and the other is unsigned, then the situation becomes slightly more involved. If the unsigned operand is narrower than the signed operand, and if the type of the signed operand can represent all values of the type of the unsigned operand, then the unsigned operand is converted to signed. Otherwise, the signed operand is converted to unsigned.

These rules can interact to produce counterintuitive results. Consider this function:

```
int compare (void) {
  long a = -1;
  unsigned b = 1;
  return a > b;
}
```

For a C/C++ implementation that defines long to be wider than unsigned, such as GCC for x86-64, this function returns zero. However, for an implementation that defines long and unsigned to have the same width, such as GCC for x86, this function returns one. The issue is that on x86-64, the comparison is between two signed integers, whereas on x86, the comparison is between two unsigned integers, one of which is very large. Some compilers are capable of warning about code like this.

C/C++ don't define exactly for all cases!

Where they do define, the behavior is implementation (size) specific to compilers, and varies by architecture!

### Real-life Incidents Due to Integer Bugs

The New York Times Magazine

### Little Bug, Big Bang

By James Gleick

Dec. 1, 1996

IT TOOK THE European Space Agency 10 years and \$7 billion to produce Ariane 5, a giant rocket capable of hurling a pair of threeton satellites into orbit with each launch and intended to give Europe overwhelming supremacy in the commercial space business.

All it took to explode that rocket less than a minute into its maiden voyage last June, scattering fiery rubble across the mangrove swamps of French Guiana, was a small computer program trying to stuff a 64-bit number into a 16-bit space.

### **₩CVE-2018-10299 Detail**

### **Current Description**

### Memory Safe ≠ Type Safe

An integer overflow in the batchTransfer function of a smart contract implementation for Beauty Ecosystem Coin (BEC), the Ethereum ERC20 token used in the Beauty Chain economic system, allows attackers to accomplish an unauthorized increase of digital assets by providing two \_receivers arguments in conjunction with a large \_value argument, as exploited in the wild in April 2018, aka the "batchOverflow" issue.

Source: MITRE

Hide Analysis Description

# From Vulnerabilities To Memory Exploits

# Control-flow Hijacking Exploits: Code Injection


- Control-oriented a.k.a control-flow hijacking
- Outcome 1: Code Injection
  - Definition: A memory exploit that hijacks control to jump to attacker's data payload

### Code Injection Example


```
int f() {
...
   g (x, y);
}

int g(int x, int y) {
   char buf[50];
   scanf("%s", buf);
}
```

```
.g
push ebp
...
call scanf
...
pop ebp
ret
```




### Code Injection Example



### Code Injection Example

- Instruction NOP, No Operation.
  - Tell CPU to do nothing and fetch the next instruction
- Including a large block of NOP instructions in the injected code as landing area
- Execution will reach shell code as long as return address pointing to somewhere in the NOP sled



Adv: You can jump anywhere in the NOP sled

## New Rounds of Control-flow Attacks: Code Reuse

# Control-oriented Exploits (II): Code Reuse


- Outcome 2: Code Reuse
  - Definition: A memory exploit that hijacks control to jump to attacker's controlled code address
- Requirements for Code Reuse
  - Req 1: Write Attack Payload in memory
  - Req 2: Have Attack Payload Be Executable
  - Req 3: Divert control-flow to payload

Insight: Re-use the existing code as payload


### Code Reuse Attack: Return-to-libc

- Attacker hijacks control flow
- Jumps back to the code segment





### Code Reuse Attack: Return-to-libc



address to code seq.

### Code Reuse Attack: Return-to-libc

```
.execv <0x8049000>

push ebp
... // read parameter1
... // read parameter2
... // read parameter3
pop ebp
ret
```


```
•g

push ebp

...


call scanf
...

pop ebp
ret
```





### Return-to-Libc

Introduce new Control Edges




### **Control Flow Graph**





# Code Reuse (II): ROP

### An Analagy





Can you see:

ROP? SECURITY?

# Control-oriented Exploits (II): Code Reuse

- Outcome 2: Code Reuse
  - Definition: A memory exploit that hijacks control to jump to attacker's controlled code address
- Requirements for Code Reuse
  - Req 1: Write Attack Payload in memory
  - Req 2: Have Attack Payload Be Executable
  - Req 3: Divert control-flow to payload

Insight: Re-use the existing code as payload

### Code Reuse Attacks (II): Return-oriented Programming (ROP)


### Key Observation:

```
f7 c7 07 00 00 00 test $0x00000007, %edi
0f 95 45 c3 setnzb -61(%ebp)

c7 07 00 00 00 0f movl $0x0f000000, (%edi)
95 xchg %ebp, %eax
inc %ebp
c3 ret
```


What is the similarity between these machine code snippets?

### Code Reuse Attacks (II): Return-oriented Programming



### **ROP Gadgets**

**ROP Gadget:** Instruction sequence which end a control transfer





Let's say the attacker's goal is:


\*(0x4a304120) = \*(0x4a304120) + 0x00032400


Attacker find the following **gadgets** in code memory:


8331c034	pop eax stack -> register ret
831e5201	pop ebx stack > reg
832a34b9	mov eax, [eax] men > reg
8324f321	add eax, ebx ret
83294a3a	pop ecx ret
8320d265	mov [ecx], eax ret











### Recap: The ROP Attack Procedure

- Attacker's goal: Execute a particular exploit code of its choice
- The attackers pre-identifies certain useful instruction patterns called "ROP gadgets" in the executable section of the program
- Procedure:
  - The attacker corrupts the stack in a particular way (see later)
  - Hijack control Cause the program to Jump to address A
  - At address A, we have a "ROP gadget" code:
    - 1. Instruction (I) at address A executes the first instruction of the payload
    - 2. The next instruction after (I) is a **ret** instruction
    - 3. The **ret** instruction will jump to address B, by reading B from the stack.
  - The step 3 above will cause the program to repeat Steps 1-3 (with a new value B instead of A) recursively.

### How many ROP Gadgets In Programs?

Binary	PSHAPE	rp++	ropper	ROPgadget
$firefox_W$	6,709	6,182	5,445	6,259
$iexplore_W$	928	888	836	888
$\mathrm{chrome}_W$	64,372	58,890	52,991	59,969
$\mathrm{mshtml}_W$	1,329,705	1,239,403	1,099,466	1,242,616
$jfxwebkit_W$	1,172,718	1,076,350	960,091	1,086,061
$\operatorname{chromium}_L$	5,358,283	5,159,712	4,579,388	5,130,856
$apache2_L$	24,164	22,722	18,061	22,875
$\mathrm{openssl}_L$	6,978	6,829	5,377	6,845
$\operatorname{nginx}_L$	26,314	25,700	21,081	25,245

#### (a) Number of extracted gadgets

Function	PSHAPE	ropper	ROPgadget
$\overline{\mathrm{W}_{VirtualProtect}}$	2/4	-	-
$\mathcal{L}_{mprotect}$	4/4	1/4	1/4
$\mathcal{L}_{mmap}$	3/3	-	-

#### (b) Number of gadget chains

Table 2: (a) Number of gadgets found by each tool on the given binaries, as determined by our evaluation. (b) It is possible to build chains to mprotect for all four Linux binaries, line mprotect shows how many of those chains each tool creates. For mmap, only three of the Linux binaries have the necessary gadgets to build a chain and this line shows how many of those each tool can create. Chains to VirtualProtect exist in four out of the five Windows binaries, this line shows how many of them each tool creates. A dash indicates that the tool does not support calling a function that requires the tool to initialize the required number of arguments. In (a) and (b), L denotes Linux and W, Windows.

### Summarizing Code Reuse Attacks

- Outcome 2: Code Reuse
  - Definition: A memory exploit that hijacks control to jump to attacker's controlled code address
- Requirements for Code Reuse
  - Req 1: Have Attack Payload Be Executable
  - Req 2: Divert control-flow to payload

# Beyond Control-flow Hijacking: Data-oriented Attacks

### **Data-oriented Attacks**

- Requirements for Data-oriented attacks
  - Req 1: Write Attack Payload in memory
  - Req 2: Have Attack Payload Be Executable
  - Req 3: Divert control-flow to payload

Insight: Simply manipulate non-control data

## **Data-Oriented Exploits**

- State-of-the-art: Corrupt security-critical data
  - leave control flow as the same
  - Exhibit "significant" damage

```
PW->pw_uid =0
```

```
// set root privilege
seteuid(0);
   set normal user
privilege
seteuid(pw->pw uid)
// execute <del>use</del>r
command
```

```
//0x1D4, 0x1E4 or 0x1F4 in
JScript 9,
//0x188 or 0x184 in JScript
5.8,
safemode = *(DWORD *)(jsobj
+ 0x188):
if(safemode & 0xB == 0) | {
      Turn on God Mode();
```


Wu-ftpd setuid operation\*

IE SafeMode Bypass<sup>+</sup>

<sup>+</sup> Yang Yu. Write Once, Pwn Anywhere. In Black Hat USA 2014 \* Shuo Chen, Jun Xu, Emre C. Sezer, Prachi Gauriar, and Ravishankar K. Iyer. Non-Control-Data Attacks Are Realistic Threats. In USENIX 2005.


### Data-oriented attacks w/o any memory corruption

- Do I need to corrupt anything for DOA?
- No! An example: Heartbleed



### Data-oriented attacks w/o any memory corruption

- Do I need to corrupt anything for DOA?
- No, An example: Heartbleed



### Heartbleed Code

- Do I need to corrupt anything for DOA?
- No! An example: Heartbleed

```
/* Read type and payload length first */
hbtype = *p++;
n2s(p, payload);
pl = p;
```

```
/* Enter response type, length and copy payload */
*bp++ = TLS1_HB_RESPONSE;
s2n(payload, bp);
memcpy(bp, pl, payload);
```

## Key Takeaways & Summary

- Vulnerabilities vs. Exploits
  - Weakness (Flaw) vs. using it for a particular goal
- Exploit Types:
  - Control-flow hijacking vs. Data-oriented
- Attackers can achieve a variety of attacks
- C/C++: weak type safety, no memory safety
- Hardware does <u>not</u> give memory & type safety