10/30/2019 Simulation Viewer

Lab Report

Your Performance

Your Score: 0 of 5 (0%) Pass Status: Not Passed Elapsed Time: 1 minute 53 seconds Required Score: 100%

Task Summary

- X Configure port Fa0/6 to 10Mbps
- Configure port Fa0/7 to half duplex
- Shut down all unused interfaces (Fa0/4, 0/5, 0/8–0/23, & Gi0/1–0/2)
- X Correct additional misconfigured ports Hide Details

Configure port Fa0/2 for auto speed
Configure port Fa0/3 for auto duplex
Enable port Fa0/24

X Save your changes to the startup-config file **Hide Details**

	Save Fa0/6 settings
- 10	Save Fa0/7 settings
	Save the shutdown for Fa0/4, 5, 8–23, and Gi0/1–2
-	Save the Fa0/2 settings
-	Save the Fa0/3 changes
	Save the Fa0/24 changes

Explanation

In this lab, you should have completed the following:

- You will be adding an older server to switch port Fa0/6 that uses 10BaseT Ethernet. Manually configure the switch port to use 10 Mbps.
- You will be adding a hub to switch port Fa0/7 that will be used for a lab for developers. Manually configure the switch port to use half-duplex communications.
- Make sure that ports Fa0/6 and Fa0/7 are enabled and can be used. Be aware that you have not yet connected devices to those ports.
- Disable all unused interfaces:
 - Fa0/4 and Fa0/5
 - Fa0/8 through Fa0/23
 - Gi0/1 and Gi0/2
- Verify that all remaining ports that are in use are configured to automatically detect speed and duplex settings and are
- Save your changes to the startup-config file.

Do the following:

- 1. Press Enter.
- 2. At the prompt, enter:

Branch1>enable Branch1#configure terminal Branch1(config)#interface FastEthernet0/6 Branch1(config-if)#speed 10 Branch1(config-if)#interface FastEthernet0/7 10/30/2019 Simulation Viewer

> Branch1(config-if)#duplex half Branch1(config-if)#interface range FastEthernet0/4-5, FastEthernet0/8-23, GigabitEthernet0/1-Branch1(config-if-range)#shutdown

- 3. Press **Ctrl** + **Z**.
- 4. At the prompt, enter:

Branch1#show interface status

- 5. Verify the port configuration of all ports, and then use the necessary commands to correct any problems you find. For example, notice that Fa0/24 is administratively down. Also notice that Fa0/2 is not configured to use auto speed and Fa/03 is not configured to use auto duplex.
- 6. At the prompt, enter:

Branch1#configure terminal Branch1(config)#interface FastEthernet0/24 Branch1(config-if)#no shutdown Branch1(config-if)#interface FastEthernet0/2 Branch1(config-if)#speed auto Branch1(config-if)#interface FastEthernet0/3 Branch1(config-if)#duplex auto

- 7. Press **Ctrl** + **Z**.
- 8. Run **show interface status** again to verify your configuration changes.
- 9. At the prompt, enter:

Branch1#copy run start

- 10. Press Enter.
- 11. Press **Enter** to save your changes.