Your Performance

Your Score: 1 of 6 (17%)

Pass Status: Not Passed
Elapsed Time: 4 minutes 33 seconds

Required Score: 100%

Task Summary

- ✓ Delete the ServerParent virtual machine
- X Set the ParentDisk.vhd file to Read Only
- X Create the Server1.vhdx disk Hide Details
 - Create the virtual hard disk
 Create a differencing disk
 Use ParentDisk.vhdx as the parent disk
- X Create the Server2.vhdx disk Hide Details
 - Create the virtual hard disk
 Create a differencing disk
 Use ParentDisk.vhdx as the parent disk
- X Create the Server1 virtual machine Hide Details
 - Create the virtual machine

 Use D:\HYPERV\ for the location

 Generation 2

 Use 4096 MB of RAM

 Use the External network

 Configure the virtual machine to use Server1.vhdx
- X Create the Server2 virtual machine Hide Details
 - □ Create the virtual machine
 □ Use D:\HYPERV\ for the location
 □ Generation 2
 □ Use 4096 MB of RAM
 □ Use the External network
 □ Configure the virtual machine to use Server2.vhdx

Explanation

In this lab, you perform the following tasks:

- Delete the ServerParent virtual machine.
- Set the D:\HYPERV\Virtual Hard Disks\ParentDisk.vhdx file to **Read-only**.
- Create two new differencing hard disks using the following parameters (each hard disk has a different name, but uses the same disk format, disk type, location, and parent disk):
 - Disk format: VHDX
 - Disk type: **Differencing**
 - Name: Server1.vhdx and Server2.vhdx
 - Location: D:\HYPERV\Virtual Hard Disks
 - Parent disk: ParentDisk.vhdx
- Create two new virtual machines using the following parameters (each virtual machine uses a different name and virtual hard disk, but the same location, generation, size, and network):
 - Name: Server1 and Server2

- Location: D:\HYPERV\Generation: Generation 2
- Size: 4096 MBNetwork: External
- Virtual hard disk: **Server1.vhdx** and **Server2.vhdx** respectively

Complete this lab as follows:

- 1. Delete a virtual machine as follows:
 - a. From Server Manager, select **Tools** > **Hyper-V Manager**.
 - b. Select **CORPSERVER**.
 - c. Right-click **ServerParent** and select **Turn Off**.
 - d. Click **Turn Off**.
 - e. Right-click **ServerParent** and select **Delete**.
 - f. Click **Delete**.
- 2. Make a virtual hard disk Read-only as follows:
 - a. From the taskbar, open **File Explorer**.
 - b. Browse to the *location* of the virtual hard disk.
 - c. Right-click **ParentDisk.vhdx** and select **Properties**.
 - d. Select **Read-only**; then click **OK**.
 - e. Close File Explorer.
- 3. Create a differencing hard disk as follows:
 - a. In Hyper-V Manager, right-click **CORPSERVER** and select **New** > **Hard Disk**.
 - b. Click Next.
 - c. Select the *disk format*; then click **Next**.
 - d. Select **Differencing** as the disk type; then click **Next**.
 - e. Enter the *name* for the hard disk file.
 - f. Enter the *location* for the hard disk file: then click **Next**.
 - g. Select **Browse** to find the parent disk.
 - h. Select the *parent disk*.
 - i. Select **Open**.
 - j. Click Next.
 - k. Click **Finish**.
 - l. Repeat step 3 to create the second differencing hard disk.
- 4. Create a virtual machine as follows:
 - a. In Hyper-V Manager, right-click **CORPSERVER** and select **New** > **Virtual Machine**.
 - b. Click Next.
 - c. Enter the *name* of the virtual machine.
 - d. Select **Store the virtual machine in a different location**.
 - e. Enter the *path*; then select **Next**.
 - f. Select the *generation* for the virtual machine; then click **Next**.
 - g. Enter the *amount* of memory to use with the virtual machine; then click **Next**.
 - h. Select the *network connection* used by the virtual machine; then click **Next**.
 - i. Select **Use an existing virtual hard disk**.
 - j. Select **Browse**.
 - k. Select the existing *virtual hard disk*; then select **Open**.
 - l. Click Next.
 - m. Click Finish.
 - n. Repeat step 4 to create the second virtual machine.