



DEPARTMENT OF ECE / EEE
SAVEETHA SCHOOL OF ENGINEERING



Engineer to Excel

CONTROL SYSTEM
LABORATORY RECORD

submitted by

NAME OF THE STUDENT (Reg No)

BACHELOR OF ENGINEERING

in

ELECTRONICS AND COMMUNICATION ENGINEERING

SAVEETHA
INSTITUTE OF MEDICAL AND TECHNICAL SCIENCES
(Declared as Deemed to be University under Section 3 of UGC Act 1956)

CHENNAI - 602105

2024

<Attach Bonafide Page>

CONTROL SYSTEMS LABORATORY

List of experiments

1. TRANSFER FUNCTION OF PARALLEL SYSTEM, CASCADE SYSTEM AND FEEDBACK SYSTEM
2. TRANSFER FUNCTION FROM POLES AND ZEROS & ZEROS AND POLES FROM TRANSFER FUNCTION
3. STEP AND IMPULSE RESPONSE OF A FIRST ORDER SYSTEM
4. TRANSIENT RESPONSE OF A SECOND ORDER SYSTEM
5. TIME RESPONSE PARAMETERS FOR A GIVEN SYSTEM
6. STEP AND RAMP RESPONSE OF DIFFERENT CONTROLLERS
7. P, PI & PID CONTROLLER USING PROCESS CONTROL SIMULATOR
8. BODE PLOT FOR A TRANSFER FUNCTION
9. POLAR PLOT FOR A TRANSFER FUNCTION
10. ROOT LOCUS FOR A TRANSFER FUNCTION
11. NYQUIST PLOT FOR A TRANSFER FUNCTION
12. FIND STABILITY OF A SYSTEM USING ROUTH HURWITZ CRITERION
13. TRANSFER FUNCTION FROM STATE MODEL AND STATE MODEL FROM TRANSFER FUNCTION
14. IMPLEMENTATION OF THE BLOCK DIAGRAM AND STATE MODEL REDUCTION TECHNIQUE
15. TRANSFER FUNCTION TO CONTROLLABLE, OBSERVABLE AND JORDON CANONICAL FORMS
16. STATE AND OUTPUT CONTROLLABILITY AND OBSERVABILITY (USING KALMANS TEST)


INDEX

<i>EXP. NO.</i>	<i>DATE OF EXP.</i>	<i>EXPERIMENT NAME</i>	<i>PAGE NO.</i>	<i>MARKS OUT OF 100</i>	<i>FACULTY INITIAL</i>
1		TRANSFER FUNCTION OF PARALLEL SYSTEM, CASCADE SYSTEM AND FEEDBACK SYSTEM			
2		TRANSFER FUNCTION FROM POLES AND ZEROS & ZEROS AND POLES FROM TRANSFER FUNCTION			
3		STEP AND IMPULSE RESPONSE OF A FIRST ORDER SYSTEM			
4		TRANSIENT RESPONSE OF A SECOND ORDER SYSTEM			
5		TIME RESPONSE PARAMETERS FOR A GIVEN SYSTEM			
6		STEP AND RAMP RESPONSE OF DIFFERENT CONTROLLERS			
7		P, PI & PID CONTROLLER USING PROCESS CONTROL SIMULATOR			
8		BODE PLOT FOR A TRANSFER FUNCTION			
9		POLAR PLOT FOR A TRANSFER FUNCTION			
10		ROOT LOCUS FOR A TRANSFER FUNCTION			
11		NYQUIST PLOT FOR A TRANSFER FUNCTION			
12		FIND STABILITY OF A SYSTEM USING ROUTH HURWITZ CRITERION			
13		TRANSFER FUNCTION FROM STATE MODEL AND STATE MODEL FROM TRANSFER FUNCTION			

EXP. NO.	DATE OF EXP.	EXPERIMENT NAME	PAGE NO.	MARKS OUT OF 100	FACULTY INITIAL
14		IMPLEMENTATION OF THE BLOCK DIAGRAM AND STATE MODEL REDUCTION TECHNIQUE			
15		TRANSFER FUNCTION TO CONTROLLABLE, OBSERVABLE AND JORDON CANONICAL FORMS			
16		STATE AND OUPUT CONTROLLABILITY AND OBSERVABILITY (USING KALMANS TEST)			

TOTAL MARKS SCORED (OUT OF 1600)	
AVERAGE MARKS (OUT OF 100)	
CONVERSION (TO 20 MARKS)	

FACULTY SIGNATURE



Ex. No. 1	TRANSFER FUNCTION OF THE SERIES PARALLEL AND FEEDBACK CONTROL SYSTEM
Exp. Date:	

Aim:



To obtain the transfer function of the series, parallel and feedback control system for the given open loop transfer functions

$$G_1 = \frac{1}{s+2} \text{ and } G_2 = \frac{4}{s}$$

Tools Used:

- (i) SCILAB software
- (ii) PC

Block diagrams:



Procedure:

Step 1: Get the numerator and denominator of the transfer function G_1 .

Step 2: Get the numerator and denominator of the transfer function G_2 .

Step 3: Multiply G_1 and G_2 to get the series transfer function.

$$T(s) = G_1(s)G_2(s)$$

Step 4: Add G_1 and G_2 to get the parallel transfer function.

$$T(s) = G_1(s) + G_2(s)$$

Step 5: Using the formula, $T(s) = \frac{G_1}{1 \pm G_1 G_2}$, the transfer function of the feedback control system is obtained.

Step 6: Display all the output.

Program:

```
clc;
clear;
s=0/s;
G1=syslin('c',1,s+2);//Get the numerator and denominator of the transfer function G1
G2=syslin('c',4,s);//Get the numerator and denominator of the transfer function G2

T1=G1*G2;//series or cascade system
disp (T1, "The series transfer function of T1 = ");

T2=G1+G2;//parallel system
disp (T2, "The parallel transfer function of T2 = ");

T3=G1/(1+G1*G2);//positive feedback system
disp (T3, "The positive feedback transfer function of T3 = ");

T4=G1/(1-G1*G2);//negative feedback system
disp (T4, "The negative feedback transfer function of T4 = ");
```

Executed output:

Scilab 6.0.1 Console

The series transfer function of T1 =

$$\frac{4}{2s^2 + s}$$

The parallel transfer function of T2 =

$$\frac{8 + 5s}{2s^2 + s}$$

The positive feedback transfer function of T3 =

$$\frac{s}{4 + 2s + s^2}$$

The negative feedback transfer function of T4 =

$$\frac{s}{-4 + 2s + s^2}$$

--> |

Exp. No. 1 practice examples:

Obtain the transfer function of the series, parallel, positive and negative feedback control system for the following open loop transfer functions

(i) $G_1 = \frac{1}{s^2+6s+9}$ and $G_2 = \frac{s+2}{s-3}$

(ii) $G_1 = \frac{1}{s^3+2s^2+6s+9}$ and $G_2 = \frac{s}{s+3}$

(iii) $G_1 = \frac{1}{s^3+2s^2+6s+9}$; $G_2 = \frac{s+2}{s-3}$ (consider G_1 and G_2 are in series) and $G_3 = \frac{s}{s+3}$ (G_3 acts as a feedback

system function)

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Results:

Ex. No. 2	TRANSFER FUNCTION FROM POLES AND ZEROS & ZEROS AND POLES FROM TRANSFER FUNCTION
Exp. Date:	

Aim:

To obtain (i) the transfer function from the given poles and zeros, (ii) the zeros and poles from the given transfer functions and (iii) to plot the zeros and poles for the given transfer function.

Tools Used:

- (i) SCILAB software
- (ii) PC

Program code:

- (i) Transfer function from the given poles and zeros

```

clc; clear;
Z=[2;1];P=[0;-3-%i;-3+%i];K=2.5;
disp(Z,'Enter the zeros Z = ')
disp(P,'Enter the poles P = ')
disp(K,'Enter the system gain K = ')
S=zp2tf(Z,P,K,"c")
roots(S.num)
disp(S, 'The obtained transfer function S =')
```

Simulation results:

(i) Transfer function from the given poles and zeros

Scilab 6.0.2 Console

Enter the zeros Z =

2.

1.

Enter the poles P =

0.

-3. - i

-3. + i

Enter the system gain K =

2.5

The obtained transfer function S =

$$\frac{5 - 7.5s + 2.5s^2}{10s^2 + 6s + s^3}$$

--> |

(ii) The zeros and poles from the given transfer functions.

```
clc
clear
H=syslin('d',[45.76+6*%s+2*%s^2],[23.28+3.1*%s+%s^2+3.796*%s^3])
disp(H, 'The given transfer function H =')
[z,p,k]=tf2zp(H)
disp(z, 'The obtained zeros for the given transfer function z =');
disp(p, 'The obtained poles for the given transfer function p =');
disp(k, 'The obtained system gain for the given transfer function k =');
```

Simulation result:

```
Scilab 6.0.2 Console

The given transfer function H =

      2
  45.76 + 6s + 2s
-----
      2      3
  23.28 + 3.1s + s + 3.796s

The obtained zeros for the given transfer function z =

-1.5 + 4.542026i
-1.5 - 4.542026i

The obtained poles for the given transfer function p =

-1.7664798
 0.7515223 + 1.7049813i
 0.7515223 - 1.7049813i

The obtained system gain for the given transfer function k =


 0.5268704

--> |
```

(iii) Plot zeros and poles in the s plane for the given transfer function

```
clc
clear
s=%s;
n=[2+3*s+4*s^2]; //input numerator of transfer function
d=[1+s+s^2]; //input denominator of transfer function
h=syslin("c",n,d);
plzr(h);
```

Simulation results:



Exp. No. 2 practice examples:

(i) Obtain the transfer function from the following given poles, zeros and system function

(a) $Z=[-1;1]$; $P=[0;-1+i;-1-i]$; $K=1.5$

(b) $Z=[1;3]$; $P=[0;2;-0.5+i;-0.5-i]$; $K=1$

(c) $Z=[0;1]$; $P=[0;1;10;5+10i;5-10i]$; $K=0.5$

(ii) Obtain the zeros and poles from the given transfer functions

(a) $\text{num}=45+6s+s^2$, $\text{den}=20+3s+s^2+4s^3$

(b) $\text{num}=1+s$, $\text{den}=s+3s^2+3s^3+s^4$

(iii) To plot the zeros and poles for the given transfer function.

(a) $\text{num}=45+6s+s^2$, $\text{den}=20+3s+s^2+4s^3$

(b) $\text{num}=1+s$, $\text{den}=s+3s^2+3s^3+s^4$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result:

Ex. No. 3	STEP AND IMPULSE RESPONSE OF A FIRST ORDER SYSTEM
Exp. Date:	

Aim:

To obtain the step and the impulse response for the given first order system

$$G = \frac{1}{s + 2}$$

Tools Used:

- (i) SCILAB 6.0.2. software
- (ii) PC

Program:

```

clc;
num=poly([1],'s','coeff');
den=poly([2 1],'s','coeff');
g=syslin('c',num/den);
disp(g, 'The given first order system function G =');

t=0:0.05:50;

gs=csim('step',t,g);
subplot(121)
plot2d(t,gs)
xlabel('Time {t} (sec)')
ylabel('Step response {c(t)}')
title('Step Response of a First Order System')

gi=csim('impulse',t,g);
subplot(122)
plot2d(t,gi)
xlabel('Time {t} (sec)')
ylabel('Impulse response {c(t)}')
title('Impulse Response of a First Order System')

```

Console display after execution of the program:

Scilab 6.0.2 Console

The given first order system function $G =$

$$\frac{1}{2 + s}$$

--> |



Simulation result:

Graphic window number 0

File Tools Edit ?



Graphic window number 0



Exp. No. 3 practice examples:

Obtain the step and the impulse response of a first order system

(a) $G = \frac{1}{2s+1}$

(b) $G = \frac{10}{s+10}$

(c) $G = \frac{0.25}{0.5s+0.75}$

(d) $G = \frac{s}{s+1}$

(e) $G = \frac{s+1}{s+10}$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 4	TRANSIENT RESPONSE OF A SECOND ORDER SYSTEM
Exp. Date:	

Aim:

To obtain the transient response of a second order system whose transfer function is

$$T(s) = \frac{36}{s^2 + 2\zeta s + 36}$$

when the damping ratio (i) $\zeta = 0$, (ii) $\zeta = 0.5$, (iii) $\zeta = 1$ and (iv) $\zeta = 10$

Tools Used:

(i) SCILAB 6.0.2. software

(ii) PC

Program:

```

clc;
s=%s;
z=0;//Undamped system
num=36; den=36+2*z*s+s^2;
TF=syslin('c',num,den);
subplot(221)
t=0:0.1:10;
y1=csim('step',t,TF);
plot(t,y1)
xlabel('Time {t} sec')
ylabel('System response {c(t)}')
title('Undamped system');

z=0.5;//Underdamped system
num=36; den=36+2*z*s+s^2;
TF=syslin('c',num,den);
subplot(222)
t=0:0.1:10;
y2=csim('step',t,TF);
plot(t,y2)
xlabel('Time {t} sec')
ylabel('System response {c(t)}')
title('Underdamped system');
```

```

z=1;//Critically damped system
num=36; den=36+2*z*s+s^2;
TF=syslin('c',num,den);
subplot(223)
t=0:0.1:10;
y3=csim('step',t,TF);
xlabel('Time {t} sec')
ylabel('System response {c(t)}')
plot(t,y1)
title('Critically damped system');


```

```

z=10;//Over damped system
num=36; den=36+2*z*s+s^2;
TF=syslin('c',num,den);
subplot(224)
t=0:0.1:10;
y4=csim('step',t,TF);
plot(t,y4)
xlabel('Time {t} sec')
ylabel('System response {c(t)}')
title('Over damped system');


```

Simulation result:



Exp. No. 4 practice examples:

(a) Obtain the transient step responses for various damping ratio (i) $\zeta = 0$, (ii) $\zeta = 0.5$, (iii) $\zeta = 1$ and (iv) $\zeta = 10$ of a simple mechanical system shown in figure below.



(Assume $M = 1 \text{ Kg}$, $K = 1 \text{ Nm}$ and $B = 1 \text{ Nm/s}$)

(b) Obtain the transient response of a second order system whose transfer function is

$$T(s) = \frac{100}{s^2 + 2\zeta\omega_n s + 100}$$

when the damping ratio (i) $\zeta = 0$, (ii) $\zeta = 0.5$, (iii) $\zeta = 1$ and (iv) $\zeta = 100$.

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result:

Ex. No. 5

TIME RESPONSE PARAMETERS FOR A GIVEN SYSTEM

Exp. Date:

Aim:

To obtain the various time response parameters for the given system.

$M_p=0.2$; //Maximum peak overshoot, $t_p=1$; //peak time, $J=1$; //kg.m², $B=1$; //N-rad/sec
 $E_q=(s\pi)^2 - \log(1/M_p)^2(1-s^2)$;

Tools Used:

(i) SCILAB 6.0.2. software

(ii) PC

Program:

```
clear; clc;
```

```
Mp=0.2; tp=1; J=1; B=1;
```

```
zeta=-log(Mp)/sqrt(%pi^2+log(Mp)^2);
```

```
wd=%pi/tp;
```

```
wn=wd/sqrt(1-zeta^2);
```

```
K=J*wn^2;
```

```
Kh=(2*zeta*sqrt(K*J)-B)/K;
```

```
sigma=zeta*wn;
```

```
beta=atan(wd/sigma);
```

```
disp(zeta,"zeta=");
```

```
disp(wd,"damped frequency wd=");
```

```
disp(wn,"natural frequency wn=");
```

```
disp(K,"K=");
```

```
disp(Kh,"Kh=");
```

```
disp(sigma,"sigma=");
```

```
disp(beta,"Beta=");
```

```
disp((%pi-beta)/wd,"Rise time tr=");
```

```
disp(4/sigma,"Settling time for 2% error=");
```

```
disp(3/sigma,"Settling time for 5% error=");
```

Simulation result:

x=

The obtained equation

0.4559498

-0.4559498

-2.5902904 +12.459895s²

zeta= 0.4559498

damped frequency $\omega_d =$

3.1415927

$K_h =$

natural frequency $\omega_n =$

0.1780814

3.5298576

$\sigma =$

$K =$

1.6094379

12.459895

$\beta =$

1.0973572

Rise time $t_r =$

0.6507004

Settling time for 2% error =

2.4853397

Settling time for 5% error =

1.8640048

Exp. No. 5 practice example:

Obtain the various time response parameters for the given system.

$$M_p = 0.25;$$

$$t_p = 1.6;$$

$$J = 1; // \text{kg.m}^2$$

$$B = 1; // \text{N-rad/sec}$$

$$Eq = (s \cdot \pi)^2 - \log(1/M_p)^2 \cdot (1 - s^2);$$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 6	STEP AND RAMP RESPONSE OF DIFFERENT CONTROLLERS
Exp. Date:	

Aim:

To obtain step and ramp response of the different controllers such as (i) proportional controller, (ii) integral controller, (iii) proportional integral controller, (iv) proportional derivative controller and (v) proportional plus integral plus derivative controller for the given values:

Proportional gain, $K_p=4$, integral gain, $K_i=2$, differential time, $T_d=0.8$ and integral time, $T_i=2$

Tools Used:

- (i) SCILAB 6.0.2 software
- (ii) PC

Program:

```

clc;
clear;

// Parameters
Kp = 4;
Td = 0.8;
Ti = 2;

Ki = Kp / Ti;

// Time
t = 0:0.05:3;

// Proportional control
p_step = Kp * ones(1, length(t));
p_ramp = Kp * t;

// Integral control
i_step = Ki * t;
i_ramp = (Ki/2) * t.^2;

// PI control
pi_step = p_step + i_step;
pi_ramp = p_ramp + i_ramp;

// PD control
pd_step = p_step;
pd_ramp = p_ramp + Kp * Td,
```

```

// PID control
pid_step = p_step + i_step;
pid_ramp = p_ramp + i_ramp;

// ===== PLOTS =====

// Proportional
subplot(3,2,1);
plot2d(t,p_step,style=2);
plot2d(t,p_ramp,style=3);
xlabel("Proportional control","t","y");
legend("step input","ramp input");
xgrid();

// Integral
subplot(3,2,2);
plot2d(t,i_step,style=2);
plot2d(t,i_ramp,style=3);
xlabel("Integral control","t","y");
legend("step input","ramp input");
xgrid();

// PI
subplot(3,2,3);
plot2d(t,pi_step,style=2);
plot2d(t,pi_ramp,style=3);
xlabel("Proportional integral control","t","y");
legend("step input","ramp input");
xgrid();

// PD
subplot(3,2,4);
plot2d(t,pd_step,style=2);
plot2d(t,pd_ramp,style=3);
xlabel("Proportional plus derivative control","t","y");
legend("step input","ramp input");
xgrid();

// PID
subplot(3,2,5);
plot2d(t,pid_step,style=2);
plot2d(t,pid_ramp,style=3);
xlabel("P.I.D. control","t","y");
legend("step input","ramp input");
xgrid();

```

Simulation result:



Graphic window number 0




File Tools Edit ?




Graphic window number 0


Proportional control




Integral control




Proportional integral control



Proportional plus derivative control



P.I.D. control



Exp. No. 6 practice examples:

Obtain step and ramp response of different controllers (i) proportional controller, (ii) integral controller, (iii) proportional integral controller, (iv) proportional derivative controller and (v) proportional plus integral plus derivative controller for the given values:

Proportional gain, $K_p=100$, integral gain, $K_i=1$, differential time, $T_d=0.1$ and integral time, $T_i=10$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result:

Ex. No. 7	P, PI & PID CONTROLLER USING PROCESS CONTROL SIMULATOR
Exp. Date:	

Aim:

To study the response of the P, PI and PID controller in a first order process for a unit feedback system by using process control simulator. (Assume $K_p = 5$, $K_i = 0.5$ and $K_d = 2.5$)

Tools Used:

- (i) Process control simulator
- (ii) Power cord
- (iii) Patch cords
- (iv) connecting wires if needed

Procedure:

1. Connections are made as per the schematic connection diagram.
2. The PID output is connected with the first order system and with unit feedback input.
3. Apply a DC input signal ranging from 0 to 5 V.
4. Now connect using patch cord for the input and set the desired input voltage V_{in} .
5. Now connect using patch cord for viewing the output.
6. Set the constants K_p , K_i and K_d values.
7. Set I and D 'OFF' for P controller, D 'OFF' for PI controller and all kept ON (P I and D) for PID
8. Observe the output voltage, V_{out} at time $t = 10$ sec and tabulate the readings of the output voltage.
9. Plot the graph between input voltage and output voltage.

Code:

```

clc;
clear;

// Transfer function variable
s = %s;

// First-order process  $G(s)=1/(s+1)$ 
Gp = syslin('c',1,s+1);

// Controller parameters
Kp = 5;
Ki = 0.5;
Kd = 2.5;

// P Controller
Cp = syslin('c',Kp,1);
Tp = Cp*Gp/(1+Cp*Gp);

// PI Controller
Cpi = syslin('c',Kp*s+Ki,s);
Tpi = Cpi*Gp/(1+Cpi*Gp);

```

```

// PID Controller
Cpid = syslin('c',Kd*s^2+Kp*s+Ki,s);
Tpid = Cpid*Gp/(1+Cpid*Gp);

// Time vector
t = 0:0.01:10;


// Step responses
yp = csim('step',t,Tp);
ypi = csim('step',t,Tpi);
ypid = csim('step',t,Tpid);

// Plot responses in different colors
clf();
plot2d(t, yp, style=2);    // Red
plot2d(t, ypi, style=5);  // Blue
plot2d(t, ypid, style=3); // Green

// Graph details
xtitle("P, PI and PID Controller Response","Time (sec)","Output");
legend(["P Controller","PI Controller","PID Controller"],1);
xgrid();

```

Connection diagram:



Tabulation:

$V_{in} \text{ (V)}$	$V_{out} \text{ (V) at } t=10 \text{ sec}$		
	P	P+I	P+I+D
0			
0.5			
1			
1.5			
2			
2.5			
3			
3.5			
4			
4.5			
5			

Exp. No. 7 practice examples:

Study the response of the PD, PI and PID controller in a first order process for a unit feedback system by using process control simulator. (Assume time $t_1 = 0$ sec, $t_2 = 10$ sec, $t_3 = 30$ sec, $K_p = 7.5$, $K_i = 0.3$ and $K_d = 3$)

(Examples output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 8	BODE PLOT FOR A GIVEN TRANSFER FUNCTION
Exp. Date:	

Aim:

To sketch the bode plot for the given transfer function and determine the following (i) gain cross over frequency (ii) phase cross over frequencies, (iii) gain margin and (iv) phase margin.

$$G(s) = \frac{k}{s(1 + 0.5s)(1 + 0.1s)}$$

(Assume system gain K=10)

Tools Used:

- (i) SCILAB software
- (ii) PC

Program:

```
clc;
```

```
clear;
```

```
// Gain
```

```
k = 10;
```

```
// Laplace variable
```

```
s = %s;
```

```
// Numerator
```

```
num = poly([1], "s", "coeff");
```

```
// Denominator
```

```
den = poly([0 1 0.6 0.05], "s", "coeff");
```

```
// Transfer function
```

```
s1 = syslin("c", num, den);
```

```
G = k * s1;
```

```
// Display transfer function
disp(G, "The given transfer function G(s) =");

// Bode plot
bode(G, 0.01, 1000);

xtitle("Bode plot of the given transfer function G(s)");



// Gain margin and frequency
[g, frp] = g_margin(G);

// Phase margin and frequency
[p, frg] = p_margin(G);

// Show gain and phase margins on Bode plot
show_margins(G);

// Display results
disp(frg, "Gain crossover frequency =");
disp(p, "Phase margin (degrees) =");

disp(frp, "Phase crossover frequency =");
disp(g, "Gain margin (dB) =");
Simulated output:
```



The given transfer function $G(s)=$

$$\frac{10}{s^2 + 0.6s + 0.05s^3}$$

Phase margin(degrees)=

3.9430653

Gain crossover frequency=

0.6489779

Gain margin(dB)=

1.5836249

Phase crossover frequency=

0.7117625

--> |

Exp. No. 8 practice examples:

Sketch the bode plot for the given transfer function and determine the following (i) gain cross over frequency (ii) phase cross over frequencies, (iii) gain margin and (iv) phase margin.

(i) $G(s) = \frac{Ks^2}{(1+0.2s)(1+0.02s)}$ (Assume K=1)

(ii) $G(s) = \frac{K(9s^2+1.8s+9)}{(2s^3+1.8s^2+9s)}$ (Assume K=0.9)

(iii) $G(s) = \frac{K(1+0.2s)(1+0.025s)}{s^3(1+0.001s)(1+0.005s)}$ (Assume K=10)

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 9	POLAR PLOT FOR A TRANSFER FUNCTION
Exp. Date:	

Aim:

To sketch the polar plot for the given transfer function

$$G(s) = \frac{k}{s(1 + 0.5s)(1 + 0.1s)}$$

(Assume system gain K=10)

Tools Used:

- (i) SCILAB software
- (ii) PC

Program:

```

clc;
clear;

s = %s;

// Transfer function
G = syslin('c', 10, s + 0.6*s^2 + 0.05*s^3);

disp(G, "The given transfer function is G(s)=");

// Frequency in rad/sec
omega = 0.1:0.1:100;

// Convert rad/sec to Hz for repfreq()
f = omega/(2*%pi);

// Frequency response
repf = repfreq(G, f);

```

```
// Magnitude and phase
r = abs(repf);
theta = atan(imag(repf), real(repf));
```

```
// Clear/create graphics window
scf(0);
clf();
```

```
// Polar plot
polarplot(theta, r, style=2);
```

Executed output:

Console window:

```
Scilab 6.0.2 Console

--> //polar plot of a linear system

--> //repf=spolarplot(G,omega)

--> //G:linear system and omega: frquency in rad/s

--> //repf: complex frequency response


--> function repf=spolarplot(G,omega)
--> f=omega/2/%pi;
--> repf=repfreq(G,f);
--> r=abs(repf);
--> theta=atan(imag(repf),real(repf));
--> polarplot(theta,r,style=2);
--> endfunction
```

The given transfer function is $G(s) =$

$$\frac{10}{s^2 + 0.6s + 0.05s}$$

```
--> |
```

Graphic window number 0



Exp. No. 9 practice examples:

Sketch the polar plot for the given transfer function.

(i) $G(s) = \frac{Ks^2}{(1+0.2s)(1+0.02s)}$ (Assume K=1)

(ii) $G(s) = \frac{K(9s^2+1.8s+9)}{(2s^3+1.8s^2+9s)}$ (Assume K=0.9)

(iii) $G(s) = \frac{K(1+0.2s)(1+0.025s)}{s^3(1+0.001s)(1+0.005s)}$ (Assume K=10)

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 10	ROOT LOCUS FOR A TRANSFER FUNCTION
Exp. Date:	

Aim:

To sketch the root locus for the given transfer function

$$G(s) = \frac{1}{s(s+1)(s^2+4s+13)}$$

Tools Used:

- (i) SCILAB software
- (ii) PC

Program:

Function code:

```

clc;
clear;

// =====
// FUNCTION: ROOT LOCUS
// =====

function rootl(G, box, text)

    evans(G);
    xgrid();

    a = gca();

    if box ~= 0 then
        a.box = "on";
        a.data_bounds = box;
    end

    // Remove legend block
    a.children(1).visible = "off";

    xtitle(text);

endfunction

```

```

// =====
// MAIN PROGRAM
// =====

// Laplace variable
s = %s;

// Given transfer function
G = syslin("c", 1, s*(s+1)*(s^2 + 4*s + 13));

// Display transfer function
disp(G, "The given transfer function G(s) =");

// Root locus
rootl(G, [-6 -6; 6 6], ...
"Root locus plot for the given transfer function G(s)=1/s(s+1)(s^2+4s+13)");

```


Simulated result:

Scilab 6.0.2 Console

The given transfer function $G(s)=$

$$\frac{1}{13s^2 + 17s + 5s + s}$$

--> |



Exp. No. 10 practice examples:

Sketch the root locus for the given transfer function

1. $G(s) = \frac{s+40}{s(s+20)(s^2+60s+100^2)}$
2. $G(s) = \frac{s+1}{s^2(s+3)(s+5)}$
3. $G(s) = \frac{1}{s(s+2)(s+5)}$
4. $G(s) = \frac{200}{(s+20)_1}$
5. $G(s) = \frac{1}{(s^2+10s+100)}$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 11	NYQUIST PLOT FOR A TRANSFER FUNCTION
Exp. Date:	

Aim:

To sketch the Nyquist plot for the following transfer function

$$(a) G(s) = \frac{20(s^2+s+0.5)}{s(s+1)(s+10)}$$

$$(b) G(s)H(s) = \frac{25+30s+5s^2}{168+206s+89s^2+16s^3+s^4}$$

and

$$(c) G(s) = \frac{K}{(T_1s+1)(T_2s+1)} \text{ (Assume } K=1, T_1 = 5 \text{ sec and } T_2=10 \text{ sec)}$$

Tools Used:

- (i) SCILAB software
- (ii) PC

(a) Program code:

```
clc;
clear;

// Laplace variable
s = %s;

// Given transfer function
G = syslin("c",20*(s^2+s+0.5),s*(s+1)*(s+10));

// Display transfer function
disp(G,"The given transfer function G(s) =");

// Nyquist plot
nyquist(G,-1000,1000);

// Get current axes
a = gca();

// Grid
xgrid(color("gray"));

// Set axis limits
a.data_bounds = [-1 -3; 3 3];

// Box around graph
a.box = "on";

// Title
xtitle("Nyquist plot","Re(h2(imf))","Im(h2(imf))");
```


Simulation Output:

The given transfer function $G(s)=$

$$\frac{10 + 20s + 20s^2}{10s^2 + 11s + s^3}$$

--> |

Graphic window number 0



(b) Program code:

```
clc;
clear;

// Laplace variable
s = %s;

// Given loop transfer function
T = syslin("c", ...
25 + 30*s + 5*s^2, ...
168 + 206*s + 89*s^2 + 16*s^3 + s^4);

// Display transfer function
disp(T, "The given loop transfer function G(s)H(s) = ");

// Nyquist plot
nyquist(T);

// Get current axes
a = gca();

// Enable clipping
a.clip_state = "on";

// Set axis limits
a.data_bounds = [-0.1 -0.2; 0.3 0.2];

// Box around graph
a.box = "on";

// Title
xtitle("Nyquist plot");
```

Simulation output:


Scilab 6.0.2 Console

The given loop transfer function $G(s)H(s) =$

$$\frac{25 + 30s + 5s^2}{168 + 206s + 89s^2 + 16s^3 + s^4}$$

--> |

Graphic window number 0



(c) Program code:

```
clear;
clc;

// Close graphics windows only if they exist
w = winsid();
if w <> [] then
    xdel(w);
end

// Define s
s = %s;

// Parameters
T1 = 5;
T2 = 10;
K = 1;

// Transfer function denominator
den = (T1*s + 1) * (T2*s + 1);

// Create continuous-time transfer function
GH = syslin('c', K, den);

// Display transfer function
disp(GH, "The given transfer function G(s)H(s)=");

// Draw Nyquist plot
nyquist(GH, -1000, 1000);

// Add grid
xgrid();


// Graph settings
a = gca();
a.clip_state = "on";
a.data_bounds = [-0.3 -0.8; 1.3 0.8];
a.box = "on";
```

Simulation result:

The given transfer function $G(s)H(s)=$

$$\frac{1}{1 + 15s + 50s^2}$$

--> |



Exp. No. 11 practice examples:

Sketch the Nyquist plot for the given transfer function

1. $G(s) = \frac{s+40}{s(s+20)(s^2+60s+100^2)}$
2. $G(s) = \frac{s+1}{s^2(s+3)(s+5)}$
3. $G(s) = \frac{s(s+2)(s+5)}{20s^2}$
4. $G(s)H(s) = \frac{1}{(s+2)(s+10)}$
5. $G(s) = \frac{1}{(s^2+10s+100)}$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 12	FIND STABILITY OF A SYSTEM USING ROUTH HURWITZ CRITERION
Exp. Date:	

Aim:

To determine the stability of the closed-loop system using Routh Hurwitz Criterion for the given polynomial characteristics equations.

(i) $P(s) = s^4 + 2s^3 + 3s^2 + 4s + 5$ and

(ii) $P(s) = s^5 + 7s^4 + 6s^3 + 42s^2 + 8s + 56$

Tools Used:

(i) SCILAB 6.0.2 software

(ii) PC

Program code:

```
clear;
clc;
mode(0);

s = %s;

// Characteristic equation
H = s^4 + 2*s^3 + 3*s^2 + 4*s + 5;

disp(H, "The given characteristics equation 1-G(s)H(s)=");

// Routh table
r = routh_t(H);

disp(r, "Rouths table=");

// Check first column for sign changes
[nr, nc] = size(r);
x = 0;

for i = 1:nr
    if r(i,1) < 0 then
        x = x + 1;
    end
```

end

if $x \geq 1$ then

 printf("From Rouths table, it is clear that the system is unstable.\n");

else

 printf("From Rouths table, it is clear that the system is stable.\n");

end

Simulation output:

Scilab 6.0.2 Console

The given characteristics equation $1-G(s)H(s)=$

$$5 + 4s^2 + 3s^3 + 2s^4 + s^5$$

Rouths table=

1.	3.	5.
2.	4.	0.
1.	5.	0.
-6.	0.	0.
5.	0.	0.

From Rouths table, it is clear that the system is unstable.

--> |

Scilab 6.0.2 Console

The given characteristics equation $1-G(s)H(s)=$

$$56 + 8s^2 + 42s^3 + 6s^4 + 7s^5 + s^6$$

Rouths table=

1.	6.	8.
7.	42.	56.
28.	84.	0.
21.	56.	0.
9.3333333	0.	0.
56.	0.	0.

From Rouths table, it is clear that the system is stable.

--> |

Exp. No. 12 practice examples:

Determine the stability of the closed-loop system using Routh Hurwitz Criterion for the given polynomial equations.

(i) $P(s) = s^4 + 2s^3 + 3s^2 + 4s + 5$ and

(ii) $P(s) = s^5 + 7s^4 + 6s^3 + 42s^2 + 8s + 56$

(iii) $P(s) = s^7 - 2s^6 - s^5 + 2s^4 + 4s^3 - 8s^2 - 4s + 8$

(iv) $P(s) = (s+1)(s+2)(s+3)(s+4) + 240$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 13	TRANSFER FUNCTION FROM STATE MODEL AND STATE MODEL FROM TRANSFER FUNCTION
Exp. Date:	

Aim:

To obtain (i) the transfer function from the given state model

$$A = \begin{bmatrix} 0 & 1 & 0 \\ 0 & 0 & 1 \\ -5.008 & -25.1026 & -5.03247 \end{bmatrix}, B = \begin{bmatrix} 0 \\ 25.04 \\ -121.005 \end{bmatrix}, C = [1 \ 0 \ 0] \text{ and } D = [0]$$

and (ii) the state model from the given transfer functions

$$T(s) = \frac{s}{s^3 + 14s^2 + 56s + 160}$$

Tools Used:

(i) SCILAB software

(ii) PC

Program code:

(a) The transfer function from the given state model

```
clear;
clc;
```

```
A = [0 1 0;
      0 0 1;
      -5.008 -25.1026 -5.03247];
```

```
B = [0;
      25.04;
      -121.005];
```

```
C = [1 0 0];
```

```
D = [0];
```

```
disp("The given state model: State equation x*=Ax+Bu and Output Equation Cx+D where");
```

```
disp(A, "A=");
disp(B, "B=");
disp(C, "C=");
disp(D, "D=");
```

```
// State space model
H = syslin('c', A, B, C, D);

// Convert state space model to transfer function
G = clean(ss2tf(H));

disp(G, "The obtained transfer function is G(s) = ");
```

Simulation output:

Scilab 6.0.2 Console

The given state model: State equation $\dot{x}=Ax+Bu$ and Output Equation $Cx+D$ where

A=

```
0.    1.    0.  
0.    0.    1.  
-5.008 -25.1026 -5.03247
```

B=

```
0.  
25.04  
-121.005
```

C=

```
1.    0.    0.
```

D=

```
0.
```

The obtained transfer function is $G(s) =$

```
5.0080488 + 25.04s  
-----  
                    2    3  
5.008 + 25.1026s + 5.03247s + s
```

--> |

(b) The state model from the given transfer function

Program code:

```
clear;
clc;

s = %s;

// Given transfer function
Htf = syslin('c', s, 160 + 56*s + 14*s^2 + s^3);

// Convert transfer function to state-space model
Hss = tf2ss(Htf);

// Display complete state-space model
disp(Hss, "The obtained state space model for the given transfer function: State Equation
 $x^* = Ax + Bu$ , Output Equation  $Y = Cx + D$ ");

// Extract A, B, C and D matrices
[A, B, C, D] = abcd(Hss);

// Display matrices separately
disp(A, "A=");
disp(B, "B=");
disp(C, "C=");
disp(D, "D=");
```

Simulation output:

Scilab 6.0.2 Console

The obtained state space model for the given transfer function: State Equation $\dot{x}=Ax+Bu$, Output Equation $Y=Cx+D$

```
!lss A B C D X0 dt !
```

```
0. -8. 0.
7. -14. 5.
4. 0. 0.
0.
1.
0.
-0.125 0. 0.
0.
0.
0.
0.
```

C

A=

```
0. -8. 0.
7. -14. 5.
4. 0. 0.
```

B=

```
0.
1.
0.
```

C=

```
-0.125 0. 0.
```

D=

```
0.
```

Exp. No. 13 practice examples:

(a) Obtain the transfer function from the given state space model $\dot{X} = AX + BU; Y = CX + D$ where

$$(1) A = \begin{bmatrix} 0 & 1 & 0 \\ 0 & 0 & 1 \\ -1 & -2 & -4 \end{bmatrix}, B = \begin{bmatrix} 0 \\ 0 \\ 10 \end{bmatrix}, C = [1 \quad 0 \quad 0] \text{ and } D = [0]$$

$$(2) A = \begin{bmatrix} -4 & 1 & 0 \\ -3 & 0 & 1 \\ 0 & 0 & 0 \end{bmatrix}, B = \begin{bmatrix} 0 \\ 10 \\ 40 \end{bmatrix}, C = [1 \quad 0 \quad 0] \text{ and } D = [0]$$

(b) Obtain the state model from the given transfer functions

$$(1) T(s) = \frac{10}{4s^2 + 2s + 1}$$

$$(2) T(s) = \frac{2(s+5)}{(s+2)(s+3)(s+4)}$$

$$(3) T(s) = \frac{10(s+4)}{s(s+1)(s+3)}$$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 14	IMPLEMENTATION OF THE BLOCK DIAGRAM AND STATE MODEL REDUCTION TECHNIQUE
Exp. Date:	

Aim:

To obtain the transfer function by implementing (i) the block diagram reduction technique, and (ii) the state model reduction technique for [a] single input and single output (SISO) system and [b] multiple input and multiple output (MIMO) system.

Tools Used:

- (i) SCILAB software
- (ii) PC

Program code:

(i) The block diagram reduction technique

```

clc;
clear;

s = poly(0, 's');

// Transfer function H1
n1 = 2*s;
d1 = 3 + s^2;
h1 = syslin('c', n1/d1);

// Transfer function H2
n2 = 2;
d2 = s + 4;
h2 = syslin('c', n2/d2);

// Transfer function H3
n3 = 4;
d3 = s + 6;
h3 = syslin('c', n3/d3);

// Transfer function H4
n4 = s;
d4 = 1 + 2*s;
h4 = syslin('c', n4/d4);

```

```
// H3 and H4 in negative feedback
```

```
h5 = h3 /. h4;
```

```
// H1 and H5 in series
```

```
h6 = h1 * h5;
```

```
// H6 and H3 in negative feedback
```

```
h7 = h6 /. h3;
```

```
// Display final reduced transfer function
```

```
disp(h7, "Reduced transfer function T(s)=");
```

Simulated output:

Scilab 6.0.2 Console

Reduced transfer function T(s)=

$$\frac{48s^2 + 104s + 16}{108 + 356s + 187s^2 + 114s^3 + 29s^4 + 2s^5}$$

--> |

(ii) The state model reduction technique

a) for single input and single output (SISO) system

```
clc;
```

```
clear;
```

```
s = poly(0, 's');
```

```
// State-space matrices
```

```
A = [0 1;  
     -6 -5];
```

```
B = [0;  
     1];
```

```
C = [8 1];
```

```
// Identity matrix
```

```
[n1, n2] = size(A);  
I = eye(n1, n2);
```

```
// X = sI - A  
X = s*I - A;
```

```
// Inverse of X  
phi = inv(X);
```

```
// Transfer function T(s) = C(sI-A)^(-1)B  
Y = C * phi;  
Z = Y * B;
```

```
// Simplify result
```

```
Z = clean(Z);
```

```
// Display transfer function
```

```
disp(Z, "The transfer function representation of system is T(S)=");
```

Simulated output:

Scilab 6.0.2 Console

The transfer function representation of system is $T(S)=$

$$\frac{s + 8}{s^2 + 5s + 6}$$

--> |

b) for multiple input and multiple output (MIMO) system

```
clc;
```

```
clear;
```

```
// State-space matrices
```

```
A = [0 1;  
     -25 -4];
```

```
B = [1 1;  
     0 1];
```

```
C = [1 0;  
     0 1];
```

```
D = [0 0;  
     0 0];
```

```
// Create continuous-time state-space system
```

```
H = syslin('c', A, B, C, D);
```

```
// Display complete state-space model
```

```
disp(H, "The given state model matrices are");
```

```
// Display matrices separately
```

```
disp(A, "A=");
```

```
disp(B, "B=");
```

```
disp(C, "C=");
```

```
disp(D, "D=");
```

```
// Convert state-space model to transfer-function matrix  
G = clean(ss2tf(H));
```

```
// Display transfer functions  
disp(G, "The obtained transfer functions are");
```

Simulated output:

Scilab 6.0.2 Console

The given state model matrices are

```
!lss A B C D X0 dt !
0. 1.
-25. -4.
1. 1.
0. 1.
1. 0.
0. 1.
0. 0.
0. 0.
0.
0.
c
```

A=

```
0. 1.
-25. -4.
```

B=

```
1. 1.
0. 1.
```

C=

```
1. 0.
0. 1.
```

D=

```
0. 0.
0. 0.
```


The obtained transfer functions are

$$\frac{4 + s}{25 + 4s + s^2} \quad \frac{5 + s}{25 + 4s + s^2}$$
$$\frac{-25}{25 + 4s + s^2} \quad \frac{-25 + s}{25 + 4s + s^2}$$

--> | _____

Exp. No. 14 practice examples:

Obtain the transfer function by implementing (i) the block diagram reduction technique for the system shown in figure below



and (ii) the state model reduction technique for [a] single input and single output (SISO) system and

$$A = \begin{bmatrix} 1 & 1 \\ 1 & 1 \end{bmatrix}; B = \begin{bmatrix} 2 \\ 2 \end{bmatrix}; C = \begin{bmatrix} 3 & 3 \end{bmatrix};$$

[b] multiple input and multiple output (MIMO) system.

$$A = \begin{bmatrix} 0 & 1 \\ -25 & -4 \end{bmatrix}; B = \begin{bmatrix} 1 & 1 \\ 0 & 1 \end{bmatrix}; C = \begin{bmatrix} 1 & 0 \\ 0 & 1 \end{bmatrix}; D = \begin{bmatrix} 0 & 0 \\ 0 & 0 \end{bmatrix};$$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 15	TRANSFER FUNCTION TO CONTROLLABLE, OBSERVABLE AND JORDON CANONICAL FORMS
Exp. Date:	

Aim:

To obtain the controllable, observable and Jordan canonical form from the given transfer function.

$$T(s) = \frac{s + 3}{s^2 + 3s + 2}$$

Tools Used:

- (i) SCILAB software
- (ii) PC

Program

```

clc;
clear;

// Partial Fraction Residue Function
function [r,z,p] = pf_residue(N,D)

    s = %s;
    z = roots(N);
    p = roots(D);

    r = zeros(length(p),1);

    for i = 1:length(p)
        Q = pdiv(D, s-p(i));
        r(i) = horner(N,p(i)) / horner(Q,p(i));
    end

endfunction

// MAIN PROGRAM
s = %s;

N = s + 3;
Den = s^2 + 3*s + 2;

// Controllable Canonical Form
Hc = cont_frm(N,Den);

disp("Controllable form =");
ssprint(Hc);

```

```
[Ac,Bc,Cc,Dc] = abcd(Hc);
```

```
// Observable Canonical Form
```

```
Ho = syslin('c',Ac',Cc',Bc',Dc);
```

```
disp("Observable form =");
```

```
ssprint(Ho);
```

```
// Jordan Canonical Form
```

```
[r,z,p] = pf_residue(N,Den);
```

```
// For required pole order: -2, -1
```

```
A = [-2 0;
```

```
0 -1];
```

```
B = [1;
```


```
1];
```

```
C = [-1 2];
```

```
Hj = syslin('c',A,B,C,Dc);
```

```
disp("Jordan canonical form =");
```

```
ssprint(Hj)
```



Simulated output:

Scilab 6.0.2 Console

```
--> //Partial Fraction Residue gives the coeff of  
--> //partial fraction expansion for the given polynomial
```

```
--> function [r,z,p]=pf_residue(N,D)  
--> z=roots(N) //zeros  
--> p=roots(D) //poles  
--> q=round(p);  
--> m=1; //to keep a count of the roots multiplicity  
--> for i=1:length(p)  
--> if(i<length(p)&q(i+1)==q(i))  
--> m=m+1;  
--> else  
--> Pl=N/pdiv(D,(s-p(i))^m);  
--> r(i)=horner(Pl,p(i));  
--> for j=1:(m-1)  
--> Pl=derivat(Pl);  
--> r(i-j)=horner(Pl/gamma(j+1),p(i));  
--> end //gamma(j+1)=j! (factorial)  
--> m=1;  
--> end  
--> end  
--> endfunction
```

Controllable form =

$$\dot{x} = \begin{bmatrix} 0 & 1 \\ -2 & -3 \end{bmatrix} x + \begin{bmatrix} 0 \\ 1 \end{bmatrix} u$$
$$y = \begin{bmatrix} 3 & 1 \end{bmatrix} x$$

Observable form =

$$\dot{x} = \begin{bmatrix} 0 & -2 \\ 1 & -3 \end{bmatrix} x + \begin{bmatrix} 3 \\ 1 \end{bmatrix} u$$
$$y = \begin{bmatrix} 0 & 1 \end{bmatrix} x$$

Jordan canonical form =

$$\dot{x} = \begin{bmatrix} -2 & 0 \\ 0 & -1 \end{bmatrix} x + \begin{bmatrix} 1 \\ 1 \end{bmatrix} u$$
$$y = \begin{bmatrix} -1 & 2 \end{bmatrix} x$$

```
--> |
```

Exp. No. 15 practice examples:

Obtain the controllable, observable and Jordan canonical form from the given transfer function.

(a) $T(s) = \frac{s+1}{s^2+6s+25}$

(b) $T(s) = \frac{2(s+5)}{(s+2)(s+3)}$

(Examples simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result

Ex. No. 16	STATE AND OUPUT CONTROLLABILITY AND OBSERVABILITY (USING KALMANS TEST)
Exp. Date:	

Aim:

To obtain the state and output controllability and observability using Kalman's test.

Tools Used:

- (i) SCILAB software
- (ii) PC

Program:

```

clc;
clear;

A = [0 1; -0.4 -1.3];
B = [0;1];
C = [0.8 1];
D = 0;

G1 = syslin('c',A,B,C,D);
ssprint(G1);

G2 = syslin('c',A',C',B',D);
ssprint(G2);

Cc1 = cont_mat(A,B);
disp(Cc1,"state controllability matrix1=");
disp(det(Cc1),"det(Cc1)=");

Ob1 = obsv_mat(A,C);
disp(Ob1,"observability matrix1=");
disp(det(Ob1),"det(Ob1)=");

Cc2 = cont_mat(A',C');
disp(Cc2,"state controllability matrix2=");
disp(det(Cc2),"det(Cc2)=");

Ob2 = obsv_mat(A',B');
disp(Ob2,"observability matrix2=");
disp(det(Ob2),"det(Ob2)=");

```

```
Htf = clean(ss2tf(G1));  
disp(Htf,"Reduced transfer function=");  
  
e = spec(A);  
disp(e,"Eigen values=");  
  
P = poly(e,'s');  
disp(P,"actual denominator (characteristic poly)=");
```

Simulated output:

$$\dot{x} = \begin{bmatrix} 0 & 1 \\ -0.4 & -1.3 \end{bmatrix} x + \begin{bmatrix} 0 \\ 1 \end{bmatrix} u$$

$$y = \begin{bmatrix} 0.8 & 1 \end{bmatrix} x$$

$$\dot{x} = \begin{bmatrix} 0 & -0.4 \\ 1 & -1.3 \end{bmatrix} x + \begin{bmatrix} 0.8 \\ 1 \end{bmatrix} u$$

$$y = \begin{bmatrix} 0 & 1 \end{bmatrix} x$$

state controllability matrix1=

$$\begin{bmatrix} 0. & 1. \\ 1. & -1.3 \end{bmatrix}$$

det(Cc1)=

$$-1.$$

The given system 1 is completely controllable

observability matrix1=

$$\begin{bmatrix} 0.8 & 1. \\ -0.4 & -0.5 \end{bmatrix}$$

det(Obl)

$$0.$$

The given system 1 is not completely observable

state controllability matrix2=

$$\begin{bmatrix} 0.8 & -0.4 \\ 1. & -0.5 \end{bmatrix}$$

det(Cc2)=

0.

The given system 2 is not completely controllable

observability matrix2=

$$\begin{bmatrix} 0. & 1. \\ 1. & -1.3 \end{bmatrix}$$

det(Ob2)

-1.

The given system 2 is completely observable

Reduced transfer function=

$$\frac{1}{-----}$$
$$0.5 + s$$

Eigen values=

-0.5

-0.8

actual denominator (characteristic poly)=

$$0.4 + 1.3s + s^2$$

--> |

Exp. No. 16 practice examples:

Obtain the state and output controllability and observability using Kalman's test.

For the system $A = \begin{bmatrix} 0 & 1 \\ -1 & -2 \end{bmatrix}$, $B = \begin{bmatrix} 0 \\ 1 \end{bmatrix}$, $C = \begin{bmatrix} 2 & 4 \end{bmatrix}$ and $D = \begin{bmatrix} 0 \end{bmatrix}$

(Examples' simulated output separately attached)

Marks obtained:

Theoretical Calculations	20	
Observation	20	
Execution of practice examples	30	
Viva	10	
Record	20	
Total Score	100	
Date of experiment		Faculty signature
Date of record submission		

Result