Charles University in Prague Faculty of Mathematics and Physics

ODCleanStore

Linked Data management tool

Administrator's & Installation Manual

Release 1.0.0 November 29, 2012

Authors: Jan Michelfeit

Dušan Rychnovský

Jakub Daniel Petr Jerman Tomáš Soukup

Supervisor: RNDr. Tomáš Knap

Contents

1	Introduction	5		
2	System Requirements 2.1 OpenLink Virtuoso			
3	Step by Step Installation Guide3.1 Prerequisities3.2 Using the Installer3.3 Post-installation Steps	Ć		
4	Starting and Stopping the Application 4.1 Engine			
5	Trying out ODCleanStore	17		
6	6 Configuration Options			
7	7 Custom Transformers			
A	A Distribution Contents			
\mathbf{R}	License	31		

4 CONTENTS

1. Introduction

ODCleanStore is a server application for management of Linked Data. It stores data in RDF, processes them and provides integrated views on the data.

This document serves as the installation guide and manual for system administrators. It includes system requirements, installation instructions, configuration overview, manual how to start the application and basic information about extending ODCleanStore's data processing capabilities by adding *custom transformers*.

What is ODCleanStore

ODCleanStore accepts arbitrary RDF data and metadata through a SOAP webservice (Input Webservice). The data is processed by transformers in one of a set of customizable pipelines and stored to a persistent store (OpenLink Virtuoso database instance). The stored data can be accessed again either directly through a SPARQL endpoint or through Output Webservice. Linked Data consumers can send queries and custom query policies to Output Webservice and receive (aggregated/integrated) RDF data relevant for their query, together with information about provenance and data quality.

Related documents

More detailed information about ODCleanStore from the perspective of a user can be found in related document "User Manual". It also contains definition of user roles, glossary of terms etc. Document "Programmer's Guide" contains more detailed information intended primarily for developers, system administrators, however, may also find interesting in-depth information in Programmer's Guide.

2. System Requirements

ODCleanStore is a multiplatform application written in Java. These are the system requirements for installing and running ODCleanStore:

- Operating System: Windows XP, Windows 7, Windows Server 2008, Linux
- Java Runtime Environment 6 or newer¹
- Installed OpenLink Virtuoso² (see below)
- Apache Tomcat³ (or an equivalent Java servlet container)

2.1 OpenLink Virtuoso

ODCleanStore uses two instances of Virtuoso database for storing data – one is used for storing data that are currently being processed (*dirty database instance*) and the other for already processed data visible to end users (*clean database instance*).

ODCleanStore requires that the two instances of Virtuoso database are created before the installation process. If you are familiar with Virtuoso and already have two Virtuoso instances that you would like to use, you can skip the rest of this section – make sure, however, to modify ODCleanStore configuration options accordingly (see Chapter 6). In particular, set correct database settings and include a directory specified in engine.clean_import_export_dir and engine.dirty_import_export_dir configuration options in DirsAllowed option of Virtuoso configuration. The user account which is used to run Engine must have permissions to both read and write in the directory.

2.1.1 Creating Database Instances

Virtuoso has a paid enterprise license, but also an open source edition⁴ available for free. In order to install it, follow instructions on the download page. Make sure that the deployed binaries (<installation-directory>/bin) are on your system PATH. You can test it by running commands isql (check that it is the Virtuoso isql) and virtuoso-t. If isql cannot be on PATH for any reason, pass the full path to the executable as a parametr of the installer.

ODCleanStore distribution contains files virtuoso.ini-clean and virtuoso.ini-dirty. While it is not required, we strongly recommend creating the two database instances with these provided configuration files.

- 1. Create one empty directory for each database instance.
- 2. Copy virtuoso.ini-clean to the directory for the clean database instance, create a copy of the file and name it virtuoso.ini. If you are familiar with Virtuoso, you may customize configuration in virtuoso.ini according to your needs.
- 3. Create a new database instance by executing

virtuoso-t +service create +instance odcsclean +configfile virtuoso.ini

¹http://www.java.com/en/download/

²http://virtuoso.openlinksw.com/

³http://tomcat.apache.org/

⁴http://virtuoso.openlinksw.com/dataspace/dav/wiki/Main/VOSDownload

in the directory for the clean database instance.

4. Start the newly creted database instance by executing

virtuoso-t +service start +instance odcsclean

- 5. Copy virtuoso.ini-dirty to the directory for the dirty database instance created in step 1. Create a copy of the file and name it virtuoso.ini. If you are familiar with Virtuoso, you may customize configuration in virtuoso.ini according to your needs.
- 6. Create a new database instance by executing

```
virtuoso-t +service create +instance odcsdirty +configfile virtuoso.ini
```

in the directory for the dirty database instance.

7. Start the newly creted database instance by executing

```
virtuoso-t +service start +instance odcsdirty
```

Security note. Don't forget to change credentials for your database instance.

3. Step by Step Installation Guide

ODCleanStore can be installed with a provided installer with graphical interface.¹

3.1 Prerequisities

Before installation, make sure your system satisfies requirements listed in Chapter 2. In particular, make sure to have two Virtuoso database instances created and *started* before installation, as described in Section 2.1.

3.2 Using the Installer

In order to run the installer, execute in the root directory of the distribution:

```
./odcs-installer.sh
```

on Linux, or run

```
odcs-installer.bat
```

on Windows. This should start the installer. If the Virtuoso's isql executable is not on system PATH for any reason, you must pass the full path to the installer manually:

```
java -jar bin/odcs-installer-<version>.jar <full-path-to-Virtuoso-isql>
```

On the first screen of the installer, choose the directory where ODCleanStore binaries should be installed.




On the second screen, you can enter the directory where Administration Frontend web archive will be deployed. This should be a directory for web applications of your servlet container. In Tomcat, for example, it would be \$CATALINA_BASE/webapps.

¹Alternatively, ODCleanStore can be deployed manually. Steps for the manual installation are described in the README.txt file in the distribution, the manual installation is intended for experienced users and developers, however, and is not officially supported.




Next, enter the connection settings for the clean and dirty Virtuoso database instances. See Section 2.1 for more information about Virtuoso database instances.




After entering valid connection settings, the installer starts the installation process. The installer will:

1. Copy Engine binaries and related files to the chosen Engine installation directory.




- 2. Copy the default configuration file to the Engine installation directory.
- 3. Initilize database instances:

(a) Clear old tables in the clean database, if there are any.



(b) Import new database tables in the clean database.




(c) Create a fulltext index for RDF data in clean database (in order to enable keyword queries).



(d) Clear old tables in the dirty database, if there are any.



(e) Import new database tables in the dirty database.



4. Adjust Administration Frontend web archive so that it contains a proper path to the de-

ployed configuration file and copy it to the chosen Administration Frontend installation directory.

If the installation was successfull, the last screen of the installer is displayed, or an error message describing what went wrong is displayed otherwise.



3.3 Post-installation Steps

After successfull install, you may customize default ODCleanStore settings in the configuration file odcs.ini in the Engine installation directory. See Chapter 6 for description of all options.

The installer deploys the web archive with Administration Frontend to the designated directory in your servlet container. Depending on the configuration of your servlet container, you may need to add the Administration Frontend web application to its configuration explicitly. If that is the case, in Tomcat, for example, this can be accomplished by adding a line similar to the following to <Host> section of Tomcat's server.xml:

```
<Context path="" docBase="{path to odcs-webfrontend-<version>.war}"> </Context>
```

After a clean installation, Administration Frontend contains two user accounts: an administrator account with username "adm", password "adm", and a user in the Data Producer (SCR) role with username "scraper", password "reparcs". For security reasons, **make sure to change the default credentials**. Also, the installer creates a user "SILK" with password "odcs" in the dirty database instance and grants it the SPARQL_UPDATE role. You should change the credentials for this user and update the affected db.dirty_update.sparql.* configuration options in odcs.ini.

4. Starting and Stopping the Application

4.1 Engine

ODCleanStore Engine can be started by executing the run-engine.cmd script (on Windows) or run-engine.sh script (on Unix) in the installation directory of ODCleanStore Engine. The Engine will load its configuration from the odcs.ini file in this directory and, after initialization, automatically start listening on Input and Output Webservice ports for requests.

In order to stop Engine, simply press Ctrl+C in the console window with Engine (send SIGINT signal to the Engine process on Linux). Engine will shutdown all services, wait (up until a timeout) until the currently active pipeline transformer finishes, and stop.

Engine is also prepared to be run as a system service on Windows, or daemon on Linux, respectively. Installing ODCleanStore as a service/daemon will be added to the installer in future.

4.2 Administration Frontend

Administration Frontend is a standard Java web application and its lifecycle depends on its servlet container – please refer to documentation of your server container¹. Usually, Administration Frontend would be reached by navigating to http://localhost:8080/ in your web browser. Please note that Administration Frontend also needs the clean Virtuoso database instance to be running.

¹E.g. http://tomcat.apache.org/tomcat-7.0-doc/index.html

5. Trying out ODCleanStore

When Engine is started and Administration Frontend successfully deployed, you may try out ODCleanStore.

ODCleanStore can be managed from Administration Frontend in your web browser. Navigate to the address where it is deployed by your servlet container (e.g. http://localhost:8080/). By default, there is a single administrator account with username "adm" and password "adm". In order to add new data processing pipelines in Administration Frontend, you will need to create a new user account, or add more roles to the default administrator account (log out and log in again for the changes to take effect).




Figure 5.1: Administration Frontend– adding a new account

There should be one default pipeline created by default. You may customize it by assigning transformers to it. The functionality of Input and Output Webservices can be then demonstrated:

Sending data to ODCleanStore. To send data to Input Webservice, you can execute run-example.cmd or run-example.sh (on Windows or Linux, respectively) from directory example/ in the distribution. The script will send data in example-data.rdf to Input Webservice together with metadata in example-metadata.properties and example-provenance-metadata.rdf

Parameters for Input Webservice can be changed in example-metadata.properties, most notably the name of the pipeline to process the data in the pipelineName option (the default pipeline will be used when none is specified) and location of Input Webservice.

Script regenerate-uuid.cmd (regenerate-uuid.sh) runs an utility that regenerates UUID in example-metadata.properties. This is necessary because every request to Input Webservice needs to have an unique UUID.

Querying over data. To query the stored data using Output Webservice, start with query-*.html documents in the example-queries/ subdirectory of the distribution. You can find more detailed information in User Manual.

URI query for http://dbpedia.org/resource/Berlin. Query executed in 1.569 s.

Subject	Predicate	Object	Quality	Source named graphs
dbpedia: Berlin	dbo:country	dbpedia: Germany	0.90000	http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/dbpedia
dbpedia: Berlin	http://linkedgeodata.org/property /capital	"yes"	0.80000	http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/linkedgeodata
dbpedia: Berlin	rdfs:label	"Berlin"	0.94252	http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/linkedgeodata, http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/geonames, http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/dppedia, http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/freebase
dbpedia: Berlin	freebase:location.geocode.longtitude	"13.402740096987914" ^^xsd:double	0.82446	http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/linkedgeodata, http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/dbpedia, http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/genames, http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/freebase
dbpedia: Berlin	rdf: type	http://schema.org/City	0.92000	http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/dbpedia, http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/freebase
dbpedia: Berlin	rdf: type	http://schema.org/Place	0.90000	http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/dbpedia
dbpedia: Berlin	rdf: type	http://umbel.org/umbel /rc/Village	0.90000	http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/dbpedia
dbpedia: Berlin	rdf: type	http://www.geonames.org /ontology#Feature	0.80000	http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/geonames

Source graphs:							
Named graph	Data source	Inserted at	Graph score	License	Update tag		
http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin /dbpedia	http://dbpedia.org/page/Berlin	2012-04-01 12:34:56.0	0.9				
http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin/error	http://example.com		0.8				
http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin /freebase	http://www.freebase.com/view/en/berlin	2012-04-02 12:34:56.0	0.8				
http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin /geonames	http://www.geonames.org/2950159 /berlin.html	2012-04-03 12:34:56.0	0.8				
http://odcs.mff.cuni.cz/namedGraph/qe-test/berlin /linkedgeodata	http://linkedgeodata.org /page/node240109189	2012-04-04 12:34:56.0	0.8				
http://odcs.mff.cuni.cz/namedGraph/qe-test/germany /dbpedia	http://dbpedia.org/page/Germany	2012-04-05 12:34:56.0	0.9				

Figure 5.2: Sample results of an URI query

6. Configuration Options

Global configuration options for ODCleanStore are stored in configuration file odcs.ini in the Engine installation directory.

The configuration file is used both by ODCleanStore Engine and administration frontend. Configuration options are loaded only once when the Engine or administration frontend is started, therefore, it is necessary to restart the Engine or administration frontend web application for the changes to take effect.

List with a description of all configuration options follows:

Database Configuration

db.clean.jdbc.connection_string

Connection string for JDBC access to the Virtuoso instance representing the clean database. Must contain connection charset.

Default value: jdbc:virtuoso://localhost:1111/CHARSET=UTF-8

db.clean.jdbc.username

Username for JDBC access to the Virtuoso instance representing the clean database.

Default value: dba

db.clean.jdbc.password

Password for JDBC access to the Virtuoso instance representing the clean database.

Default value: dba

db.clean.sparql.endpoint_url

URL of the SPARQL endpoint of the clean database. Used by Linker to read RDF data.

Default value: http://localhost:8890/sparql

db.dirty.jdbc.connection_string

Connection string for JDBC access to the Virtuoso instance representing the dirty database. Must contain connection charset.

Default value: jdbc:virtuoso://localhost:1112/CHARSET=UTF-8

db.dirty.jdbc.username

Username for JDBC access to the Virtuoso instance representing the dirty database.

Default value: dba

db.dirty.jdbc.password

Password for JDBC access to the Virtuoso instance representing the dirty database.

db.dirty.sparql.endpoint_url

URL of the SPARQL endpoint of the dirty database. Used by Linker to read RDF data. Default value: http://localhost:8891/sparql

db.dirty_update.sparql.endpoint_url

URL of the secured SPARQL endpoint of the dirty database. Used by Linker to store

created links.

Default value: http://localhost:8891/sparql-auth

db.dirty_update.sparql.endpoint_username

Name of the user, who is authorized for using SPARQL UPDATE on the authorized endpoint.

Default value: SILK

db.dirty_update.sparql.endpoint_password

Password of the user, who is authorized for using SPARQL UPDATE on the authorized endpoint.

Default value: odcs

Input Webservice Configuration

input_ws.endpoint_url

URL where the input webservice is listening.

Default value: http://localhost:8088/inputws

input_ws.recovery_crash_penalty

Waiting penalty after Input Webservice recovery crash before recovery restart in milliseconds.

Default value: 60000

input_ws.named_graphs_prefix

Prefix of named graphs incoming where data & metadata are stored. Must be a valid URL.

Default value: http://opendata.cz/infrastructure/odcleanstore/

Output Webservice Configuration

output_ws.result_data_prefix

Prefix of named graphs and URIs where query results and metadata in the output are placed.

Default value: http://opendata.cz/infrastructure/odcleanstore/query/

output_ws.port

Port of the output webservice

Default value: 8087

output_ws.keyword_path

Relative path fragment for the keyword query over the output webservice.

Default value: keyword

output_ws.uri_path

Relative path fragment for the uri query over the output webservice.

Default value: uri

output_ws.metadata_path

Relative path fragment for the metadata query over the output webservice.

Default value: metadata

output_ws.named_graph_path

Relative path fragment for the named graph query over the output webservice.

Default value: namedGraph

Query Execution Configuration

query_execution.max_query_result_size

Maximum number of results allowed in each database query performed during a query execution. This option effectively affects the maximum number of results returned in response to a query through Ouptut Webservice to a multiple of this number (cca 3 times the value of this option).

Default value: 500

Conflict Resolution Configuration

conflict_resolution.agree_coefficient

Agree coefficient used in aggregated quality formula – value N means that agreement of N+1 sources with score 1 on the same value will increase the quality of that value to 1. Default value: 4

conflict_resolution.score_if_unknown

Graph score used if none is given in the input of Conflict Resolution (e.g. is unknown). Default value: 1

conflict_resolution.named_graph_score_weight

Weight of the named graph score in aggregated quality calculation (see conflict_resolution.publisher_score_weight)

Default value: 0.8

conflict_resolution.publisher_score_weight

Weight of the graph publisher's score in aggregated quality calculation (see conflict_resolution.named_graph_score_weight)

Default value: 0.2

conflict resolution.max date difference

Difference between two dates when their distance is equal to MAX_DISTANCE constant, given in seconds. When the difference of two dates is higher or equal to this value, in Conflict Resolution, they are considered to be totally different; when the difference is smaller, the difference coefficient is proportionally smaller.

Default value: 31622400 (366 days)

Transformers Configuration

object_identification.link_within_graph

Sets whether to link incoming data against itself by default.

Default value: true

object_identification.link_attachd_graphs

Sets whether to link data from attached graphs created by preceding transformers by default.

Default value: true

Engine & Backend Configuration

backend.query_timeout

Timeout for database queries executed by predefined transformers, Query Execution and Engine in seconds.

Default value: 30

engine.clean_import_export_dir

Directory for Clean Virtuoso instance data import and export files. Base for relative path is clean db server root (directory of the Virtuoso INI file). Path or his parent must be specified in the DirsAllowed param in the virtuoso INI file and the Virtuoso server restarted for access to be allowed to the files by Virtuoso.

Default value: odcs/

engine.dirty_import_export_dir

Directory for Dirty Virtuoso instance data import and export files. Base for relative path is clean db server root (directory of the Virtuoso INI file). Path or his parent must be specified in the DirsAllowed param in the virtuoso INI file and the Virtuoso server restarted for access to be allowed to the files by Virtuoso.

Default value: odcs/

engine.startup_timeout

Maximum time in milliseconds for services initializing before engine shutdown.

Default value: 30000

engine.shutdown_timeout

Maximum time in milliseconds for services shutdown before engine exit.

Default value: 30000

engine.look_for_graph_interval

Additional timer setting interval for lookup for graph for processing in milliseconds.

Default value: 8000

engine.second_crash_penalty

Waiting penalty after double pipeline crash before pipeline restart in milliseconds.

Default value: 60000

engine.state_to_db_writing_interval

Interval for writing engine state information to db in milliseconds.

Default value: 5000

engine.engine_uuid

Identifier of Engine instance when data processing is distributed over multiple parallel nodes. This setting has currently no effect and is reserved for future extensions.

Administration Frontend Configuration

web_frontend.gmail_address

Username of a GMAIL accout to send emails through.

Default value: odcleanstore@gmail.com

web_frontend.gmail_password

Password of a GMAIL accout to send emails through.

Default value: odcleanstore2012

web_frontend.output_ws_host

Output webservice host.

Default value: http://localhost

web_frontend.debug_directory_path

Path to transformer directory for debugging.

Default value: ./odcs-debug

7. Custom Transformers

The administrator may extend data-processing capabilities of ODCleanStore by adding new custom transformers. In order to start using the transformer:

- 1. Implement your custom transformer by implementing the Transformer interface in Java or other compatible language.
 - The classfile for the Transformer interface is in bin/odcs-core-<version>.jar file in the ODCleanStore distribution, or can be obtained from sources in odcs-core maven artifact see Chapter "Setting up Development Environment" in Programmer's Guide. For more information about how to implement a custom transformer and what features it should have, please refer to chapter "Transformers Introduction" in Programmer's Guide.
- 2. Save the .jar file with the implementing classfiles to a location where Engine can read it from the filesystem. The classfiles of the odcs-core maven artifact need not be included in the .jar file (as they will be already loaded by Engine when the custom transformer is loaded at runtime).
- 3. In Administration Frontend, go to "Transformers" > "Add a new transformer" (Figure 7.1). Enter the path to the .jar file with the implementation, the fully qualified name of your class that implements the Transformer interface and fill in the other fields. Submit the form.
- 4. Now, the custom transformer is registered and can be assigned to pipelines and used for data processing.




Figure 7.1: Screen for registering a custom transformer

A. Distribution Contents

The distribution archive or CD contains ODCleanStore binaries, installer, documentation and some testing data. For a quick start, the relevant files for you are README.txt and scripts install.cmd or install.sh (for Windows or Linux, respectively) which start the installer.

Meaning of the other files and directories is explained below.

bin/ Contains all Java binaries of ODCleanStore.

engine/

Contains binaries and dependencies for Engine part of ODCleanStore.

webapp/

Contains the Administration Frontend web archive.

utils/

Contains utilities. regenerateUUID.jar Generates a new UUID for metadata file used by odcs-simplescraper. frontend-config.jar is a utility for updating of path to the ODCleanStore configuration file in the Administration Frontend web archive.

odcs-installer-< version>.jar

Installer with a graphical user interface.

odcs-simplescraper-<version>.jar

A simple utility for testing of sending of data to Input Webservice.

odcs-simpletransformer-<version>.jar

A simple example of a custom transformer.

odcs-core-< version>.jar

odcs-core artifact. This can be used as a library when writing custom transformers, as it contains definition of the Transformer interface and other related classes.

run-engine.cmd, run-engine.sh

Scripts that start Engine for case of a manual installation.

update-war-path.cmd, update-war-path.sh

Scripts that update path to global configuration file in the Administration Frontend web archive. Supplied for convenience in case of manual installation.

config/ Contains the default configuration file for ODCleanStore and recommended configuration files for Virtuoso database instances.

odcs.ini

The default global configuration file of ODCleanStore.

virtuoso.ini-clean

The recommended configuration file for the clean database instance of Virtuoso.

virtuoso.ini-dirty

The recommended configuration file for the dirty database instance of Virtuoso.

database/ Scripts for initialization of database instances.

install/

SQL scripts used by the installer.

clean_db/

SQL scripts for manual import for the clean database instance.

dirty_db/

SQL scripts for manual import for the dirty database instance.

doc/ Documentation for ODCleanStore.

javadoc/

API documentation of ODCleanStore sources in generated from javadoc.

LICENSE.txt

License under which ODCleanStore is distributed.

ODCleanStore User Manual.pdf

Documentation for ODCleanStore users.

 ${\tt ODCleanStore}\ {\tt Administrator's}\ {\tt and}\ {\tt Installation}\ {\tt Manual.pdf}$

This document.

ODCleanStore Programmer's Guide.pdf

Detailed documentation intended for developers.

sourceforge.txt

Link to the project homepage.

example / Example data that can be send to Input Webservice.

example-data.rdf, example-data-isvzus.ttl

The actual payload data to be sent to Input Webservice.

 $\verb|example-metadata.properties|, example-metadata-isvzus.properties|\\$

Property file with metadata sent together with payload data.

example-provenance-metadata.rdf

Example provenance metadata to be sent together with payload data.

run-example.cmd, run-example-isvzus.cmd

Script that sends the example data to Input Webservice.

regenerate-uuid.cmd

Script for updating UUID in metadata property files. This is necessary as every new input graph needs to have a unique UUID.

example-queries/ Simple forms in HTML that can be used for querying over Output Webservice. These forms are provided for testing and debugging purposes.

query-uri.html

Form for executing a URI query via Output Webservice.

query-keyword.html

Form for executing a keyword query via Output Webservice.

query-named-graph.html

Form for executing a named graph query via Output Webservice.

query-metadata.html

Form for executing a metadata query via Output Webservice.

README.txt File with basic information and instructions how to start with ODCleanStore.

release-notes.txt Release notes with information about changes between versions.

install.cmd, install.sh Scripts for starting the installer in Windows and Unix, respectively.

B. License

ODCleanStore is released as open source software under Apache License, Version 2.0.

Apache License
Version 2.0, January 2004
http://www.apache.org/licenses/

TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION

1. Definitions.

"License" shall mean the terms and conditions for use, reproduction, and distribution as defined by Sections 1 through 9 of this document.

"Licensor" shall mean the copyright owner or entity authorized by the copyright owner that is granting the License.

"Legal Entity" shall mean the union of the acting entity and all other entities that control, are controlled by, or are under common control with that entity. For the purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object

form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including
the original version of the Work and any modifications or additions
to that Work or Derivative Works thereof, that is intentionally
submitted to Licensor for inclusion in the Work by the copyright owner
or by an individual or Legal Entity authorized to submit on behalf of
the copyright owner. For the purposes of this definition, "submitted"
means any form of electronic, verbal, or written communication sent
to the Licensor or its representatives, including but not limited to
communication on electronic mailing lists, source code control systems,
and issue tracking systems that are managed by, or on behalf of, the
Licensor for the purpose of discussing and improving the Work, but
excluding communication that is conspicuously marked or otherwise
designated in writing by the copyright owner as "Not a Contribution."

"Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a Contribution has been received by Licensor and subsequently incorporated within the Work.

- 2. Grant of Copyright License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.
- 3. Grant of Patent License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work or a Contribution incorporated within the Work constitutes direct

or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.

- 4. Redistribution. You may reproduce and distribute copies of the Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:
 - (a) You must give any other recipients of the Work or Derivative Works a copy of this License; and
 - (b) You must cause any modified files to carry prominent notices stating that You changed the files; and
 - (c) You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and
 - (d) If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents of the NOTICE file are for informational purposes only and do not modify the License. You may add Your own attribution notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License.

You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use, reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

- 5. Submission of Contributions. Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions.

 Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.
- 6. Trademarks. This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.
- 7. Disclaimer of Warranty. Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A PARTICULAR PURPOSE. You are solely responsible for determining the appropriateness of using or redistributing the Work and assume any risks associated with Your exercise of permissions under this License.
- 8. Limitation of Liability. In no event and under no legal theory, whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.
- 9. Accepting Warranty or Additional Liability. While redistributing the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability

incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.