

Formula Name MIDAZOLAM 500MG IN 100ML of 0.9% SODIUM CHLORIDE INJ Sol (CADD CASSETTE) 5MG/ML INJ

Initials AP **Quantity** 100 **MLS** **Schedule** 4 **Days to Exp** 14 **Date of Formula** 7/25/2023

Cost \$0.00 **Cost Per Unit** \$0.00 **AWP** \$0.00 **AWP Per Unit** \$0.00 **Last Review** 1/6/2016

Chemical Ingredients

Chemical Name	Form	Qty	Units	QS	Est Cost	Ha	Note
MIDAZOLAM 50MG/10ML INJ VIAL	INJ	100.0000	MLS	☐	\$0.00		

Therapy

Description

Clear colorless solution free of particulate matter

Classification(s) CATEGORY 1 CSP

Disease State(s)

Instructions

A. Calculations/Special Considerations:
None

B. Equipment Required:

100mL cassette, 45" extension tubing, 16/18G needles, 60mL luer lock syringe, green connector, alcohol pads

C. Method of Preparation:

1. Perform hand-hygiene procedure by wetting hands and forearms and washing using soap and warm water for at least 30 seconds. Dry hands with a lint-free towel.
2. Don sterile gloves and use waterless alcohol-based surgical hand scrub.
3. Clean and disinfect the isolator hood according to proper policy and procedures.
4. Spray down all compounding items (needles, syringes, alcohol pads, stock bottles, etc) with 70% IPA, dry them and place them in the isolator hood.
5. Place a second set of gloves over the gloves in the isolator hood.
6. Disinfect injection ports and stoppers with 70% IPA.
7. Attach luer lock syringe to cassette, withdraw all air from the cassette and clamp the tubing.
8. Using a needle and luer lock syringe, draw up 100mL of midazolam. Take the needle off of the syringe, screw to the cassette tubing, unclamp the tubing, and push the midazolam into the cassette.
9. Hold cassette at an angle to get all of the air bubbles in one place. Draw out the air with the syringe attached and CLAMP the tubing.
10. Attach the 45" extension tubing.
11. Prime the tubing: Attach a green connector to a luer lock syringe and attach it to the extension tubing. Unclamp cassette tubing and pull the syringe back to prime the tubing (until a drop of medication is seen in the syringe).
12. CLAMP the cassette tubing.
13. Attach red cap.
14. Place used syringes in port with Sharps container, place the remainder of the garbage in the port with a garbage bag.
15. Disinfect the isolator hood with 70% IPA.
16. Label cassette with the appropriate pharmacy labels and refrigerate auxiliary label.

D. Labeling:

Record Manufacturer, Lot Number, NDC, and Expiration for Stock Midazolam Injectable Bottle
Label with Refrigerate Auxiliary Label

Add prepack label if compound lot made to stock for multiple Rx's

Add Rx auxiliary label if compound lot made to order for a unique Rx

_____ (place label here) _____

Appropriate References Should Be
Consulted. Safety And Efficacy Of
These Formulas Are The
Responsibility Of The Compounding
Pharmacist

E. Description of Finished Product:

Clear colorless solution free of particulate matter

F. Quality Control Procedures:

Physical appearance of compound verified by compounding certified pharmacist

Container-closure integrity is verified to be free of any defect

Volume of final product is within 5% of intended batch size

Pharmacist signature: _____

G. Packaging Container:

Dispense in CADD cassette covered by a UV protective foil bag with cold packs

H. Storage Requirements

Store refrigerated (36° - 46 °F)

Maximum BUD - 14 days

I. Formula Source & BUD Testing:

USP 797

Appropriate References Should Be
Consulted. Safety And Efficacy Of
These Formulas Are The
Responsibility Of The Compounding
Pharmacist