

**Formula Name** NOREPINEPHRINE 16MG IN 500ML OF 5% DEXTROSE INJ (BAG) 32MCG/ML INJ

|                 |        |                      |        |            |                 |        |                     |        |                        |           |
|-----------------|--------|----------------------|--------|------------|-----------------|--------|---------------------|--------|------------------------|-----------|
| <b>Initials</b> | AP     | <b>Quantity</b>      | 500    | <b>MLS</b> | <b>Schedule</b> | 0      | <b>Days to Exp</b>  | 2      | <b>Date of Formula</b> | 7/25/2023 |
| <b>Cost</b>     | \$0.00 | <b>Cost Per Unit</b> | \$0.00 | <b>AWP</b> |                 | \$0.00 | <b>AWP Per Unit</b> | \$0.00 | <b>Last Review</b>     | 1/6/2016  |

**Chemical Ingredients**

| Chemical Name                  | Form | Qty      | Units | QS                       | Est Cost | Ha | Note |
|--------------------------------|------|----------|-------|--------------------------|----------|----|------|
| DEXTROSE 5% SOLUTION 500ML     | SOLN | 500.0000 | MLS   | <input type="checkbox"/> | \$0.00   |    |      |
| NOREPINEPHRINE 4MG/4ML INJ AMP | SOLN | 16.0000  | MLS   | <input type="checkbox"/> | \$0.00   |    |      |

**Therapy****Description**

Clear colorless solution free of particulate matter

**Classification(s)**

CATEGORY 1 CSP

**Disease State(s)****Instructions****A. Calculations/Special Considerations:**

None

**B. Equipment Required:**

5mL Luer Lock Syringe, 16G Transfer Needle, FILTER Needle Alcohol Pad, Sterile gloves, Port Cover Sticker

**C. Method of Preparation:**

1. Perform hand-hygiene procedure by wetting hands and forearms and washing using soap and warm water for at least 30 seconds. Dry hands with a lint-free towel.
2. Don sterile gloves and use waterless alcohol-based surgical hand scrub.
3. Clean and disinfect the isolator hood according to proper policy and procedures.
4. Spray down all compounding items (needles, syringes, alcohol pads, stock bottles, etc) with 70% isopropyl alcohol (IPA), dry them and place them in the isolator hood
5. Place a second set of gloves over the gloves in the isolator hood.
6. Disinfect injection ports and stoppers with 70% IPA.
7. Remove 16ml of D5W from bag
8. Snap end off of norepinephrine ampules
9. Use filter needle to remove entire contents of ampule, discard filter needle
10. Transfer the norepinephrine ampule into the 500ml D5W IV bag using the transfer needles
11. Cover the injection port with port sticker.
12. Label the bag with the appropriate pharmacy label.

**D. Labeling:**

Record Manufacturer, Lot Number, NDC, and Expiration date for Norepinephrine

Record Manufacturer, Lot Number, NDC, and Expiration date for stock Dextrose 5% Bag

Label with lot number and expiration label

Add prepack label if compound lot made to stock for multiple Rx's

Add Rx auxiliary label if compound lot made to order for a unique Rx

\_\_\_\_\_ (place label here) \_\_\_\_\_

**E. Description of Finished Product:**

Clear colorless solution free of particulate matter

**F. Quality Control Procedures:**

Physical appearance of compound verified by compounding certified pharmacist

Container-closure integrity is verified to be free of any defect

Volume of final product is within 5% of intended batch size

Appropriate References Should Be  
Consulted. Safety And Efficacy Of  
These Formulas Are The  
Responsibility Of The Compounding  
Pharmacist

Pharmacist signature: \_\_\_\_\_

G. Packaging Container:  
Dispense in IV admixture bag

H. Storage Requirements  
Store at room temperature  
Maximum BUD - 48 hours

I. Formula Source & BUD Testing:  
USP 797

---

Appropriate References Should Be  
Consulted. Safety And Efficacy Of  
These Formulas Are The  
Responsibility Of The Compounding  
Pharmacist