

Formula Name SILDENAFIL SUSP INACTIVE 2.5MG/ML SUSP

Initials ETJ **Quantity** 300 **MLS** **Schedule** 0 **Days to Exp** 90 **Date of Formula** 1/14/2016
Cost \$17.77 **Cost Per Unit** \$0.06 **AWP** \$0.00 **AWP Per Unit** \$0.00 **Last Review** 1/6/2016

Chemical Ingredients

Chemical Name	Form	Qty	Units	QS	Est Cost	Ha	Note
SILDENAFIL 20MG TAB	TABLET	37.5000	EACH	☐	\$17.77		-
ORA-BLEND	SUSP	0.0000	MLS	☒	\$0.00		SOLUBILITY:N/A SWEET ORAL VEHICLE

Therapy**Classification(s)****Description****Disease State(s)****Instructions**

Equipment Needed:

Mortar & pestle, graduated cylinder, amber bottle.

Labelling & Storage:

Label with refrigerate sticker

Label with shake well sticker

Label with lot number and expiration barcode

Special Considerations:

None

1. Calculate required amounts and fill out compounding log
2. Measure out ingredients
3. In a mortar, crush Sildenafil tablets into a fine powder using the pestle
4. Wet Sildenafil powder with small amount of Ora Blend in mortar
5. Pour into amber bottle
6. Add Ora-Blend, shake well
7. Pour into graduated cylinder to QS
8. Transfer back to amber bottle
9. Shake well until evenly dispersed
10. Label with RX label and "Shake well" and "Refrigerate" auxiliary labels
11. Tape labels

Formula Source:

PCCA 8702

Testing:

PCCA 8702

Appropriate References Should Be
Consulted. Safety And Efficacy Of
These Formulas Are The
Responsibility Of The Compounding
Pharmacist