

Formula Name HYDROMORPHONE 600MG IN 300ML of 0.9% SODIUM CHLORIDE INJ Sol (CADD Cassette) 2MG/ML INJ

Initials AP **Quantity** 300 **MLS** **Schedule** 2 **Days to Exp** 14 **Date of Formula** 7/25/2023

Cost \$0.00 **Cost Per Unit** \$0.00 **AWP** \$0.00 **AWP Per Unit** \$0.00 **Last Review** 1/6/2016

Chemical Ingredients

Chemical Name	Form	Qty	Units	QS	Est Cost	Ha	Note
HYDROMORPHONE 500MG/50ML INJ SOL	INJ	50.0000	MLS	☐	\$0.00		
SODIUM CHLORIDE 0.9% 250ML INJ SOL	INJ	240.0000	MLS	☐	\$0.00		
HYDROMORPHONE 50MG/5ML INJ VIAL	INJ	10.0000	MLS	☐	\$0.00		

Therapy

Description

Clear colorless solution free of particulate matter

Classification(s) CATEGORY 1 CSP

Disease State(s)

Instructions

A. Calculations/Special Considerations:

None

B. Equipment Required:

Empty Sterile Bag, 60ml Luer Lock Syringe, CADD 100ml Cassette, CADD Admin Set tubing, 16/18G Transfer Needle, Alcohol Pad

C. Method of Preparation:

1. Perform hand-hygiene procedure by wetting hands and forearms and washing using soap and warm water for at least 30 seconds. Dry hands with a lint-free towel.
2. Don sterile gloves and use waterless alcohol-based surgical hand scrub.
3. Clean and disinfect the isolator hood according to proper policy and procedures.
4. Spray down all compounding items (needles, syringes, alcohol pads, stock bottles, etc) with 70% IPA, dry them and place them in the isolator hood.
5. Place a second set of gloves over the gloves in the isolator hood.
6. Disinfect injection ports and stoppers with 70% IPA.
7. Use 16G needle and add 240mL of 0.9% sodium chloride to the empty sterile bag.
8. Using a needle and luer lock syringe, draw up 60mL of hydromorphone and add to the bag.
9. Draw out all air from the bag using the needle and syringe.
10. Insert tubing into the bag and CLAMP tubing.
11. Prime tubing: UNCLAMP tubing, push on bag until you can see a drop of medication reach the end of the tubing. CLAMP tubing.
12. Attach red cap.
13. Place a red sticker over the medication access PORT on the bag.
14. Place used syringes in port with Sharps container, place the remainder of the garbage in the port with a garbage bag.
15. Disinfect the isolator hood with 70% IPA.
16. Label bag with the appropriate pharmacy labels and refrigerate auxiliary label.

D. Labeling:

Record Manufacturer, Lot Number, NDC and Expiration for Stock Hydromorphone Injectable Vial(s)

Record Manufacturer, Lot Number, NDC and Expiration for Stock Sodium Chloride Injectable Bag

Label with Refrigerate Auxiliary Label

Add prepack label if compound lot made to stock for multiple Rx

Add Rx auxiliary label if compound lot made to order for a unique Rx

_____ (place label here) _____

E. Description of Finished Product:

Appropriate References Should Be
Consulted. Safety And Efficacy Of
These Formulas Are The
Responsibility Of The Compounding
Pharmacist

Clear colorless solution free of particulate matter

F. Quality Control Procedures:

Physical appearance of compound verified by compounding certified pharmacist

Container-closure integrity is verified to be free of any defect

Volume of final product is within 5% of intended batch size

Pharmacist signature: _____

G. Packaging Container:

Dispense in IV cassette device covered by a UV protective foil bag with cold packs

H. Storage Requirements

Store refrigerated (36° - 46 °F)

Maximum BUD - 14 days

I. Formula Source & BUD Testing:

USP 797