

Volume II Advanced Programming Guide

Version 6.10

August 5th 1998

i

CLIPS Advanced Programming Guide

Version 6.10 August 5th 1998

CONTENTS

Preface	xi
Acknowledgements	xv
Section 1 - Introduction	1
1.1 Warning About Interfacing With CLIPS	1
1.2 C++ Compatibility	1
Section 2 - Installing and Tailoring CLIPS	3
2.1 Installing CLIPS	
2.1.1 Additional Considerations	6
2.2 Tailoring CLIPS	7
Section 3 - Integrating CLIPS with External Functions	15
3.1 Declaring User-Defined External Functions	15
3.2 Passing Arguments from CLIPS to External Functions	19
3.2.1 Determining the Number of Passed Arguments	19
3.2.2 Passing Symbols, Strings, Instance Names, Floats, and Integers	19
3.2.3 Passing Unknown Data Types	21
3.2.4 Passing Multifield Values	24
3.3 Returning Values To CLIPS From External Functions	26
3.3.1 Returning Symbols, Strings, and Instance Names	
3.3.2 Returning Boolean Values.	28
3.3.3 Returning External Addresses and Instance Addresses	29
3.3.4 Returning Unknown Data Types	30
3.3.5 Returning Multifield Values	
3.4 User-Defined Function Example	36
Section 4 - Embedding CLIPS	39
4.1 Environment Functions	39
4.1.1 AddClearFunction	39
4.1.2 AddPeriodicFunction.	40
4.1.3 AddResetFunction	40
4.1.4 Bload	41
4.1.5 Bsave	41
4.1.6 Clear	
4.1.7 FunctionCall.	
4.1.8 GetAutoFloatDividend.	
4.1.9 GetDynamicConstraintChecking	42

	4.1.10 GetSequenceOperatorRecognition.	. 43
	4.1.11 GetStaticConstraintChecking	43
	4.1.12 InitializeEnvironment	. 43
	4.1.13 Load	. 44
	4.1.14 RemoveClearFunction	. 44
	4.1.15 RemovePeriodicFunction	. 44
	4.1.16 RemoveResetFunction	45
	4.1.17 Reset	. 45
	4.1.18 Save	. 45
	4.1.19 SetAutoFloatDividend	46
	4.1.20 SetDynamicConstraintChecking	. 46
	4.1.21 SetSequenceOperator Recognition	. 47
	4.1.22 SetStaticConstraintChecking	. 47
	4.1.23 BatchStar	. 47
	4.1.24 Build	. 48
	4.1.25 Eval	. 48
4.2	Debugging Functions	. 49
	4.2.1 DribbleActive	. 49
	4.2.2 DribbleOff	. 49
	4.2.3 DribbleOn.	. 49
	4.2.4 GetWatchItem.	. 49
	4.2.5 Unwatch.	
	4.2.6 Watch	. 50
4.3	Deftemplate Functions.	. 51
	4.3.1 DeftemplateModule	. 51
	4.3.2 FindDeftemplate	
	4.3.3 GetDeftemplateList.	. 51
	4.3.4 GetDeftemplateName	
	4.3.5 GetDeftemplatePPForm	. 52
	4.3.6 GetDeftemplateWatch	. 52
	4.3.7 GetNextDeftemplate	. 52
	4.3.8 IsDeftemplateDeletable	
	4.3.9 ListDeftemplates.	
	4.3.10 SetDeftemplateWatch	
	4.3.11 Undeftemplate	
4.4	Fact Functions	
	4.4.1 Assert	
	4.4.2 AssertString	
	4.4.3 AssignFactSlotDefaults	
	4.4.4 CreateFact	
	4.4.5 DecrementFactCount.	
	4.4.6 FactIndex	
	4.4.7 Facts	. 59

4.4.8 GetFactDuplication.	59
4.4.9 GetFactListChanged	60
4.4.10 GetFactPPForm	60
4.4.11 GetFactSlot	60
4.4.12 GetNextFact	61
4.4.13 IncrementFactCount	61
4.4.14 LoadFacts	62
4.4.15 PutFactSlot	62
4.4.16 Retract	63
4.4.17 SaveFacts	63
4.4.18 SetFactDuplication	64
4.4.19 SetFactListChanged	64
4.4.20 FactExistp	64
4.4.21 FactSlotNames	65
4.4.22 GetFactList	65
4.4.23 LoadFactsFromString	66
4.5 Deffacts Functions	66
4.5.1 DeffactsModule	66
4.5.2 FindDeffacts	66
4.5.3 GetDeffactsList	67
4.5.4 GetDeffactsName	67
4.5.5 GetDeffactsPPForm	67
4.5.6 GetNextDeffacts	68
4.5.7 IsDeffactsDeletable	68
4.5.8 ListDeffacts	68
4.5.9 Undeffacts	69
4.6 Defrule Functions	69
4.6.1 DefruleHasBreakpoint	69
4.6.2 DefruleModule	69
4.6.3 FindDefrule	70
4.6.4 GetDefruleList	70
4.6.5 GetDefruleName	70
4.6.6 GetDefrulePPForm	70
4.6.7 GetDefruleWatchActivations	71
4.6.8 GetDefruleWatchFirings	71
4.6.9 GetIncrementalReset	71
4.6.10 GetNextDefrule	72
4.6.11 IsDefruleDeletable	72
4.6.12 ListDefrules	72
4.6.13 Matches	73
4.6.14 Refresh	73
4.6.15 RemoveBreak	73
4.6.16 SetBreak	73

	4.6.17 SetDefruleWatchActivations	74
	4.6.18 SetDefruleWatchFirings	74
	4.6.19 SetIncrementalReset	74
	4.6.20 ShowBreaks	75
	4.6.21 Undefrule	75
4.7	Agenda Functions	75
	4.7.1 AddRunFunction.	75
	4.7.2 Agenda	76
	4.7.3 ClearFocusStack	77
	4.7.4 DeleteActivation	77
	4.7.5 Focus	77
	4.7.6 GetActivationName	77
	4.7.7 GetActivationPPForm.	78
	4.7.8 GetActivationSalience	
	4.7.9 GetAgendaChanged	78
	4.7.10 GetFocus	
	4.7.11 GetFocusStack.	79
	4.7.12 GetNextActivation.	79
	4.7.13 GetSalienceEvaluation	80
	4.7.14 GetStrategy.	80
	4.7.15 ListFocusStack	
	4.7.16 PopFocus	
	4.7.17 RefreshAgenda	
	4.7.18 RemoveRunFunction	
	4.7.19 ReorderAgenda	81
	4.7.20 Run	
	4.7.21 SetActivationSalience	82
	4.7.22 SetAgendaChanged	83
	4.7.23 SetSalienceEvaluation	83
	4.7.24 SetStrategy	83
4.8	Defglobal Functions.	84
	4.8.1 DefglobalModule	
	4.8.2 FindDefglobal	84
	4.8.3 GetDefglobalList	
	4.8.4 GetDefglobalName	
	4.8.5 GetDefglobalPPForm	
	4.8.6 GetDefglobalValue	
	4.8.7 GetDefglobalValueForm	
	4.8.8 GetDefglobalWatch	
	4.8.9 GetGlobalsChanged	
	4.8.10 GetNextDefglobal	
	4.8.11 GetResetGlobals.	
	4.8.12 IsDefglobalDeletable	

	4.8.13 ListDefglobals	88
	4.8.14 SetDefglobalValue	88
	4.8.15 SetDefglobalWatch	89
	4.8.16 SetGlobalsChanged	89
	4.8.17 SetResetGlobals	89
	4.8.18 ShowDefglobals	89
	4.8.19 Undefglobal	90
4.9	Deffunction Functions	90
	4.9.1 DeffunctionModule	90
	4.9.2 FindDeffunction	91
	4.9.3 GetDeffunctionList.	91
	4.9.4 GetDeffunctionName	91
	4.9.5 GetDeffunctionPPForm	92
	4.9.6 GetDeffunctionWatch	92
	4.9.7 GetNextDeffunction.	92
	4.9.8 IsDeffunctionDeletable	92
	4.9.9 ListDeffunctions	93
	4.9.10 SetDeffunctionWatch	93
	4.9.11 Undeffunction	93
4.1	0 Defgeneric Functions	94
	4.10.1 DefgenericModule	94
	4.10.2 FindDefgeneric	94
	4.10.3 GetDefgenericList	94
	4.10.4 GetDefgenericName	95
	4.10.5 GetDefgenericPPForm	95
	4.10.6 GetDefgenericWatch	95
	4.10.7 GetNextDefgeneric	96
	4.10.8 IsDefgenericDeletable	96
	4.10.9 ListDefgenerics.	96
	4.10.10 SetDefgenericWatch	97
	4.10.11 Undefgeneric	97
4.1	1 Defmethod Functions	97
	4.11.1 GetDefmethodDescription	97
	4.11.2 GetDefmethodList	98
	4.11.3 GetDefmethodPPForm	98
	4.11.4 GetDefmethodWatch	99
	4.11.5 GetMethodRestrictions	99
	4.11.6 GetNextDefmethod	99
	4.11.7 IsDefmethodDeletable	100
	4.11.8 ListDefmethods.	100
	4.11.9 SetDefmethodWatch	100
	4.11.10 Undefmethod	101
4.1	2 Defclass Functions.	101

	4.12.1 BrowseClasses	.101
	4.12.2 ClassAbstractP	.102
	4.12.3 ClassReactiveP	.102
	4.12.4 ClassSlots	.102
	4.12.5 ClassSubclasses	.103
	4.12.6 ClassSuperclasses	.103
	4.12.7 DefclassModule	.103
	4.12.8 DescribeClass.	.104
	4.12.9 FindDefclass	.104
	4.12.10 GetDefclassList	.104
	4.12.11 GetDefclassName	. 105
	4.12.12 GetDefclassPPForm	.105
	4.12.13 GetDefclassWatchInstances.	. 105
	4.12.14 GetDefclassWatchSlots	.106
	4.12.15 GetNextDefclass	.106
	4.12.16 IsDefclassDeletable	.106
	4.12.17 ListDefclasses	.107
	4.12.18 SetDefclassWatchInstances	.107
	4.12.19 SetDefclassWatchSlots	.107
	4.12.20 SlotAllowedValues	.107
	4.12.21 SlotCardinality	.108
	4.12.22 SlotDirectAccessP	.108
	4.12.23 SlotExistP	.109
	4.12.24 SlotFacets	.109
	4.12.25 SlotInitableP	.109
	4.12.26 SlotPublicP	.110
	4.12.27 SlotRange	.110
	4.12.28 SlotSources	.110
	4.12.29 SlotTypes	.111
	4.12.30 SlotWritableP	.111
	4.12.31 SubclassP	.111
	4.12.32 SuperclassP	.112
	4.12.33 Undefclass	.112
4.1	3 Instance Functions	.112
	4.13.1 BinaryLoadInstances	.112
	4.13.2 BinarySaveInstances.	.113
	4.13.3 CreateRawInstance.	.113
	4.13.4 DecrementInstanceCount	.113
	4.13.5 DeleteInstance	.114
	4.13.6 DirectGetSlot	.114
	4.13.7 DirectPutSlot.	.114
	4.13.8 FindInstance	.115
	4.13.9 GetInstanceClass	.115

vi Table of Contents

4.13.11 GetInstancePForm 1 4.13.12 GetInstancesChanged 1 4.13.13 GetNextInstance 1 4.13.14 GetNextInstanceInClass 1 4.13.15 GetNextInstanceInClassAndSubclasses 1 4.13.16 IncrementInstanceCount 1 4.13.17 Instances 1 4.13.18 LoadInstances 1 4.13.19 MakeInstance 1 4.13.20 RestoreInstances 1 4.13.21 SaveInstances 1 4.13.22 Send 1 4.13.23 SetInstanceSchanged 1 4.13.24 UnmakeInstance 1 4.13.25 ValidInstanceSfromString 1 4.13.26 LoadInstancesFromString 1 4.13.27 RestoreInstancesFromString 1 4.14.1 PindDefmessageHandler Functions 1 4.14.1 FindDefmessageHandler Functions 1 4.14.2 GetDefmessageHandler Ist 1 4.14.3 GetDefmessageHandlerPPForm 1 4.14.4 GetDefmessageHandlerWatch 1 4.14.5 GetDefmessageHandlerWatch 1 4.14.6 GetDefmessageHandlerDeletable 1 4.14.10 PreviewSend 1 4.15 Definstances	4.13.10 GetInstanceName	116
4.13.13 GetNextInstance (Class) 1 4.13.14 GetNextInstanceInClass 1 4.13.15 GetNextInstanceInClassAndSubclasses 1 4.13.16 IncrementInstanceCount 1 4.13.17 Instances 17 4.13.18 LoadInstances 17 4.13.19 MakeInstance 17 4.13.20 RestoreInstances 17 4.13.21 SaveInstances 17 4.13.22 Send 17 4.13.23 SetInstancesChanged 17 4.13.24 UnmakeInstance 17 4.13.25 ValidInstanceAddress 17 4.13.26 LoadInstancesFromString 17 4.14 Defmessage-handler Functions 17 4.14 I FindDefmessageHandler 17 4.14.1 FindDefmessageHandler 17 4.14.2 GetDefmessageHandlerName 17 4.14.3 GetDefmessageHandlerName 17 4.14.5 GetDefmessageHandlerWatch 17 4.14.7 GetNextDefmessageHandlerWatch 17 4.14.9 ListDefmessageHandlerWatch 17 4.14.10 PreviewSend 17 4.15.10 Definstances Functions 17 4.15.10 GetDefinstancesModule 17 4.15.2	4.13.11 GetInstancePPForm	116
4.13.14 GetNextInstanceInClass AndSubclasses 1 4.13.15 IncrementInstanceCount 1 4.13.17 Instances 1 4.13.18 LoadInstances 1 4.13.19 MakeInstance 1 4.13.20 RestoreInstances 1 4.13.21 SaveInstances 1 4.13.22 Send 1 4.13.23 SetInstancesChanged 1 4.13.24 UnmakeInstance 1 4.13.25 ValidInstanceAddress 1 4.13.26 LoadInstancesFromString 1 4.13.27 RestoreInstancesFromString 1 4.14.1 FindDefmessageHandler Functions 1 4.14.2 GetDefmessageHandler Functions 1 4.14.1 FindDefmessageHandler Functions 1 4.14.2 GetDefmessageHandler Functions 1 4.14.1 GetDefmessageHandler Functions 1 4.14.2 GetDefmessageHandler Functions 1 4.14.3 GetDefmessageHandler Functions 1 4.14.4 GetDefmessageHandler Functions 1 4.14.5 GetDefmessageHandler Functions 1 4.14.6 GetDefmessageHandler Functions 1 4.14.6 GetDefmessageHandler Functions 1 4.14.1 Definestances Functi	4.13.12 GetInstancesChanged	116
4.13.15 GetNextInstanceInClassAndSubclasses 1 4.13.16 IncrementInstanceCount 1 4.13.17 Instances 1 4.13.18 LoadInstances 1 4.13.19 MakeInstance 1 4.13.20 RestoreInstances 1 4.13.21 SaveInstances 1 4.13.22 Send 1 4.13.23 SetInstancesChanged 1 4.13.24 UnmakeInstance 1 4.13.25 ValidInstanceAddress 1 4.13.27 RestoreInstancesFromString 1 4.13.27 RestoreInstancesFromString 1 4.14.26 LoadInstancesFromString 1 4.14.1 FindDefmessageHandler Functions 1 4.14.2 GetDefmessageHandler 1 4.14.3 GetDefmessageHandlerName 1 4.14.4 GetDefmessageHandlerPPForm 1 4.14.5 GetDefmessageHandlerType 1 4.14.6 GetDefmessageHandlerWatch 1 4.14.7 GetNextDefmessageHandler 1 4.14.9 ListDefmessageHandler 1 4.14.1 SetDefmessageHandler 1 4.15.2 FindDefinstances 1 4.15.3 GetDefinstancesShame 1 4.15.4 GetDefinstancesN	4.13.13 GetNextInstance	117
4.13.16 IncrementInstanceCount 1 4.13.17 Instances 1 4.13.18 LoadInstances 1 4.13.19 MakeInstances 1 4.13.20 RestoreInstances 1 4.13.21 SaveInstances 1 4.13.22 Send 1 4.13.23 SetInstanceSChanged 1 4.13.25 ValidInstanceAddress 1 4.13.25 ValidInstanceAddress 1 4.13.26 LoadInstancesFromString 1 4.13.27 RestoreInstancesFromString 1 4.14 Defmessage-handler Functions 1 4.14.1 FindDefmessageHandler Functions 1 4.14.2 GetDefmessageHandlerList 1 4.14.3 GetDefmessageHandlerName 1 4.14.4 GetDefmessageHandlerName 1 4.14.4 GetDefmessageHandlerType 1 4.14.5 GetDefmessageHandlerWatch 1 4.14.7 GetNextDefmessageHandlerWatch 1 4.14.9 ListDefmessageHandlerSageHandler 1 4.14.10 PreviewSend 1 4.14.11 SetDefmessageHandler 1 4.15.2 FindDefinstances Functions 1 4.15.3 GetDefinstancesModule 1 4.15.4 GetD	4.13.14 GetNextInstanceInClass	117
4.13.17 Instances 17 4.13.18 LoadInstances 17 4.13.19 MakeInstance 17 4.13.20 RestoreInstances 17 4.13.21 SaveInstances 17 4.13.22 Send 17 4.13.23 ValidInstanceSchanged 17 4.13.24 UnmakeInstance 17 4.13.25 ValidInstanceAddress 17 4.13.26 LoadInstancesFromString 17 4.13.27 RestoreInstancesFromString 17 4.14 Defmessage-handler Functions 17 4.14.1 FindDefmessageHandler 17 4.14.2 GetDefmessageHandler 17 4.14.3 GetDefmessageHandlerName 17 4.14.4 GetDefmessageHandlerPPForm 17 4.14.5 GetDefmessageHandlerWatch 17 4.14.7 GetNextDefmessageHandlerWatch 17 4.14.8 IsDefmessageHandlerDeletable 17 4.14.10 PreviewSend 17 4.14.11 SetDefmessageHandlerWatch 17 4.15.1 Definstances Functions 17 4.15.2 FindDefinstances 17 4.15.3 GetDefinstancesName 17 4.15.4 GetDefinstancesDeletable 17 4.15.5 GetDefin	4.13.15 GetNextInstanceInClassAndSubclasses	117
4.13.19 MakeInstance. 1.7 4.13.20 RestoreInstances 1.7 4.13.21 SaveInstances 1.7 4.13.22 Send 1.7 4.13.23 SetInstancesChanged. 1.7 4.13.24 UnmakeInstance 1.7 4.13.25 ValidInstanceAddress. 1.7 4.13.26 LoadInstancesFromString 1.7 4.13.27 RestoreInstancesFromString 1.7 4.14 Defmessage-handler Functions 1.7 4.14.1 FindDefmessageHandler Functions 1.7 4.14.2 GetDefmessageHandlerName 1.7 4.14.3 GetDefmessageHandlerName 1.7 4.14.4 GetDefmessageHandlerType 1.7 4.14.5 GetDefmessageHandlerWatch 1.7 4.14.6 GetDefmessageHandlerWatch 1.7 4.14.7 GetNextDefmessageHandler 1.7 4.14.8 IsDefmessageHandler 1.7 4.14.9 ListDefmessageHandler 1.7 4.14.10 PreviewSend 1.7 4.15.2 Definstances Functions 1.7 4.15.1 Definstances Functions 1.7 4.15.2 FindDefinstances 1.7 4.15.3 GetDefinstancess 1.7 4.15.4 GetDefinstancesName 1.7	4.13.16 IncrementInstanceCount	118
4.13.20 RestoreInstances 12 4.13.21 SaveInstances 13 4.13.22 Send 14 4.13.23 SetInstancesChanged 14 4.13.24 UnmakeInstance 15 4.13.25 ValidInstanceAddress 15 4.13.26 LoadInstancesFromString 17 4.13.27 RestoreInstancesFromString 17 4.14 Defmessage-handler Functions 17 4.14.1 FindDefmessageHandler 17 4.14.2 GetDefmessageHandlerList 17 4.14.3 GetDefmessageHandlerName 17 4.14.4 GetDefmessageHandlerPForm 17 4.14.5 GetDefmessageHandlerWatch 17 4.14.6 GetDefmessageHandlerWatch 17 4.14.7 GetNextDefmessageHandler 17 4.14.8 IsDefmessageHandlerDeletable 17 4.14.9 ListDefmessageHandler 17 4.14.10 PreviewSend 17 4.15 Definstances Functions 17 4.15.1 Definstances Module 17 4.15.2 FindDefinstances 17 4.15.3 GetDefinstancesName 17 4.15.4 GetDefinstancesPForm 18 4.15.5 GetDefinstancesDeletable 17 <td< td=""><td>4.13.17 Instances</td><td>120</td></td<>	4.13.17 Instances	120
4.13.20 RestoreInstances 1.7 4.13.21 SaveInstances 1.7 4.13.22 Send 1.7 4.13.23 SetInstancesChanged 1.7 4.13.24 UnmakeInstance 1.7 4.13.25 ValidInstanceAddress 1.7 4.13.26 LoadInstancesFromString 1.7 4.13.27 RestoreInstancesFromString 1.7 4.14 Defmessage-handler Functions 1.7 4.14.1 FindDefmessageHandler 1.7 4.14.2 GetDefmessageHandlerList 1.7 4.14.3 GetDefmessageHandlerName 1.7 4.14.4 GetDefmessageHandlerPForm 1.7 4.14.5 GetDefmessageHandlerWatch 1.7 4.14.6 GetDefmessageHandlerWatch 1.7 4.14.7 GetNextDefmessageHandler 1.7 4.14.8 IsDefmessageHandlerDeletable 1.7 4.14.9 ListDefmessageHandlerSageHandler 1.7 4.14.10 PreviewSend 1.7 4.15.1 Definstances Functions 1.7 4.15.2 FindDefinstances Module 1.7 4.15.3 GetDefinstancesNodule 1.7 4.15.4 GetDefinstancesName 1.7 4.15.5 GetDefinstancesName 1.7 4.15.6 GetNextDefinstances	4.13.18 LoadInstances	120
4.13.21 SaveInstances 17 4.13.22 Send 17 4.13.23 SetInstancesChanged 17 4.13.24 UnmakeInstance 17 4.13.25 ValidInstanceAddress 17 4.13.26 LoadInstancesFromString 17 4.13.27 RestoreInstancesFromString 17 4.14 Defmessage-handler Functions 17 4.14.1 FindDefmessageHandler 17 4.14.2 GetDefmessageHandlerName 17 4.14.3 GetDefmessageHandlerPame 17 4.14.4 GetDefmessageHandlerPForm 17 4.14.5 GetDefmessageHandlerWatch 17 4.14.6 GetDefmessageHandlerWatch 17 4.14.7 GetNextDefmessageHandler 17 4.14.8 IsDefmessageHandlerDeletable 17 4.14.9 ListDefmessageHandlerWatch 17 4.14.11 SetDefmessageHandlerWatch 17 4.14.12 UndefmessageHandlerWatch 17 4.15.1 Definstances Functions 17 4.15.2 FindDefinstances 17 4.15.3 GetDefinstancesName 17 4.15.4 GetDefinstancesPerform 18 4.15.7 IsDefinstancesPeletable 17 4.15.8 ListDefinstances 17	4.13.19 MakeInstance	121
4.13.22 Send 1.7 4.13.23 SetInstancesChanged 1.7 4.13.24 UnmakeInstance 1.7 4.13.25 ValidInstancesFromString 1.7 4.13.26 LoadInstancesFromString 1.7 4.13.27 RestoreInstancesFromString 1.7 4.14 Defmessage-handler Functions 1.7 4.14.1 FindDefmessageHandler 1.7 4.14.2 GetDefmessageHandlerList 1.7 4.14.3 GetDefmessageHandlerName 1.7 4.14.4 GetDefmessageHandlerPForm 1.7 4.14.5 GetDefmessageHandlerType 1.7 4.14.6 GetDefmessageHandlerWatch 1.7 4.14.7 GetNextDefmessageHandler 1.7 4.14.8 IsDefmessageHandlerDeletable 1.7 4.14.9 ListDefmessageHandlerSageHandler 1.7 4.14.10 PreviewSend 1.7 4.14.11 SetDefmessageHandlerWatch 1.7 4.15.1 Definstances Functions 1.7 4.15.2 FindDefinstances 1.7 4.15.3 GetDefinstancesNodule 1.7 4.15.4 GetDefinstancesPerform 1.7 4.15.5 GetDefinstancesPerform 1.7 4.15.6 GetNextDefinstances 1.7 4.15.7 IsDefinstances<	4.13.20 RestoreInstances	121
4.13.23 SetInstancesChanged. 17 4.13.24 UnmakeInstance 17 4.13.25 ValidInstanceAddress. 17 4.13.26 LoadInstancesFromString 17 4.13.27 RestoreInstancesFromString 17 4.14 Defmessage-handler Functions 17 4.14.1 FindDefmessageHandler. 17 4.14.2 GetDefmessageHandler. 17 4.14.3 GetDefmessageHandlerName 17 4.14.4 GetDefmessageHandlerPPForm 17 4.14.5 GetDefmessageHandlerType 17 4.14.6 GetDefmessageHandlerWatch 17 4.14.8 IsDefmessageHandlerDeletable 17 4.14.9 ListDefmessageHandler 17 4.14.10 PreviewSend 17 4.14.11 SetDefmessageHandlerWatch 17 4.14.12 UndefmessageHandler 17 4.15.15 Definstances Functions 17 4.15.2 FindDefinstances 17 4.15.4 GetDefinstancesName 17 4.15.5 GetDefinstancesPPForm 11 4.15.6 GetNextDefinstances 17 4.15.7 IsDefinstancesDeletable 17 4.15.8 ListDefinstances 17 4.15.9 Undefinstances 17	4.13.21 SaveInstances	121
4.13.24 UnmakeInstance 12 4.13.25 ValidInstanceAddress 12 4.13.26 LoadInstancesFromString 12 4.13.27 RestoreInstancesFromString 12 4.14 Defmessage-handler Functions 12 4.14.1 FindDefmessageHandler 12 4.14.2 GetDefmessageHandlerIst 12 4.14.3 GetDefmessageHandlerName 12 4.14.4 GetDefmessageHandlerPPForm 12 4.14.5 GetDefmessageHandlerType 12 4.14.6 GetDefmessageHandlerWatch 12 4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerSedetable 12 4.14.9 ListDefmessageHandlerSedetable 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15.15 Definstances Functions 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesName 12 4.15.4 GetDefinstancesPPForm 12 4.15.6 GetNextDefinstancesDeletable 12 4.15.7 IsDefinstancesDeletable 12 4.15.8 ListDefinstances 12 4.15.9 Undefinstances	4.13.22 Send	122
4.13.25 ValidInstanceAddress 17 4.13.26 LoadInstancesFromString 17 4.13.27 RestoreInstancesFromString 17 4.14 Defmessage-handler Functions 17 4.14.1 FindDefmessageHandler 17 4.14.2 GetDefmessageHandlerList 17 4.14.3 GetDefmessageHandlerName 17 4.14.4 GetDefmessageHandlerPFForm 17 4.14.5 GetDefmessageHandlerType 17 4.14.6 GetDefmessageHandlerWatch 17 4.14.7 GetNextDefmessageHandler 17 4.14.8 IsDefmessageHandlerDeletable 17 4.14.9 ListDefmessageHandlerS 17 4.14.10 PreviewSend 17 4.14.11 SetDefmessageHandlerWatch 17 4.15.1 Definstances Functions 17 4.15.1 Definstances Functions 17 4.15.2 FindDefinstances Module 17 4.15.3 GetDefinstancesList 17 4.15.4 GetDefinstancesName 17 4.15.5 GetDefinstancesPPForm 16 4.15.7 IsDefinstancesDeletable 17 4.15.8 ListDefinstances 17 4.15.9 Undefinstances 17 4.16 Defmodule Functions 17	4.13.23 SetInstancesChanged	123
4.13.26 LoadInstancesFromString 17 4.13.27 RestoreInstancesFromString 17 4.14 Defmessage-handler Functions 17 4.14.1 FindDefmessageHandler 17 4.14.2 GetDefmessageHandlerList 17 4.14.3 GetDefmessageHandlerName 17 4.14.4 GetDefmessageHandlerPForm 17 4.14.5 GetDefmessageHandlerType 17 4.14.6 GetDefmessageHandlerWatch 17 4.14.7 GetNextDefmessageHandler 17 4.14.8 IsDefmessageHandlerDeletable 17 4.14.9 ListDefmessageHandlerS 17 4.14.10 PreviewSend 17 4.15.1 Definstances Functions 17 4.15.1 Definstances Functions 17 4.15.2 FindDefinstances Module 17 4.15.3 GetDefinstancesList 17 4.15.4 GetDefinstancesList 17 4.15.5 GetDefinstancesName 17 4.15.6 GetNextDefinstances 12 4.15.7 IsDefinstancesDeletable 17 4.15.8 ListDefinstances 17 4.16 Defmodule Functions 17	4.13.24 UnmakeInstance	123
4.13.27 RestoreInstancesFromString 12 4.14 Defmessage-handler Functions 12 4.14.1 FindDefmessageHandler 12 4.14.2 GetDefmessageHandlerList 12 4.14.3 GetDefmessageHandlerName 12 4.14.4 GetDefmessageHandlerPPForm 12 4.14.5 GetDefmessageHandlerType 12 4.14.6 GetDefmessageHandlerWatch 12 4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlerSageHandlers 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.15.1 Definstances Functions 12 4.15.1 Definstances Functions 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 12 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.6 GetNextDefinstances 12 4.15.7 IsDefinstancesDeletable 12 4.15.9 Undefinstances 12 4.15.9 Undefinstances 12 4.16 Defmodule Functions 12	4.13.25 ValidInstanceAddress	123
4.14 Defmessage-handler Functions 12 4.14.1 FindDefmessageHandler 12 4.14.2 GetDefmessageHandlerList 12 4.14.3 GetDefmessageHandlerName 12 4.14.4 GetDefmessageHandlerPPForm 12 4.14.5 GetDefmessageHandlerType 12 4.14.6 GetDefmessageHandlerWatch 12 4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlers 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.15.1 Definstances Functions 12 4.15.1 Definstances Functions 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesName 12 4.15.4 GetDefinstancesName 12 4.15.5 GetDefinstancesPPForm 13 4.15.7 IsDefinstancesDeletable 12 4.15.8 ListDefinstances 12 4.16 Defmodule Functions 13	4.13.26 LoadInstancesFromString	123
4.14.1 FindDefmessageHandler 12 4.14.2 GetDefmessageHandlerList 12 4.14.3 GetDefmessageHandlerName 12 4.14.4 GetDefmessageHandlerPForm 12 4.14.5 GetDefmessageHandlerType 12 4.14.6 GetDefmessageHandlerWatch 12 4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlers 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.15.1 Definstances Functions 12 4.15.1 Definstances Functions 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 12 4.15.4 GetDefinstancesName 12 4.15.5 GetDefinstancesPPForm 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.13.27 RestoreInstancesFromString	124
4.14.2 GetDefmessageHandlerList. 12 4.14.3 GetDefmessageHandlerName 12 4.14.4 GetDefmessageHandlerPFForm 12 4.14.5 GetDefmessageHandlerType 12 4.14.6 GetDefmessageHandlerWatch 12 4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlers 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15 Definstances Functions 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 12 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14 Defmessage-handler Functions	124
4.14.3 GetDefmessageHandlerName 12 4.14.4 GetDefmessageHandlerPPForm 12 4.14.5 GetDefmessageHandlerType 12 4.14.6 GetDefmessageHandlerWatch 12 4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlerS 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15.1 Definstances Functions 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.1 FindDefmessageHandler	124
4.14.4 GetDefmessageHandlerPPForm 12 4.14.5 GetDefmessageHandlerType 12 4.14.6 GetDefmessageHandlerWatch 12 4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlers 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15.1 Definstances Functions 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.2 GetDefmessageHandlerList	125
4.14.5 GetDefmessageHandlerType 12 4.14.6 GetDefmessageHandlerWatch 12 4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlers 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15 Definstances Functions 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.3 GetDefmessageHandlerName	125
4.14.6 GetDefmessageHandlerWatch 12 4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlerS 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 13 4.15 Definstances Functions 13 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.7 IsDefinstancesDeletable 12 4.15.8 ListDefinstances 12 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.4 GetDefmessageHandlerPPForm	126
4.14.7 GetNextDefmessageHandler 12 4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlers 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15 Definstances Functions 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 12 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 12 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.5 GetDefmessageHandlerType	126
4.14.8 IsDefmessageHandlerDeletable 12 4.14.9 ListDefmessageHandlerS 12 4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15 Definstances Functions 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 12 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 12 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.6 GetDefmessageHandlerWatch	126
4.14.9 ListDefmessageHandlers. 12 4.14.10 PreviewSend. 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15 Definstances Functions. 13 4.15 DefinstancesModule 12 4.15.2 FindDefinstances 13 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.6 GetNextDefinstances 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.7 GetNextDefmessageHandler	127
4.14.10 PreviewSend 12 4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15 Definstances Functions 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.6 GetNextDefinstances 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.8 IsDefmessageHandlerDeletable	127
4.14.11 SetDefmessageHandlerWatch 12 4.14.12 UndefmessageHandler 12 4.15 Definstances Functions 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.6 GetNextDefinstances 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.9 ListDefmessageHandlers	127
4.14.12 UndefmessageHandler 12 4.15 Definstances Functions 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.6 GetNextDefinstances 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.10 PreviewSend	128
4.15 Definstances Functions. 12 4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.6 GetNextDefinstances 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.11 SetDefmessageHandlerWatch	128
4.15.1 DefinstancesModule 12 4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.6 GetNextDefinstances 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.14.12 UndefmessageHandler	128
4.15.2 FindDefinstances 12 4.15.3 GetDefinstancesList 13 4.15.4 GetDefinstancesName 14 4.15.5 GetDefinstancesPPForm 15 4.15.6 GetNextDefinstances 15 4.15.7 IsDefinstancesDeletable 15 4.15.8 ListDefinstances 15 4.15.9 Undefinstances 15 4.16 Defmodule Functions 16	4.15 Definstances Functions.	129
4.15.3 GetDefinstancesList 1 4.15.4 GetDefinstancesName 1 4.15.5 GetDefinstancesPPForm 1 4.15.6 GetNextDefinstances 1 4.15.7 IsDefinstancesDeletable 1 4.15.8 ListDefinstances 1 4.15.9 Undefinstances 1 4.16 Defmodule Functions 1	4.15.1 DefinstancesModule	129
4.15.4 GetDefinstancesName 13 4.15.5 GetDefinstancesPPForm 13 4.15.6 GetNextDefinstances 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.15.2 FindDefinstances	129
4.15.5 GetDefinstancesPPForm 13 4.15.6 GetNextDefinstances 13 4.15.7 IsDefinstancesDeletable 13 4.15.8 ListDefinstances 13 4.15.9 Undefinstances 13 4.16 Defmodule Functions 13	4.15.3 GetDefinstancesList	130
4.15.6 GetNextDefinstances134.15.7 IsDefinstancesDeletable134.15.8 ListDefinstances134.15.9 Undefinstances134.16 Defmodule Functions13	4.15.4 GetDefinstancesName	130
4.15.7 IsDefinstancesDeletable.134.15.8 ListDefinstances.134.15.9 Undefinstances134.16 Defmodule Functions.13	4.15.5 GetDefinstancesPPForm	130
4.15.8 ListDefinstances.134.15.9 Undefinstances134.16 Defmodule Functions.13	4.15.6 GetNextDefinstances	131
4.15.9 Undefinstances134.16 Defmodule Functions13	4.15.7 IsDefinstancesDeletable.	131
4.16 Defmodule Functions	4.15.8 ListDefinstances	131
	4.15.9 Undefinstances	132
4464 77 470 0 144	4.16 Defmodule Functions	132
4.16.1 FindDefmodule	4.16.1 FindDefmodule	132

4.16.2 GetCurrentModule	132
4.16.3 GetDefmoduleList	132
4.16.4 GetDefmoduleName	
4.16.5 GetDefmodulePPForm	133
4.16.6 GetNextDefmodule	133
4.16.7 ListDefmodules.	134
4.16.8 SetCurrentModule	134
4.17 Embedded Application Examples	134
4.17.1 User-Defined Functions	
4.17.2 Manipulating Objects and Calling CLIPS Functions	136
Section 5 - Creating a CLIPS Run-time Program	
5.1 Compiling the Constructs	139
Section 6 - Combining CLIPS with Languages Other Than C	143
6.1 Introduction	
6.2 Ada and FORTRAN Interface Package Function List	
6.3 Embedded CLIPS - Using an External Main Program	
6.4 Asserting Facts into CLIPS	
6.5 Calling a Subroutine from CLIPS	
6.6 Passing Arguments from CLIPS to an External Function	
6.7 String Conversion	
6.8 Compiling and Linking	
6.8.1 VMS Ada Version	
6.8.2 VMS FORTRAN Version	151
6.8.3 CLIPS Library	152
6.9 Building an Interface Package	
Section 7 - I/O Router System	
7.1 Introduction	153
7.2 Logical Names	153
7.3 Routers	155
7.4 Router Priorities	156
7.5 Internal I/O Functions	157
7.5.1 ExitRouter	157
7.5.2 GetcRouter	157
7.5.3 PrintRouter	158
7.5.4 UngetcRouter.	
7.6 Router Handling Functions	159
7.6.1 ActivateRouter	159
7.6.2 AddRouter	
7.6.3 DeactivateRouter	161
7.6.4 DeleteRouter	

viii Table of Contents

Section 8 - Memory Management	163
8.1 How CLIPS Uses Memory	
8.2 Standard Memory Functions	
8.2.1 GetConserveMemory	
8.2.2 MemRequests	
8.2.3 MemUsed	
8.2.4 ReleaseMem.	
8.2.5 SetConserveMemory	
8.2.6 SetOutOfMemoryFunction	
Appendix A - Language Integration Listings	169
A.1 Ada Interface Package for CLIPS	
A.2 FORTRAN Interface Package for VAX VMS	173
A.3 Function to Convert C Strings for VMS Ada or FORTRAN	176
Appendix B - I/O Router Examples	179
B.1 Dribble System	
B.2 Better Dribble System	
B.3 Batch System	
B.4 Simple Window System	
Appendix C - Update Release Notes	189
C.1 Version 6.10	
C.1 Version 6.05	
Appendix D - Differences Between Versions 5.1 and 6.0	191
Index	197

Preface

The History of CLIPS

The origins of the C Language Integrated Production System (CLIPS) date back to 1984 at NASA's Johnson Space Center. At this time, the Artificial Intelligence Section (now the Software Technology Branch) had developed over a dozen prototype expert systems applications using state-of-the-art hardware and software. However, despite extensive demonstrations of the potential of expert systems, few of these applications were put into regular use. This failure to provide expert systems technology within NASA's operational computing constraints could largely be traced to the use of LISP as the base language for nearly all expert system software tools at that time. In particular, three problems hindered the use of LISP based expert system tools within NASA: the low availability of LISP on a wide variety of conventional computers, the high cost of state-of-the-art LISP tools and hardware, and the poor integration of LISP with other languages (making embedded applications difficult).

The Artificial Intelligence Section felt that the use of a conventional language, such as C, would eliminate most of these problems, and initially looked to the expert system tool vendors to provide an expert system tool written using a conventional language. Although a number of tool vendors started converting their tools to run in C, the cost of each tool was still very high, most were restricted to a small variety of computers, and the projected availability times were discouraging. To meet all of its needs in a timely and cost effective manner, it became evident that the Artificial Intelligence Section would have to develop its own C based expert system tool.

The prototype version of CLIPS was developed in the spring of 1985 in a little over two months. Particular attention was given to making the tool compatible with expert systems under development at that time by the Artificial Intelligence Section. Thus, the syntax of CLIPS was made to very closely resemble the syntax of a subset of the ART expert system tool developed by Inference Corporation. Although originally modelled from ART, CLIPS was developed entirely without assistance from Inference or access to the ART source code.

The original intent for CLIPS was to gain useful insight and knowledge about the construction of expert system tools and to lay the groundwork for the construction of a replacement tool for the commercial tools currently being used. Version 1.0 demonstrated the feasibility of the project concept. After additional development, it became apparent that CLIPS would be a low cost expert system tool ideal for the purposes of training. Another year of development and internal use went into CLIPS improving its portability, performance, functionality, and supporting documentation. Version 3.0 of CLIPS was made available to groups outside of NASA in the summer of 1986.

Further enhancements transformed CLIPS from a training tool into a tool useful for the development and delivery of expert systems as well. Versions 4.0 and 4.1 of CLIPS, released

respectively in the summer and fall of 1987, featured greatly improved performance, external language integration, and delivery capabilities. Version 4.2 of CLIPS, released in the summer of 1988, was a complete rewrite of CLIPS for code modularity. Also included with this release were an architecture manual providing a detailed description of the CLIPS software architecture and a utility program for aiding in the verification and validation of rule-based programs. Version 4.3 of CLIPS, released in the summer of 1989, added still more functionality.

Originally, the primary representation methodology in CLIPS was a forward chaining rule language based on the Rete algorithm (hence the Production System part of the CLIPS acronym). Version 5.0 of CLIPS, released in the spring of 1991, introduced two new programming paradigms: procedural programming (as found in languages such as C and Ada) and object-oriented programming (as found in languages such as the Common Lisp Object System and Smalltalk). The object-oriented programming language provided within CLIPS is called the CLIPS Object-Oriented Language (COOL). Version 5.1 of CLIPS, released in the fall of 1991, was primarily a software maintenance upgrade required to support the newly developed and/or enhanced X Window, MS-DOS, and Macintosh interfaces. Version 6.0 of CLIPS, released in 1993, provided support for the development of modular programs and tight integration between the object-oriented and rule-based programming capabilities of CLIPS.

Because of its portability, extensibility, capabilities, and low-cost, CLIPS has received widespread acceptance throughout the government, industry, and academia. The development of CLIPS has helped to improve the ability to deliver expert system technology throughout the public and private sectors for a wide range of applications and diverse computing environments. CLIPS is being used by numerous users throughout the public and private community including: all NASA sites and branches of the military, numerous federal bureaus, government contractors, universities, and many private companies.

CLIPS is now maintained as public domain software by the main program authors who no longer work for NASA. See appendix A of the *Basic Programming Guide* for information on obtaining CLIPS and support.

CLIPS Version 6.1

Version 6.1 of CLIPS contains two major enhancements. First, the CLIPS source code is now C++ compatible. It can now be compiled using either an ANSI C or C++ compiler. Second, several new commands provide the ability to profile the time spent in constructs and user-defined functions. For a detailed listing of differences between versions 5.1 and 6.0 of CLIPS and differences between the 6.x releases, refer to appendices B and C of the *Basic Programming Guide* and appendices C and D of the *Advanced Programming Guide*.

xii Preface

CLIPS Documentation

Two documents are provided with CLIPS.

- The *CLIPS Reference Manual* which is split into the following parts:
 - *Volume I The Basic Programming Guide*, which provides the definitive description of CLIPS syntax and examples of usage.
 - *Volume II The Advanced Programming Guide*, which provides detailed discussions of the more sophisticated features in CLIPS and is intended for people with extensive programming experience who are using CLIPS for advanced applications.
 - Volume III The Interfaces Guide, which provides information on machine-specific interfaces.
- The *CLIPS User's Guide* which provides an introduction to CLIPS rule-based and object-oriented programming and is intended for people with little or no expert system experience.

Acknowledgements

As with any large project, CLIPS is the result of the efforts of numerous people. The primary contributors have been: Robert Savely, previous branch chief of the STB and now chief scientist of advanced software technology at JSC, who conceived the project and provided overall direction and support; Chris Culbert, current branch chief of the STB, who managed the project, wrote the original *CLIPS Reference Manual*, and designed the original version of CRSV; Gary Riley, who designed and developed the rule-based portion of CLIPS, co-authored the *CLIPS Reference Manual* and *CLIPS Architecture Manual*, and developed the Macintosh interface for CLIPS; Brian Donnell, who designed and developed the CLIPS Object Oriented Language (COOL), co-authored the *CLIPS Reference Manual* and *CLIPS Architecture Manual*, and developed the previous MS-DOS interfaces for CLIPS; Bebe Ly, who was responsible for maintenance and enhancements to CRSV and is now responsible for developing the X Window interface for CLIPS; Chris Ortiz, who developed the Windows 95 interface for CLIPS; Dr. Joseph Giarratano of the University of Houston-Clear Lake, who wrote the *CLIPS User's Guide*; and Frank Lopez, who designed and developed CLIPS version 1.0 and wrote the CLIPS 1.0 User's Guide.

Many other individuals contributed to the design, development, review, and general support of CLIPS, including: Jack Aldridge, Carla Armstrong, Paul Baffes, Ann Baker, Stephen Baudendistel, Les Berke, Tom Blinn, Marlon Boarnet, Dan Bochsler, Bob Brown, Barry Cameron, Tim Cleghorn, Major Paul Condit, Major Steve Cross, Andy Cunningham, Dan Danley, Mark Engelberg, Kirt Fields, Ken Freeman, Kevin Greiner, Ervin Grice, Sharon Hecht, Patti Herrick, Mark Hoffman, Grace Hua, Gordon Johnson, Phillip Johnston, Sam Juliano, Ed Lineberry, Bowen Loftin, Linda Martin, Daniel McCoy, Terry McGregor, Becky McGuire, Scott Meadows, C. J. Melebeck, Paul Mitchell, Steve Mueller, Bill Paseman, Cynthia Rathjen, Eric Raymond, Reza Razavipour, Marsha Renals, Monica Rua, Tim Saito, Michael Sullivan, Gregg Swietek, Eric Taylor, James Villarreal, Lui Wang, Bob Way, Jim Wescott, Charlie Wheeler, and Wes White.

Section 1 - Introduction

This manual is the *Advanced Programming Guide* for CLIPS. It is intended for users interested in the more sophisticated features of CLIPS. It is written with the assumption that the user has a complete understanding of the basic features of CLIPS and a background in programming. Many sections will not be understandable without a working knowledge of C. Knowledge of other languages also may be helpful. The information presented here will require some experience to understand, but every effort has been made to implement capabilities in a simple manner consistent with the portability and efficiency goals of CLIPS.

Section 2 describes how to install and tailor CLIPS to meet specific needs. Section 3 of this document describes how to add user-defined functions to a CLIPS expert system. Section 4 describes how to embed a CLIPS application in a C program. Section 5 describes how to create run-time CLIPS programs. Section 6 discusses integrating CLIPS with languages other than C. Section 7 details the input/ output (I/O) router system used by CLIPS and how the user can define his own I/O routers. Section 8 discusses CLIPS memory management.

Not all of the features documented here will be of use to all users. Users should pick those areas which are of specific use to them. It is advised that users complete the *Basic Programming Guide* before reading this manual.

1.1 WARNING ABOUT INTERFACING WITH CLIPS

CLIPS provides numerous methods for integrating with user-defined code. As with any powerful capability, some care must be taken when using these features. By providing users with the ability to access internal information, we have also opened the door to the possibility of users corrupting or destroying data that CLIPS needs to work properly. Users are advised to be careful when dealing with data structures or strings which are returned from calls to CLIPS functions. Generally, these data structures represent useful information to CLIPS and should not be modified or changed in any way except as described in this manual. A good rule of thumb is to duplicate in user-defined storage space every piece of information taken out of or passed into CLIPS. In particular, *do not* store pointers to strings returned by CLIPS as part of a permanent data structure. When CLIPS performs garbage collection on symbols and strings, the pointer reference to the string may be rendered invalid. To store a permanent reference to a string, allocate storage for a copy of the string and then copy the string returned by CLIPS to the copy's storage area.

1.2 C++ COMPATIBILITY

The CLIPS source code can now be compiled using either an ANSI C or C++ compiler. Minimally, non-ANSI C compilers must support full ANSI style function prototypes and the void data type in order to compile CLIPS.

Section 2 - Installing and Tailoring CLIPS

This section describes how to install and tailor CLIPS to meet specific needs.

2.1 INSTALLING CLIPS

CLIPS executables for DOS, Windows 95, and MacOS are available for download from the internet. See Appendix A in the *Basic Programming Guide* for details. To tailor CLIPS or to install it on another machine, the user must port the source code and create a new executable version.

Testing of CLIPS 6.10 included the following hardware/software environments:

- HP Pavilion running Windows 95 with DJGPP v2.01 (for creating 32-bit protected mode DOS applications), Borland C++ v5.0, and CodeWarrior Professional Release 3.
- PowerTower Pro running MacOS 8.1 using MachTen 4.03 and CodeWarrior Professional Release 3.

CLIPS was designed specifically for portability and has been installed on numerous other computers without making modifications to the source code. It *should* run on any system which supports an ANSI C or C++ compiler. Some compilers have extended syntax to support a particular platform which will add additional reserved words to the C language. In the event that this extended syntax conflicts with the CLIPS source, the user will have to edit the code. This usually only involves a global search-and-replace of the particular reserved word. The following steps describe how to create a new executable version of CLIPS:

1) Load the source code onto the user's system

The following C source files are necessary to set up the basic CLIPS system:

agenda.h	dffnxpsr.h	incrrset.h	predrpsr.h
analysis.h	dfinsbin.h	inherpsr.h	prdctfun.h
argacces.h	dfinscmp.h	inscom.h	prntutil.h
bload.h	drive.h	insfile.h	proflfun.h
bmathfun.h	ed.h	insfun.h	reorder.h
bsave.h	emathfun.h	insmngr.h	reteutil.h
classcom.h	engine.h	insmoddp.h	retract.h
classexm.h	evaluatn.h	insmult.h	router.h
classfun.h	expressn.h	inspsr.h	rulebin.h
classinf.h	exprnbin.h	insquery.h	rulebld.h
classini.h	exprnops.h	insqypsr.h	rulebsc.h
classpsr.h	exprnpsr.h	iofun.h	rulecmp.h

clips.h	extnfunc.h	lgcldpnd.h	rulecom.h
clsltpsr.h	extobj.h	match.h	rulecstr.h
cmptblty.h	factbin.h	memalloc.h	ruledef.h
commline.h	factbld.h	miscfun.h	ruledlt.h
conscomp.h	factomp.h	modulbin.h	rulelhs.h
constant.h	factcom.h	modulbsc.h	rulepsr.h
constrct.h	factfun.h	modulemp.h	scanner.h
construt.h		moduldef.h	
	factgen.h facthsh.h		setup.h shrtlnkn.h
crstrtgy.h cstrcbin.h	factlhs.h	modulpsr.h modulutl.h	sortfun.h
	factmch.h		~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~ ~
cstrccmp.h		msgcom.h	strngfun.h
cstrccom.h	factmngr.h	msgfun.h	strngrtr.h
cstrcpsr.h	factprt.h	msgpass.h	symblbin.h
cstrnbin.h	factrete.h	msgpsr.h	symblemp.h
cstrnchk.h	factrhs.h	multifld.h	symbol.h
cstrncmp.h	filecom.h	multifun.h	sysdep.h
cstrnops.h	filertr.h	network.h	textpro.h
cstrnpsr.h	generate.h	objbin.h	tmpltbin.h
cstrnutl.h	genrcbin.h	objcmp.h	tmpltbsc.h
default.h	genrccmp.h	object.h	tmpltcmp.h
defins.h	genrccom.h	objrtbin.h	tmpltdef.h
developr.h	genrcexe.h	objrtbld.h	tmpltfun.h
dffctbin.h	genrcfun.h	objrtcmp.h	tmpltlhs.h
dffctbsc.h	genrcpsr.h	objrtfnx.h	tmpltpsr.h
dffctcmp.h	globlbin.h	objrtgen.h	tmpltrhs.h
dffctdef.h	globlbsc.h	objrtmch.h	tmpltutl.h
dffctpsr.h	globlcmp.h	parsefun.h	userdata.h
dffnxbin.h	globlcom.h	pattern.h	utility.h
dffnxcmp.h	globldef.h	pprint.h	watch.h
dffnxexe.h	globlpsr.h	prccode.h	
dffnxfun.h	immthpsr.h	prcdrfun.h	
agenda.c	drive.c	immthpsr.c	predrpsr.c
analysis.c	edbasic.c	incrrset.c	prdctfun.c
argacces.c	edmain.c	inherpsr.c	prntutil.c
bload.c	edmisc.c	inscom.c	proflfun.c
bmathfun.c	edstruct.c	insfile.c	reorder.c
bsave.c	edterm.c	insfun.c	reteutil.c
classcom.c	emathfun.c	insmngr.c	retract.c
classexm.c	engine.c	insmoddp.c	router.c
classfun.c	evaluatn.c	insmult.c	rulebin.c
classinf.c	expressn.c	inspsr.c	rulebld.c
classini.c	exprnbin.c	insquery.c	rulebsc.c
		-	

classpsr.c	exprnops.c	insqypsr.c	rulecmp.c
clsltpsr.c	exprnpsr.c	iofun.c	rulecom.c
commline.c	extnfunc.c	lgcldpnd.c	rulecstr.c
conscomp.c	factbin.c	main.c	ruledef.c
constrct.c	factbld.c	memalloc.c	ruledlt.c
constrnt.c	factcmp.c	miscfun.c	rulelhs.c
crstrtgy.c	factcom.c	modulbin.c	rulepsr.c
cstrcbin.c	factfun.c	modulbsc.c	scanner.c
cstrccom.c	factgen.c	modulemp.c	sortfun.c
cstrcpsr.c	facthsh.c	moduldef.c	strngfun.c
cstrnbin.c	factlhs.c	modulpsr.c	strngrtr.c
cstrnchk.c	factmch.c	modulutl.c	symblbin.c
cstrncmp.c	factmngr.c	msgcom.c	symblemp.c
cstrnops.c	factprt.c	msgfun.c	symbol.c
cstrnpsr.c	factrete.c	msgpass.c	sysdep.c
cstrnutl.c	factrhs.c	msgpsr.c	textpro.c
default.c	filecom.c	multifld.c	tmpltbin.c
defins.c	filertr.c	multifun.c	tmpltbsc.c
developr.c	generate.c	objbin.c	tmpltcmp.c
dffctbin.c	genrcbin.c	objemp.c	tmpltdef.c
dffctbsc.c	genrccmp.c	objrtbin.c	tmpltfun.c
dffctcmp.c	genrccom.c	objrtbld.c	tmpltlhs.c
dffctdef.c	genrcexe.c	objrtcmp.c	tmpltpsr.c
dffctpsr.c	genrcfun.c	objrtfnx.c	tmpltrhs.c
dffnxbin.c	genrcpsr.c	objrtgen.c	tmpltutl.c
dffnxcmp.c	globlbin.c	objrtmch.c	userdata.c
dffnxexe.c	globlbsc.c	parsefun.c	utility.c
dffnxfun.c	globlcmp.c	pattern.c	watch.c
dffnxpsr.c	globlcom.c	pprint.c	
dfinsbin.c	globldef.c	prccode.c	
dfinscmp.c	globlpsr.c	predrfun.c	

Additional files must also be included if one of the machine specific user interfaces is to be set up. See the *Utilities and Interfaces Guide* for details on compiling the machine specific interfaces.

2) Modify all include statements (if necessary)

All of the ".c" files and most of the ".h" files have #include statements. These #include statements may have to be changed to either match the way the compiler searches for include files or to include a different ".h" file.

3) Tailor CLIPS environment and/or features

Edit the setup.h file and set any special options. CLIPS uses compiler directives to allow machine-dependent features. The first flag in the setup.h file tells CLIPS on what kind of machine the code is being compiled. The default setting for this flag is GENERIC, which will create a version of CLIPS that will run on any computer. The user may set this flag for the user's type of system. If the system type is unknown, the first flag should be set to GENERIC. If you change the system type to anything other than GENERIC, make sure that the version number of your compiler is greater than or equal to the version number listed in the setup.h file (as earlier versions of a compiler may not support some system dependent features). Other flags in the setup.h file also allow a user to tailor the features in CLIPS to specific needs. For more information on using the flags, see section 2.2

4) Compile all of the ".c" files to object code

Use the standard compiler syntax for the user's machine. The ".h" files are include files used by the other files and do not need to be compiled. Some options may have to be set, depending on the compiler.

If user-defined functions are needed, compile the source code for those functions as well and modify the UserFunctions definition in main.c to reflect the user's functions (see section 3 for more on user-defined functions).

5) Create the interactive CLIPS executable element

To create the interactive CLIPS executable, link together all of the object files. This executable will provide the interactive interface defined in section 2.1 of the *Basic Programming Guide*.

2.1.1 Additional Considerations

Although compiling CLIPS should not be difficult even for inexperienced C programmers, some non-obvious problems can occur. One type of problem is linking with inappropriate system libraries. Normally, default libraries are specified through the environment; i.e., not specified as a part of the compile/link process. On occasion, the default system libraries are inappropriate for use with CLIPS. For example, when using a compiler which supports different memory models, be sure to link with the system libraries that match the memory model under which the CLIPS code was compiled. The same can be said for floating-point models. Some computers provide multiple ways of storing floating-point numbers (typically differing in accuracy or speed of processing). Be sure to link with system libraries that use the same storage formats with which the CLIPS code was compiled. Some additional considerations for compiling CLIPS with specific compilers and/or operating systems are described following.

DJGPP v2.01

The CLIPS 32 bit DOS executable for 386 or higher PCs was created using the free DJGPP C compiler. This executable can access memory beyond the DOS 640K limit, but your environment must have DMPI services available in order to run this executable. If you are

running Windows 3.1, Windows 95, or OS/2, DPMI services are provided for you. Information on this compiler is available at the WWW URL http://www.delorie.com/djgpp/. A free DPMI server is also available at this location.

The built-in MicroEMACS editor will not work with this compiler, so the **EMACS_EDITOR** compiler directive in setup.h should be set to 0. With the compiler installed, the following command will compile CLIPS

```
gcc -o clipsdos *.c -lm
```

UNIX

If the **EX_MATH** compiler directive is enabled, then the **-lm** option must be used when compiling CLIPS with the gcc command. Similary, if the **EMACS_EDITOR** compiler directive is enabled, the **-ltermcap** option must be used when compiling CLIPS. If all of the CLIPS source code is contained in the same directory and the compiler directives are set to their default values in the **setup.h** file, then the following command line will compile CLIPS

```
gcc -o clips *.c -lm -ltermcap
```

2.2 TAILORING CLIPS

CLIPS makes use of compiler directives to allow easier porting and recompiling of CLIPS. Compiler directives allow the incorporation of system-dependent features into CLIPS and also make it easier to tailor CLIPS to specific applications. All available compiler options are controlled by a set of flags defined in the **setup.h** file.

The first flag in **setup.h** indicates on what type of compiler/machine CLIPS is to run. The source code is sent out with the flag for GENERIC CLIPS turned on. When compiled in this mode, all system-dependent features of CLIPS are excluded and the program should run on any system. A number of other flags are available in this file, indicating the types of compilers/machines on which CLIPS has been compiled previously. If the user's implementation matches one of the available flags, set that flag to 1 and turn the GENERIC flag off (set it to 0). The code for most of the features controlled by the compiler/machine-type flag is in the **sysdep.c** file.

Many other flags are provided in setup.h. Each flag is described below.

RUN_TIME

This flag will create a run-time version of CLIPS for use with compiled constructs. It should be turned on only *after* the constructs-to-c function has been used to generate the C code representation of the constructs, but *before* compiling the constructs C code. When used, about 90K of memory can be saved from the basic CLIPS executable. See section 5 for a description of how to use this. This is off in the standard CLIPS executable.

DEFRULE_CONSTRUCT

This flag controls the use of the defrule construct. If it is off, the defrule construct is not recognized by CLIPS. This is on in the standard CLIPS executable.

CONFLICT_RESOLUTION_STRATEGIES

This flag controls the availability of conflict resolution strategies (see sections 5.2 and 5.3 of the *Basic Programming Guide*) for use with the defrule construct. If it is off, then the depth conflict resolution strategy is the only strategy used and the functions setstrategy and get-strategy are not available. This is on in the standard CLIPS executable.

DYNAMIC_SALIENCE

This flag controls the availability of dynamic salience (see sections 5.2 and 5.4.9 of the *Basic Programming Guide*) for use with the defrule construct. If it is off, then dynamic salience can not be used and the functions refresh-agenda, get-salience-evaluation, and get-salience-evaluation are not available. This is on in the standard CLIPS executable.

INCREMENTAL RESET

This flag controls the availability of incremental reset (see sections 5.1 and 12.1.7 of the *Basic Programming Guide*) for use with the defrule construct. If it is off, then newly defined rules are not aware of facts or instances that were created before the rule was defined. In addition, the functions set-incremental-reset and get-incremental-reset are not available if this flag is off. This is on in the standard CLIPS executable.

LOGICAL DEPENDENCIES

This flag controls the availability of logical dependencies (see section 5.4.8 of the *Basic Programming Guide*) for use with the defrule construct. If it is off, then the logical CE cannot be used on the LHS of a rule and the functions dependencies and dependents are not available. This is on in the standard CLIPS executable.

DEFFACTS CONSTRUCT

This flag controls the use of deffacts. If it is off, deffacts are not allowed which can save some memory and performance during resets. This is on in the standard CLIPS executable. If this flag is off, the (initial-fact) fact is still created during a reset if the DEFTEMPLATE_CONSTRUCT flag is on.

DEFTEMPLATE_CONSTRUCT

This flag controls the use of deftemplate. If it is off, deftemplate is not allowed which can save some memory. This is on in the standard CLIPS executable.

DEFGLOBAL_CONSTRUCT

This flag controls the use of defglobal. If it is off, defglobal is not allowed which can save some memory. This is on in the standard CLIPS executable.

DEFFUNCTION CONSTRUCT

This flag controls the use of deffunction. If it is off, deffunction is not allowed which can save some memory. This is on in the standard CLIPS executable.

DEFGENERIC CONSTRUCT

This flag controls the use of defgeneric and defmethod. If it is off, defgeneric and defmethod are not allowed which can save some memory. This is on in the standard CLIPS executable.

IMPERATIVE METHODS

This flag determines if the following functions are available for use in generic function methods: **next-methodp**, **call-next-method**, **override-next-method** and **call-specific-method**. These functions allow imperative control over the generic dispatch by calling shadowed methods (see section 8.5.3 of the *Basic Programming Guide*). This flag is on in the standard CLIPS executable. Turning this flag off can save some memory and marginally increase the speed of the generic dispatch.

OBJECT SYSTEM

This flag controls the use of defclass, definstances, and defmessage-handler. If it is off, these constructs are not allowed which can save some memory. If this flag is on, the MULTIFIELD_FUNCTIONS flag should also be on if you want to be able to manipulate multifield slots. This is on in the standard CLIPS executable.

DEFINSTANCES_CONSTRUCT

This flag controls the use of definstances (see section 9.6.1.1 of the *Basic Programming Guide*). If it is off, definstances are not allowed which can save some memory and performance during resets. This is on in the standard CLIPS executable. If this flag is off, the [initial-object] instance is still created during a reset if the INSTANCE_PATTERN_MATCHING flag is on.

IMPERATIVE_MESSAGE_HANDLERS

This flag determines if **around** message-handlers and the following functions are available for use in object message dispatch: **next-handlerp**, **call-next-handler** and **override-next-handler**. These functions allow imperative control over the message dispatch by calling shadowed message-handlers (see section 9.5.3 of the *Basic Programming Guide*). This flag is on in the standard CLIPS executable. Turning this flag off can save some memory and marginally increase the speed of the message dispatch.

AUXILIARY_MESSAGE_HANDLERS

This flag determines if **before** and **after** message-handlers are available for use in object message dispatch. These handler types enhance declarative control over the message dispatch (see section 9.4.3 of the *Basic Programming Guide*). This flag is on in the standard CLIPS executable. Turning this flag off can save some memory and marginally increase the speed of the message dispatch.

INSTANCE_SET_QUERIES

This flag determines if the instance-set query functions are available: **any-instance**, **find-instance**, **find-all-instances**, **do-for-instance**, **do-for-all-instances** and **delayed-do-for-all-instances**. This is on in the standard CLIPS executable. Turning this flag off can save some memory.

INSTANCE PATTERN MATCHING

This flag controls the ability to include object patterns on the LHS of rules (see section 5.4.1.8 of the *Basic Programming Guide*). This is on in the standard CLIPS executable. Turning this flag off can save some memory.

BLOAD INSTANCES

This flag controls the ability to load instances in binary format from a file via the **bload-instances** command (see section 13.11.4.7 of the *Basic Programming Guide*). This is on in the standard CLIPS executable. Turning this flag off can save some memory.

BSAVE_INSTANCES

This flag controls the ability to save instances in binary format to a file via the **bsave-instances** command (see section 13.11.4.4 of the *Basic Programming Guide*). This is on in the standard CLIPS executable. Turning this flag off can save some memory.

DEFMODULE_CONSTRUCT

This flag controls the use of the defmodule construct. If it is off, then new defmodules cannot be defined (however the MAIN module will exist). This is on in the standard CLIPS executable.

EX MATH

This flag indicates whether the extended math package should be included in the compilation. If this flag is turned off (set to 0), the final executable will be about 25-30K smaller, a consideration for machines with limited memory. This is on in the standard CLIPS executable.

TEXTPRO_FUNCTIONS

This flag controls the CLIPS text-processing functions. It must be turned on to use the **fetch**, **toss**, and **print-region** functions in a user-defined help system. It also must be turned on to use the on-line help system. This is on in the standard CLIPS executable.

HELP_FUNCTIONS

If this flag is on, the on-line help system will be available from the CLIPS top-level interface. When this is turned on, the **HELP_DEFAULT** flag should be set to point to the full path name for the CLIPS help file. This is on in the standard CLIPS executable.

EMACS_EDITOR

This flag controls the integrated MicroEMACS editor. If it is turned on, the editor will be available. If it is turned off, the editor will not be available but about 40K of memory will be saved. NOTE: The editor is machine dependent and will not run on all machines. See the **setup.h** file for a description of which machines can support the editor. This is on in the standard CLIPS executable.

CONSTRUCT COMPILER

This flag controls the construct compiler functions. If it is turned on, constructs may be compiled to C code for use in a run-time module (see section 5). This is off in the standard CLIPS executable.

BLOAD_ONLY

This flag controls access to the binary and ASCII load commands (bload and load). This would be used to save some memory in systems which require binary load capability only. This flag is off in the standard CLIPS executable.

BLOAD

This flag controls access to the binary load command (bload). This would be used to save some memory in systems which require

binary load but not save capability. This is off in the standard CLIPS executable.

BLOAD_AND_BSAVE

This flag controls access to the binary load and save commands. This would be used to save some memory in systems which require neither binary load nor binary save capability. This is on in the standard CLIPS executable.

BASIC IO

This flag controls access to the basic I/O functions in CLIPS. These functions are printout, read, open, and close. If this flag is off, these functions are not available. This would be used to save some memory in systems which used custom I/O routines. This is on in the standard CLIPS executable.

EXT IO

This flag controls access to the extended I/O functions in CLIPS. These functions are format and readline. If this flag is off, these functions are not available. This would be used to save some memory in systems which used custom I/O routines or only the basic I/O routines. This is on in the standard CLIPS executable.

MULTIFIELD_FUNCTIONS

This flag controls access to the multifield manipulation functions in CLIPS. These functions are subseq\$, delete\$, insert\$, replace\$, explode\$, implode\$, nth\$, member\$, first\$, rest\$, progn\$, and subsetp. The function create\$ is always available regardless of the setting of this flag. This would be used to save some memory in systems which performed limited or no operations with multifield values. This flag is on in the standard CLIPS executable.

STRING FUNCTIONS

This flag controls access to the string manipulation functions in CLIPS. These functions are str-cat, sym-cat, str-length, str-compare, upcase, lowcase, sub-string, str-index, eval, and build. This would be used to save some memory in systems which perform limited or no operations with strings. This flag is on in the standard CLIPS executable.

DEBUGGING FUNCTIONS

This flag controls access to commands such as agenda, facts, ppdefrule, ppdeffacts, etc. This would be used to save some memory in BLOAD_ONLY or RUN_TIME systems. This flag is on in the standard CLIPS executable.

BLOCK_MEMORY

This option controls memory allocation. If the flag is on, memory is allocated from the operating system in large blocks. This can improve performance if the system memory allocation routines are extremely inefficient or place arbitrary restrictions on the number of memory allocations that can be made. This flag is off in the standard CLIPS executable.

WINDOW_INTERFACE

This flag indicates that a windowed interface is being used. Currently, the help system uses this flag to determine whether it should handle more processing by itself or allow the interface to take care of more processing. This is off in the standard CLIPS executable.

SHORT_LINK_NAMES

ANSI C compilers must be able to distinguish between identifiers which use at least 31 significant characters. Some linkers, however, use considerably fewer characters when determining name conflicts (potentially as few as 6 characters). If this flag is on, then identifiers which cannot be uniquely distinguished within 6 characters are replaced with alternate names that are distinguishable with 6 characters. This is off in the standard CLIPS executable.

Section 3 - Integrating CLIPS with External Functions

One of the most important features of CLIPS is an ability to integrate CLIPS with **external functions** or applications. This section discusses how to add external functions to CLIPS and how to pass arguments to them and return values from them. A user can define external functions for use by CLIPS at any place a function can normally be called. In fact, the vast majority of system defined functions and commands provided by CLIPS are integrated with CLIPS in the exact same manner described in this section. The examples shown in this section are in C, but section 6 discusses how other languages can be combined with CLIPS. Prototypes for the functions listed in this section can be included by using the **clips.h** header file.

3.1 DECLARING USER-DEFINED EXTERNAL FUNCTIONS

All external functions must be described to CLIPS so they can be properly accessed by CLIPS programs. User-defined functions are described to CLIPS by modifying the function **UserFunctions**. This function is initially in the CLIPS **main.c** file and may be modified there or moved to a user's file. Within **UserFunctions**, a call should be made to the **DefineFunction** routine for every function which is to be integrated with CLIPS. The user's source code then can be compiled and linked with CLIPS.

An example **UserFunctions** declaration follows:

The first argument to **DefineFunction** is the CLIPS function name, a string representation of the name that will be used when calling the function from within CLIPS.

The second argument is the type of the value which will be returned to CLIPS. Note that this is not necessarily the same as the function type. Allowable return types are shown as follows:

Return Code	Return Type Expected
a	External Address
b	Boolean
c	Character
d	Double Precision Float
f	Single Precision Float
i	Integer
j	Unknown Data Type (Symbol, String, or Instance Name Expected)
k	Unknown Data Type (Symbol or String Expected)
1	Long Integer
m	Multifield
n	Unknown Data Type (Integer or Float Expected)
0	Instance Name
S	String
u	Unknown Data Type (Any Type Expected)
V	Void—No Return Value
W	Symbol
X	Instance Address

Boolean functions should return a value of type int (0 for the symbol FALSE and any other value for the symbol TRUE). String, symbol, instance name, external address, and instance address functions should return a pointer of type void *. Character return values are converted by CLIPS to a symbol of length one. Integer return values are converted by CLIPS to long integers for internal storage. Single precision float values are converted by CLIPS to double precision float values for internal storage. If a user function is not going to return a value to CLIPS, the function should be defined as type void and this argument should be v for void. Return types o and x are only available if the object system has been enabled (see section 2.2).

Function types j, k, m, n, and u are all passed a data object as an argument in which the return value of function is stored. This allows a user defined function to return one of several possible return types. Function type u is the most general and can return any data type. By convention, function types j, k, m, and n return specific data types. CLIPS will signal an error if one of these functions return a disallowed type. See section 3.3.4 for more details on returning unknown data types.

The third argument is a pointer to the actual function, the compiled function name (an **extern** declaration of the function may be appropriate). The CLIPS name (first argument) need not be the same as the actual function name (third argument). The macro identifier PTIF can be placed in front of a function name to cast it as a pointer to a function returning an integer (primarily to prevent warnings from compilers which allow function prototypes).

The fourth argument is a string representation of the third argument (the pointer to the actual C function). This name *should be identical* to the third argument, but enclosed in quotation marks.

DefineFunction returns zero if the function was unsuccessfully called (e.g. bad function type parameter), otherwise a non-zero value is returned.

User-defined functions are searched before system functions. If the user defines a function which is the same as one of the defined functions already provided, the user function will be executed in its place. Appendix A of the *Basic Programming Guide* contains a list of function names used by CLIPS.

In place of **DefineFunction**, the **DefineFunction2** function can be used to provide additional information to CLIPS about the number and types of arguments expected by a CLIPS function or command.

The first four arguments to **DefineFunction2** are identical to the four arguments for **DefineFunction**. The fifth argument is a restriction string which indicates the number and types of arguments that the CLIPS function expects. The syntax format for the restriction string is

```
<min-args> <max-args> [<default-type> <types>*]
```

The values <min-args> and <max-args> must be specified in the string. Both values must either be a character digit (0-9) or the character *. A digit specified for <min-args> indicates that the function must have at least <min-args> arguments when called. The character * for this value indicates that the function does not require a minimum number of arguments. A digit specified for <max-args> indicates that the function must have no more than <max-args> arguments when called. The character * for this value indicates that the function does not prohibit a maximum number of arguments. The optional <default-type> is the assumed type for each argument for a function call. Following the <default-type>, additional type values may be supplied to indicate specific type values for each argument. The type codes for the arguments are as follows:

Type Code	Allowed Types
a	External Address
d	Float
e	Instance Address, Instance Name, or Symbol
f	Float
g	Integer, Float, or Symbol
h	Instance Address, Instance Name, Fact Address, Integer, or Symbol
i	Integer
j	Symbol, String, or Instance Name
k	Symbol or String
1	Integer
m	Multifield
n	Integer or Float
O	Instance Name
p	Instance Name or Symbol
q	Symbol, String, or Multifield
S	String
u	Any Data Type
W	Symbol
X	Instance Address
У	Fact Address
Z	Fact address, Integer, or Symbol

Examples

The restriction string for a function requiring a minimum of three arguments is:

"3*"

The restriction string for a function requiring no more than five arguments is:

" * 5 "

The restriction string for a function requiring at least three and no more than five arguments (each of which must be an integer or float) is:

"35n"

The restriction string for a function requiring exactly six arguments (of which the first must be a string, the third an integer, and the remaining arguments floats) is:

"66fsui"

3.2 PASSING ARGUMENTS FROM CLIPS TO EXTERNAL FUNCTIONS

Although arguments are listed directly following a function name within a function call, CLIPS actually calls the function without any arguments. The arguments are stored internally by CLIPS and can be accessed by calling the argument access functions. Access functions are provided to determine both the number and types of arguments.

3.2.1 Determining the Number of Passed Arguments

User-defined functions should first determine that they have been passed the correct number of arguments. Several functions are provided for this purpose.

```
int RtnArgCount();
int ArgCountCheck(functionName, restriction, count);
int ArgRangeCheck(functionName, min, max);
int restriction, count, min, max;
char *functionName;
```

A call to **RtnArgCount** will return an integer telling how many arguments with which the function was called. The function **ArgCountCheck** can be used for error checking if a function expects a minimum, maximum, or exact number of arguments (but not a combination of these restrictions). It returns an integer telling how many arguments with which the function was called (or -1 if the argument restriction for the function was unsatisfied). The first argument is the name of the function to be printed within the error message if the restriction is unsatisfied. The *restriction* argument should be one of the values NO_MORE_THAN, AT_LEAST, or EXACTLY. The *count* argument should contain a value for the number of arguments to be used in the restriction test. The function **ArgRangeCheck** can be used for error checking if a function expects a range of arguments. It returns an integer telling how many arguments with which the function was called (or -1 if the argument restriction for the function was unsatisfied). The first argument is the name of the function to be printed within the error message if the restriction is unsatisfied. The second argument is the minimum number of arguments and the third argument is the maximum number of arguments.

3.2.2 Passing Symbols, Strings, Instance Names, Floats, and Integers

Several access functions are provided to retrieve arguments that are symbols, strings, instance names, floats, and integers.

```
char    *RtnLexeme(argumentPosition);
double    RtnDouble(argumentPosition);
long    RtnLong(argumentPosition);
int    argumentPosition;
```

A call to **RtnLexeme** returns a character pointer from either a symbol, string, or instance name data type (NULL is returned if the type is not SYMBOL, STRING, or INSTANCE_NAME), **RtnDouble** returns a floating-point number from either an INTEGER or FLOAT data type, and **RtnLong** returns a long integer from either an INTEGER or FLOAT data type. The arguments have to be requested one at a time by specifying each argument's position number as the *argumentPosition* to **RtnLexeme**, **RtnDouble**, or **RtnLong**. If the type of argument is unknown, another function can be called to determine the type. See section 3.2.3 for a further discussion of unknown argument types. *Do not* store the pointer returned by **RtnLexeme** as part of a permanent data structure. When CLIPS performs garbage collection on symbols and strings, the pointer reference to the string may be rendered invalid. To store a permanent reference to a string, allocate storage for a copy of the string and then copy the string returned by **RtnLexeme** to the copy's storage area.

Example

The following code is for a function to be called from CLIPS called **rta** which will return the area of a right triangle.

```
*/
                        /* This include definition
#include "clips.h"
                       /* should start each file which */
                       /* has CLIPS functions in it
Use DefineFunction2("rta", 'd', PTIF rta, "rta", "22n");
double rta()
  double base, height;
  /*=======*/
  /* Check for exactly two arguments. */
  /*=======*/
  if (ArgCountCheck("rta", EXACTLY, 2) == -1) return(-1.0);
  /*=========*/
  /* Get the values for the 1st and 2nd arguments. */
  /*----*/
  base = RtnDouble(1);
  height = RtnDouble(2);
  /*======*/
  /* Return the area of the triangle. */
  /*=======*/
  return(0.5 * base * height);
 }
```

As previously shown, **rta** also should be defined in **UserFunctions**. If the value passed from CLIPS is not the data type expected, an error occurs. Section 3.2.3 describes a method for testing the data type of the passed arguments which would allow user-defined functions to do their own

error handling. Once compiled and linked with CLIPS, the function **rta** could be called as shown following.

3.2.3 Passing Unknown Data Types

Section 3.2.2 described how to pass data to and from CLIPS when the type of data is explicitly known. It also is possible to pass parameters of an unknown data type to and from external functions. To pass an unknown parameter *to* an external function, use the **RtnUnknown** function.

```
#include "clips.h"
                              /* or "evaluatn.h" */
DATA_OBJECT *RtnUnknown(argumentPosition, &argument);
       GetType(argument);
int
       GetpType(&argument);
int
       ArgTypeCheck(char *, argumentPosition,
int
                    expectedType, &argument);
char
      *DOToString(argument);
      *DOPToString(&argument);
char
double DOToDouble(argument);
double DOPToDouble(&argument);
float DOToFloat(argument);
      DOPToFloat(&argument);
float
       DOToLong(argument);
long
       DOPToLong(&argument);
long
       DOToInteger(argument);
int
int
       DOPToInteger(&argument);
      *DOToPointer(argument);
voi d
      *DOPToPointer(&argument);
int argumentPosition, expectedType;
DATA_OBJECT argument;
```

Function **RtnUnknown** should be called first. It copies the elements of the internal CLIPS structure that represent the unknown-type argument into the DATA_OBJECT structure pointed to by the second argument. It also returns a pointer to that same structure, passed as the second argument. After obtaining a pointer to the DATA_OBJECT structure, a number of macros can be used to extract type information and the arguments value.

Macros **GetType** or **GetpType** can be used to determine the type of argument and will return an integer (STRING, SYMBOL, FLOAT, INTEGER, MULTIFIELD, INSTANCE_ADDRESS,

INSTANCE_NAME, or EXTERNAL_ADDRESS) defined in the **clips.h** file. Once the data type is known, the functions **DOToDouble**, **DOPToDouble**, **DOToFloat**, or **DOPToFloat** (for FLOAT), **DOToString**, or **DOPToString** (for STRING, SYMBOL, or INSTANCE_NAME), **DOToLong**, **DOPToLong**, **DOToInteger**, or **DOPToInteger** (for INTEGER), and **DOToPointer** and **DOPToPointer** (for INSTANCE_ADDRESS and EXTERNAL_ADDRESS) can be used to extract the actual value of the variable from the DATA_OBJECT structure. Accessing multifield values is discussed in section 3.2.4. *Do not* store the pointer returned by **DOToString** or **DOPToString** as part of a permanent data structure. When CLIPS performs garbage collection on symbols and strings, the pointer reference to the string may be rendered invalid. To store a permanent reference to a string, allocate storage for a copy of the string and then copy the string returned by **DOToString** or **DOPToString** to the copy's storage area.

The function **ArgTypeCheck** can be used for error checking if a function expects a specific type of argument for a particular parameter. It returns a non-zero integer value if the parameter was of the specified type, otherwise it returns zero. The first argument is the name of the function to be printed within the error message if the type restriction is unsatisfied. The second argument is the index of the parameter to be tested. The third argument is the type restriction and must be one of the following CLIPS defined constants: STRING, SYMBOL, SYMBOL_OR_STRING, FLOAT, INTEGER, INTEGER_OR_FLOAT, MULTIFIELD, EXTERNAL_ADDRESS, INSTANCE_ADDRESS, INSTANCE_NAME, or INSTANCE_OR_INSTANCE_NAME. If the FLOAT type restriction is used, then integer values will be converted to floating-point numbers. If the INTEGER type restriction is used, then floating-point values will be converted to integers. The fourth argument is a pointer to a DATA_OBJECT structure in which the unknown parameter will be stored.

Example

The following function **mul** takes two arguments from CLIPS. Each argument should be either an integer or a float. Float arguments are rounded and converted to the nearest integer. Once converted, the two arguments are multiplied together and this value is returned. If an error occurs (wrong type or number of arguments), then the value 1 is returned.

```
{ return(1L); }
/*----*/
/* Get the first argument using the ArgTypeCheck function. */
/* Return if the correct type has not been passed.
/*----*/
if (ArgTypeCheck("mul", 1, INTEGER_OR_FLOAT, &temp) == 0)
 { return(1L); }
/*-----*/
/* Convert the first argument to a long integer. If it's not */
/* an integer, then it must be a float (so round it to the */
/* nearest integer using the C library ceil function.
/*----*/
if (GetType(temp) == INTEGER)
 { firstNumber = DOToLong(temp); }
else /* the type must be FLOAT */
 { firstNumber = (long) ceil(DOToDouble(temp) - 0.5); }
/*-----*/
/* Get the second argument using the RtnUnknown function. */
/* Note that no type error checking is performed. */
/*========*/
RtnUnknown(2, &temp);
/*-----*/
/* Convert the second argument to a long integer. If it's */
/* not an integer or a float, then it's the wrong type. */
/*----*/
if (GetType(temp) == INTEGER)
 { secondNumber = DOToLong(temp); }
else if (GetType(temp) == FLOAT)
 { secondNumber = (long) ceil(DOToDouble(temp) - 0.5); }
else
 { return(1L); }
/*-----*/
/* Multiply the two values together and return the result. */
/*----*/
return (firstNumber * secondNumber);
```

Once compiled and linked with CLIPS, the function **mul** could be called as shown following.

```
CLIPS> (mul 3 3)
9
CLIPS> (mul 3.1 3.1)
9
CLIPS> (mul 3.8 3.1)
12
CLIPS> (mul 3.8 4.2)
16
CLIPS>
```

3.2.4 Passing Multifield Values

Data passed from CLIPS to an external function may be stored in multifield values. To access a multifield value, the user first must call **RtnUnknown** or **ArgTypeCheck** to get the pointer. If the argument is of type MULTIFIELD, several macros can be used to access the values of the multifield value.

```
#include "clips.h"
                               /* or "evaluatn.h" */
       GetD0Length(argument);
i nt
i nt
       GetpD0Length(&argument);
i nt.
       GetDOBegin(argument);
int
       GetpDOBegin(&argument);
       GetD0End(argument);
i nt
int
       GetpD0End(&argument);
       GetMFType(multifieldPtr, fieldPosition);
i nt
     *GetMFValue(multifieldPtr, fieldPosition);
DATA_OBJECT argument;
void *multifieldPtr;
int fieldPosition;
```

Macros GetDOLength and GetpDOLength can be used to determine the length of a DATA_OBJECT or DATA_OBJECT_PTR respectively. The macros GetDOBegin, GetpDOBegin, GetpDOEnd, GetpDOEnd can be used to determine the beginning and ending indices of a DATA_OBJECT or DATA_OBJECT_PTR containing a multifield value. Since multifield values are often extracted from arrays of other data structures (such as facts), these indices are used to indicate the beginning and ending positions within the array. Thus it is very important when traversing a multifield value to use indices that run from the begin index to the end index and not from one to the length of the multifield value. The begin index points to the first element in the multifield value and the end index points to the last element in the multifield value. A multifield value of length one will have the same values for the begin and end indices. A multifield value of length zero will have an end index that is one less than the begin index.

The macros **GetMFType** and **GetMFValue** can be used to examine the types and values of fields within a multifield value. The first argument to these macros should be the value retrieved from a DATA_OBJECT or DATA_OBJECT_PTR using the **GetValue** and **GetpValue** macros. The second argument is the index of the field within the multifield value. Once again, this argument should fall in the range between the begin index and the end index for the DATA_OBJECT from which the multifield value is stored. Macros **ValueToString**, **ValueToDouble**, **ValueToLong**, and **ValueToInteger** can be used to convert the retrieved value from **GetMFValue** to a C object of type char *, double, and long respectively. *Do not* store the pointer returned by **ValueToString** as part of a permanent data structure. When CLIPS performs garbage collection on symbols and strings, the pointer reference to the string may be rendered invalid. To store a permanent reference to a string, allocate storage for a copy of the string and then copy the string returned by **ValueToString** to the copy's storage area.

The multifield macros should only be used on DATA_OBJECTs that have type MULTIFIELD (e.g. the macro GetDOLength returns erroneous values if the type is not MULTIFIELD).

Examples

The following function returns the length of a multifield value. It returns -1 if an error occurs.

```
#include "clips.h"
Use DefineFunction2("mfl", 'l', PTIF MFLength, "MFLength", "11m");
long int MFLength()
  DATA_OBJECT argument;
  /*=======*/
  /* Check for exactly one argument. */
  /*=======*/
  if (ArgCountCheck("mfl", EXACTLY, 1) == -1) return(-1L);
  /*=========*/
  /* Check that the 1st argument is a multifield value. */
  /*=========*/
  if (ArgTypeCheck("mfl", 1, MULTIFIELD, &argument) == 0)
   { return(-1L); }
  /*=======*/
  /* Return the length of the multifield value. */
  /*========*/
  return ( (long) GetDOLength(argument));
```

The following function counts the number of characters in the symbols and strings contained within a multifield value.

```
/*=======*/
if (ArgCountCheck("cmfc", EXACTLY, 1) == -1) return(0L);
/*----*/
/* Check that the first argument is a multifield value. */
/*===========*/
if (ArgTypeCheck("cmfc", 1, MULTIFIELD, &argument) == 0)
 { return(OL); }
/*_____*/
/* Count the characters in each field. */
/*======*/
end = GetD0End(argument);
multifieldPtr = GetValue(argument);
for (i = GetDOBegin(argument); i \le end; i++)
  if ((GetMFType(multifieldPtr,i) == STRING) ||
     (GetMFType(multifieldPtr,i) == SYMBOL))
    tempPtr = ValueToString(GetMFValue(multifieldPtr,i));
    count += strlen(tempPtr);
 }
/*=======*/
/* Return the character count. */
/*======*/
return(count);
```

3.3 RETURNING VALUES TO CLIPS FROM EXTERNAL FUNCTIONS

Functions which return doubles, floats, integers, long integers, characters, external addresses, and instance addresses can directly return these values to CLIPS. Other data types including the unknown (or unspecified) data type and multifield data type, must use functions provided by CLIPS to construct return values.

3.3.1 Returning Symbols, Strings, and Instance Names

CLIPS uses symbol tables to store all symbols, strings, and instance names. Symbol tables increase both performance and memory efficiency during execution. If a user-defined function returns a symbol, string, or an instance name (type 's', 'w', or 'o' in **DefineFunction**), the symbol must be stored in the CLIPS symbol table prior to use. Other types of returns (such as unknown and multifield values) may also contain symbols which must be added to the symbol table. These symbols can be added by calling the function **AddSymbol** and using the returned pointer value.

```
#include "clips.h" /* or "symbol.h" */
```

```
void *AddSymbol(string);
char *string;
```

Example

This function reverses the character ordering in a string and returns the reversed string. The null string is returned if an error occurs.

```
/* ANSI C library header file */
#include <stdlib.h>
                       /* ANSI C library header file */
#include <stddef.h>
#include "clips.h"
Use DefineFunction2("reverse-str", 's', PTIF Reverse, "Reverse",
               "11s"):
*/
void *Reverse()
  DATA_OBJECT temp;
  char *lexeme, *tempString;
  void *returnValue;
  int i, length;
  /*=======*/
  /* Check for exactly one argument. */
  /*=======*/
  if (ArgCountCheck("reverse-str", EXACTLY, 1) == -1)
   { return(AddSymbol("")); }
  /*----*/
  /* Get the first argument using the ArgTypeCheck function. */
  /*----*/
  if (ArgTypeCheck("reverse-str", 1, STRING, &temp) == 0)
   { return(AddSymbol("")); }
  lexeme = DOToString(temp);
  /*----*/
  /* Allocate temporary space to store the reversed string. */
  /*==============*/
  length = strlen(lexeme);
  tempString = (char *) malloc(length + 1);
  /*=======*/
  /* Reverse the string. */
  /*=======*/
  for (i = 0; i < length; i++)
   { tempString[length - (i + 1)] = lexeme[i]; }
  tempString[length] = '\0';
  /*=======*/
  /* Return the reversed string. */
  /*======*/
```

```
returnValue = AddSymbol(tempString);
free(tempString);
return(returnValue);
}
```

3.3.2 Returning Boolean Values

A user function may return a boolean value in one of two ways. The user may define an integer function and use **DefineFunction** to declare it as a BOOLEAN type ('b'). The function should then either return the value **TRUE** or **FALSE**. Alternatively, the function may be declare to return a SYMBOL type ('w') or UNKNOWN type ('u') and return the symbol **FalseSymbol** or **TrueSymbol**.

```
#include "clips.h" /* or "symbol.h" */
#define FALSE 0
#define TRUE 1

void *FalseSymbol
void *TrueSymbol
```

Examples

This function returns true if its first argument is a number greater than zero. It uses a boolean return value.

```
#include "clips.h"
Use DefineFunction2("positivep1", 'b', positivep1, "positivep1",
              "11n");
* /
int positivep1()
  DATA_OBJECT temp;
  /*=======*/
  /* Check for exactly one argument. */
  /*=======*/
  if (ArgCountCheck("positivep1", EXACTLY, 1) == -1)
   { return(FALSE); }
  /*==========*/
  /* Get the first argument using the ArgTypeCheck function. */
  /*----*/
  if (ArgTypeCheck("positivep1", 1, INTEGER_OR_FLOAT, &temp) == 0)
   { return(FALSE); }
  /*==========*/
  /* Determine if the value is positive. */
  /*==========*/
```

```
if (GetType(temp) == INTEGER)
   { if (DOToLong(temp) <= 0L) return(FALSE); }
else /* the type must be FLOAT */
   { if (DOToDouble(temp) <= 0.0) return(FALSE); }
return(TRUE);
}</pre>
```

This function also returns true if its first argument is a number greater than zero. It uses a symbolic return value.

```
#include "clips.h"
Use DefineFunction("positivep2", 'w', PTIF positivep2, "positivep2",
               "11n");
void *positivep2()
  DATA OBJECT temp;
  /*----*/
  /* Check for exactly one argument. */
  /*=======*/
  if (ArgCountCheck("positivep1", EXACTLY, 1) == -1)
    { return(FalseSymbol); }
  /*=============*/
  /* Get the first argument using the ArgTypeCheck function. */
  /*===========*/
  if (ArgTypeCheck("positivep1", 1, INTEGER_OR_FLOAT, &temp) == 0)
    { return(FalseSymbol); }
  /*==========*/
  /* Determine if the value is positive. */
  /*==========*/
  if (GetType(temp) == INTEGER)
    { if (DOToLong(temp) <= OL) return(FalseSymbol); }
  else /* the type must be FLOAT */
    { if (DOToDouble(temp) <= 0.0) return(FalseSymbol); }
  return(TrueSymbol);
```

3.3.3 Returning External Addresses and Instance Addresses

A user function may return an external address or an instance address. The user should use **DefineFunction** to declare their function as returning an external address type ('a') or an instance address type ('x'). The function should then either return a pointer that has been typecast to (void *). Within CLIPS, the printed representation of an external address is

```
<Pointer-XXXXXXXXX
```

where XXXXXXX is the external address. Note that it is up to the user to make sure that external addresses remain valid within CLIPS. The printed representation of an instance address is

```
<Instance-XXX>
```

where XXX is the name of the instance.

Example

This function uses the memory allocation function malloc to dynamically allocated 100 bytes of memory and then returns a pointer to the memory to CLIPS.

3.3.4 Returning Unknown Data Types

A user-defined function also may return values of an unknown type. The user must declare the function as returning type unknown; i.e., place a 'u' for data type in the call to **DefineFunction**. The user function will be passed a pointer to a structure of type DATA_OBJECT (DATA_OBJECT_PTR) which should be modified to contain the return value. The user should set both the type and the value of the DATA_OBJECT. Note that the value of a DATA_OBJECT cannot be directly set to a double or long value (the functions **AddLong** and **AddDouble** should be used in a manner similar to **AddSymbol**). The actual return value of the user function is ignored.

```
#include "clips.h"
                               /* or "evaluatn.h" */
i nt
       SetType(argument, type)
       SetpType(&argument, type)
i nt
      *SetValue(argument, value)
voi d
      *SetpValue(&argument, value)
voi d
      *AddLong(longValue);
voi d
      *AddDouble(doubleValue);
voi d
voi d
      *GetValue(argument);
      *GetpValue(&argument);
voi d
```

```
char *ValueToString(value);
double ValueToDouble(value);
long ValueToLong(value);
int ValueToInteger(value);

long longValue;
double doubleValue;
void *value;
int type;
DATA_OBJECT argument;
```

Macros **SetType** and **SetpType** can be used to set the type of a DATA_OBJECT or DATA_OBJECT_PTR respectively. The type parameter should be one of the following CLIPS defined constants (note that these are not strings): SYMBOL, STRING, INTEGER, FLOAT, EXTERNAL_ADDRESS, INSTANCE_NAME, or INSTANCE_ADDRESS. Macros **SetValue** (for DATA_OBJECTs) and **SetpValue** (for DATA_OBJECT_PTRs) can be used to set the value of a DATA_OBJECT. The functions **AddSymbol** (for symbols, strings and instance names), **AddLong** (for integers) and **AddDouble** (for floats) can be used to produce values that can be used with these macros (external addresses and instance addresses can be used directly). Macros **GetValue** (for DATA_OBJECTs) and **GetpValue** (for DATA_OBJECT_PTRs) can be used to retrieve the value of a DATA_OBJECT. Note that the value for an external address or an instance address can be retrieved directly using one of these macros. For other data types, the macros **ValueToString** (for symbols, strings, and instance names), **ValueToLong** (for integers), **ValueToInteger** (for integers), and **ValueToDouble** (for floats) can be used to convert the retrieved value from a DATA_OBJECT to a C object of type char *, double, long, or integer respectively.

Example

This function "cubes" its argument returning either an integer or float depending upon the type of the original argument. It returns the symbol FALSE upon an error.

```
#include "clips.h"

/*
Use DefineFunction2("cube", 'u', PTIF cube, "cube", "11n");

*/

void cube(
   DATA_OBJECT_PTR returnValuePtr)
{
   void *value;
   long longValue;
   double doubleValue;

   /*============*/
   /* Check for exactly one argument. */
   /*==========*/
   if (ArgCountCheck("cube", EXACTLY, 1) == -1)
    {
       SetpType(returnValuePtr, SYMBOL);
   }
}
```

```
SetpValue(returnValuePtr, FalseSymbol);
  return;
/*-----*/
/* Get the first argument using the ArgTypeCheck function. */
/*-----*/
if (! ArgTypeCheck("cube", 1, INTEGER_OR_FLOAT, returnValuePtr))
  SetpType(returnValuePtr, SYMB0L);
  SetpValue(returnValuePtr, FalseSymbol);
  return;
/*-----*/
/* Cube the argument. Note that the return value DATA_OBJECT */
/* is used to retrieve the function's argument and return
/* the function's return value.
/*-----*/
if (GetpType(returnValuePtr) == INTEGER)
  value = GetpValue(returnValuePtr);
  longValue = ValueToLong(value);
  value = AddLong(longValue * longValue * longValue);
else /* the type must be FLOAT */
 {
  value = GetpValue(returnValuePtr);
  doubleValue = ValueToDouble(value);
  val ue = AddDoubl e(doubl eVal ue * doubl eVal ue * doubl eVal ue);
/*-----*/
/* Set the value of the return DATA_OBJECT. The return */
/* type does not have to be changed since it will be */
/* the same as the 1st argument to the function.
/*-----*/
SetpValue(returnValuePtr, value);
return;
```

3.3.5 Returning Multifield Values

Multifield values can also be returned from an external function. When defining such an external function, the data type should be set to 'm' in the call to **DefineFunction**. Note that a multifield value can also be returned from a 'u' function, whereas only a multifield value should be returned from an 'm' function. As with returning unknown data types, the user function will be passed a pointer of type DATA_OBJECT_PTR which can be modified to set up a multifield value. The following macros and functions are useful for this purpose:

```
voi d
      *CreateMultifield(size);
       SetMFType(multifieldPtr, fieldPosition, type);
i nt
      *SetMFValue(multifieldPtr, fieldPosition, value);
voi d
       Set DOBegin (return Value, field Position);
i nt
       SetpDOBegin(&returnValue, fieldPosition);
i nt
       SetDOEnd(returnValue, fieldPosition);
int
       SetpD0End(&returnValue, fieldPosition);
i nt
voi d
       Set Mul ti fi el dError Val ue (&return Val ue);
DATA_OBJECT returnValue;
int size, fieldPosition;
void *multifieldPtr;
void *value;
```

If a new multifield is to be created from an existing multifield, then the type and value of the existing multifield can be copied and the begin and end indices can be modified to obtain the appropriate subfields of the multifield value. If you wish to create a new multifield value that is not part of an existing multifield value, then use the function **CreateMultifield**. Given an integer argument, this function will create a multifield value of the specified size with valid indices ranging from one to the given size (zero is a legitimate parameter to create a multifield value with no fields). The macros **SetMFType** and **SetMFValue** can be used to set the types and values of the fields of the newly created multifield value. Both macros accept as their first argument the value returned by **CreateMultifield**. The second argument should be an integer representing the position of the multifield value to be set. The third argument is the same as the arguments used for **SetType** and **SetValue** macros.

Do *not* set the value or type of any field within a multifield value that has been returned to you by CLIPS. Use these macros only on multifield values created using the **CreateMultifield** function.

The macros **SetDOBegin**, **SetpDOBegin**, **SetpDOEnd**, **SetpDOEnd** can be used to assign values to the begin and end indices of a DATA_OBJECT or DATA_OBJECT_PTR containing a multifield value. These macros are useful for creating "new" multifield values by manipulating the indices of a currently existing multifield value. For example, a function that returns the first field of a multifield value could do so by setting the end index equal to the begin index (if the length of the multifield value was greater than zero).

The function **SetMultifieldErrorValue** can be used to create a multifield value of length zero (which is useful to return as an error value). Its only parameter is a DATA_OBJECT_PTR which is appropriately modified to create a zero length multifield value.

Examples

The following example creates a multifield value with two fields, a word and a number:

```
#include "clips.h"
```

```
Use DefineFunction2("sample4", 'm', PTIF sample4, "sample4", "00");
void sample4(
 DATA_OBJECT_PTR returnValuePtr)
  void *multifieldPtr;
  /*========*/
  /* Check for exactly zero arguments. */
  /*=======*/
  if (ArgCountCheck("sample4", EXACTLY, 0) == -1)
    SetMul ti fi el dErrorVal ue(returnVal uePtr);
    return:
  /*==========*/
  /* Create a multi-field value of length 2 */
  /*==========*/
  multifieldPtr = CreateMultifield(2);
  /*========*/
  /* The first field in the multi-field value
  /* will be a SYMBOL. Its value will be
  /* "altitude".
                                        * /
  /*========*/
  SetMFType(multifieldPtr, 1, SYMBOL);
  SetMFValue(multifieldPtr, 1, AddSymbol("altitude"));
  /*==========*/
  /* The second field in the multi-field value */
  /* will be a FLOAT. Its value will be 900. */
  /*=========*/
  SetMFType(multifieldPtr, 2, FLOAT);
  SetMFValue(multifieldPtr, 2, AddDouble(900.0));
  ^{\prime *} Assign the type and value to the return DATA_OBJECT. ^{*\prime }
  /*-----*/
  SetpType(returnValuePtr, MULTIFIELD);
  SetpValue(returnValuePtr, multifieldPtr);
  /*=============*/
  /* The length of our multi-field value will be 2.
  /* Since we will create our own multi-field value
  /* the begin and end indexes to our function will
                                            */
  /* be 1 and the length of the multi-field value
                                            */
  /* respectively. If we are examining a multi-field */
  /* value, or using an existing multi-field value
                                           * /
  /* to create a new multi-field value, then the
                                            */
  /* begin and end indexes may not correspond to 1
                                            */
```

```
/* and the length of the multi-field value.
   /*========*/
   SetpD0Begin(returnValuePtr, 1);
   SetpD0End(returnValuePtr, 2);
   return;
  }
The following example returns all but the first field of a multifield value:
#include "clips.h"
/*
Use DefineFunction2("rest", 'm', PTIF rest, "rest", "11m");
void rest(
  DATA_OBJECT_PTR returnValuePtr)
   /*=======*/
   /* Check for exactly one argument. */
   /*=======*/
   if (ArgCountCheck("rest", EXACTLY, 1) == -1)
     SetMul ti fi el dErrorVal ue(returnVal uePtr);
     return;
   /*======*/
   /* Check for a MULTIFIELD. */
   /*======*/
   if (ArgTypeCheck("rest", 1, MULTIFIELD, returnValuePtr) == 0)
     SetMultifieldErrorValue(returnValuePtr);
     return:
    }
   /*========*/
   /* Don't bother with a zero length multifield value. */
   /*========*/
   if (GetpDOBegin(returnValuePtr) > GetpDOEnd(returnValuePtr))
    { return; }
   /*=======*/
   /* Increment the begin index by one. */
   /*=======*/
   SetpD0Begin(returnValuePtr, GetpD0Begin(returnValuePtr) + 1);
```

3.4 USER-DEFINED FUNCTION EXAMPLE

This section lists the steps needed to define and implement a user-defined function. The example given is somewhat trivial, but it demonstrates the point. The user function merely triples a number and returns the new value.

- 1) Copy all of the CLIPS source code file to the user directory.
- 2) Define the user function in a new file.

```
#include "clips.h"
double TripleNumber()
   {
    return(3.0 * RtnDouble(1));
}
```

The preceding function does the job just fine. The following function, however, accomplishes the same purpose while providing error handling on arguments and allowing either an integer or double return value.

```
#include "clips.h"
void TripleNumber(
 DATA_OBJECT_PTR returnValuePtr)
             *value:
  voi d
  long
              longValue;
  doubl e
              doubl eVal ue:
  /*==========*/
  /* If illegal arguments are passed, return zero. */
  /*========*/
  if (ArgCountCheck("triple", EXACTLY, 1) == -1)
     SetpType(returnValuePtr, INTEGER);
     SetpValue(returnValuePtr, AddLong(0L));
     return;
  if (! ArgTypeCheck("triple", 1, INTEGER_OR_FLOAT, returnValuePtr))
     SetpType(returnValuePtr, INTEGER);
     SetpValue(returnValuePtr, AddLong(0L));
     return;
  /*=======*/
  /* Triple the number. */
  /*======*/
  if (GetpType(returnValuePtr) == INTEGER)
     value = GetpValue(returnValuePtr);
```

```
longValue = 3 * ValueToLong(value);
SetpValue(returnValuePtr, AddLong(longValue));
}
else /* the type must be FLOAT */
{
  value = GetpValue(returnValuePtr);
  doubleValue = 3.0 * ValueToDouble(value);
  SetpValue(returnValuePtr, AddDouble(doubleValue));
}
return;
}
```

3) Define the constructs which use the new function in a new file (or in an existing constructs file). For example:

```
(deffacts init-data
    (data 34)
    (data 13.2))

(defrule get-data
    (data ?num)
=>
    (printout t "Tripling " ?num crlf)
    (assert (new-value (triple ?num))))

(defrule get-new-value
    (new-value ?num)
=>
    (printout t crlf "Now equal to " ?num crlf))
```

4) Modify the CLIPS **main.c** file to include the new UserFunctions definition.

- 5) Compile the CLIPS files along with any files which contain user-defined functions.
- 6) Link all object code files.
- 7) Execute new CLIPS executable. Load the constructs file and test the new function.

Section 4 - Embedding CLIPS

CLIPS was designed to be embedded within other programs. When CLIPS is used as an embedded application, the user must provide a main program. Calls to CLIPS are made like any other subroutine. To embed CLIPS, add the following include statements to the user's main program file:

```
#include <stdio.h>
#include "clips.h"
```

(These statements may have to be tailored so the compiler on the user's system can find the CLIPS include file.) The user's main program must initialize CLIPS by calling the function **InitializeEnvironment** at some time prior to loading constructs. **UserFunctions** also must be defined, regardless of whether CLIPS calls any external functions. Compile and link all of the user's code with all CLIPS files *except* the object version of **main.c**. When running CLIPS as an embedded program, many of the capabilities available in the interactive interface (in addition to others) are available through function calls. The functions are documented in the following sections. Prototypes for these functions can be included by using the **clips.h** header file.

4.1 ENVIRONMENT FUNCTIONS

The following function calls control the CLIPS environment:

4.1.1 AddClearFunction

```
int AddClearFunction(clearItemName, clearFunction, priority);
char *clearItemName;
void (*clearFunction)();
int priority;
void clearFunction();
```

Purpose:

Adds a user defined function to the list of functions which are called when the CLIPS **clear** command is executed.

Arguments:

- 1) The name of the new clear item.
- 2) A pointer to the function which is to be called whenever a **clear** command is executed.
- 3) The priority of the clear item which determines the order in which clear items are called (higher priority items are called first). The values -2000 to 2000 are reserved for CLIPS system defined clear items and should not be used for user defined clear items.

Returns:

Returns a zero value if the clear item could not be added, otherwise a non-zero value is returned.

4.1.2 AddPeriodicFunction

Purpose:

Adds a user defined function to the list of functions which are called periodically while CLIPS is executing. This ability was primarily included to allow interfaces to process events and update displays during CLIPS execution. Care should be taken not to use any operations in a periodic function which would affect CLIPS data structures constructively or destructively, i.e. CLIPS internals may be examined but not modified during a periodic function.

Arguments:

- 1) The name of the new periodic item.
- 2) A pointer to a function which is to be called periodically while CLIPS is executing.
- 3) The priority of the periodic item which determines the order in which periodic items are called (higher priority items are called first). The values -2000 to 2000 are reserved for CLIPS system defined periodic items and should not be used for user defined periodic items.

Returns:

Returns a zero value if the periodic item could not be added, otherwise a non-zero value is returned.

4.1.3 AddResetFunction

```
int AddResetFunction(resetItemName, resetFunction, priority);
char *resetItemName;
void (*resetFunction)();
int priority;
void resetFunction();
```

Purpose:

Adds a user defined function to the list of functions which are called when the CLIPS **reset** command is executed.

Arguments:

1) The name of the new reset item.

- 2) A pointer to the function which is to be called whenever a **reset** command is executed.
- 3) The priority of the reset item which determines the order in which reset items are called (higher priority items are called first). The values -2000 to 2000 are reserved for CLIPS system defined reset items and should not be used for user defined reset items.

Returns:

Returns a zero value if the reset item could not be added, otherwise a non-zero value is returned.

4.1.4 Bload

```
int Bload(fileName);
char *fileName;
```

Purpose: Loads a binary image of constructs into the CLIPS data base (the C

equivalent of the CLIPS bload command).

Arguments: A string representing the name of the file.

Returns: Returns an integer; if zero, an error occurred. A positive one is

returned upon success.

4.1.5 Bsave

```
int Bsave(fileName);
char *fileName;
```

Purpose: Saves a binary image of constructs from the CLIPS data base (the C

equivalent of the CLIPS bsave command).

Arguments: A string representing the name of the file.

Returns: Returns an integer; if zero, an error occurred. A positive one is

returned upon success.

4.1.6 Clear

void Clear();

Purpose: Clears the CLIPS environment (the C equivalent of the CLIPS clear

command).

Arguments: None.

Returns: No meaningful return value.

4.1.7 FunctionCall

```
void FunctionCall(functionName, arguments, &result);
char *functionName, *arguments;
DATA_OBJECT result;
```

Purpose: Allows CLIPS system functions, deffunctions and generic functions

to be called from C.

Arguments:

1) The name of the system function, deffunction or generic

function to be called.

2) A string containing any *constant* arguments separated by blanks

(this argument can be NULL).

3) Caller's buffer for storing the result of the function call. See sections 3.2.3 and 3.2.4 for information on getting the value

stored in a DATA_OBJECT.

Returns: No meaningful return value.

Example

```
DATA_OBJECT rtn;
FunctionCall("+", "1 2", &rtn);
```

4.1.8 GetAutoFloatDividend

```
int GetAutoFloatDividend();
```

Purpose: Returns the current value of the auto-float dividend behavior (the C

equivalent of the CLIPS get-auto-float-dividend command).

Arguments: None.

Returns: An integer; FALSE (0) if the behavior is disabled and TRUE (1) if

the behavior is enabled.

4.1.9 GetDynamicConstraintChecking

int GetDynamicConstraintChecking();

Purpose: Returns the current value of the dynamic constraint checking

behavior (the C equivalent of the CLIPS

get-dynamic-constraint-checking command).

Arguments: None.

Returns: An integer; FALSE (0) if the behavior is disabled and TRUE (1) if

the behavior is enabled.

4.1.10 GetSequenceOperatorRecognition

int GetSequenceOperatorRecognition();

Purpose: Returns the current value of the sequence operator recognition

behavior (the C equivalent of the CLIPS get-sequence-operator-

recognition command).

Arguments: None.

Returns: An integer; FALSE (0) if the behavior is disabled and TRUE (1) if

the behavior is enabled.

4.1.11 GetStaticConstraintChecking

int GetStaticConstraintChecking();

Purpose: Returns the current value of the static constraint checking behavior

(the C equivalent of the CLIPS get-static-constraint-checking

command).

Arguments: None.

Returns: An integer; FALSE (0) if the behavior is disabled and TRUE (1) if

the behavior is enabled.

4.1.12 InitializeEnvironment

void InitializeEnvironment();

Purpose: Initializes the CLIPS system. Must be called prior to any other

CLIPS function call. NOTE: This function should be called only

once.

Arguments: None.

Returns: No meaningful return value.

4.1.13 Load

```
int Load(fileName);
char *fileName;
```

Purpose: Loads a set of constructs into the CLIPS data base (the C equivalent

of the CLIPS load command).

Arguments: A string representing the name of the file.

Returns: Returns an integer; Zero if the file couldn't be opened, -1 if the file

was opened but an error occurred while loading, and 1 if the file was opened an no errors occurred while loading. If syntactic errors are in the constructs, **Load** still will attempt to read the entire file

and error notices will be sent to werror.

Other: The load function is not available for use in run-time programs

(since individual constructs can't be added or deleted). To execute different sets of constructs, the switching feature must be used in a

run-time program (see section 5 for more details).

4.1.14 RemoveClearFunction

int RemoveClearFunction(clearItemName);
char *clearItemName;

Purpose: Removes a named function from the list of functions to be called

during a clear command.

Arguments: The name associated with the user-defined clear function. This is

the same name that was used when the clear function was added

with the function AddClearFunction.

Returns: Returns the integer value 1 if the named function was found and

removed, otherwise 0 is returned.

4.1.15 RemovePeriodicFunction

```
int RemovePeriodicFunction(periodicItemName);
char *periodicItemName;
```

Purpose: Removes a named function from the list of functions which are

called periodically while CLIPS is executing.

Arguments: The name associated with the user-defined periodic function. This

is the same name that was used when the periodic function was

added with the function AddPeriodicFunction.

Returns: Returns the integer value 1 if the named function was found and

removed, otherwise 0 is returned.

4.1.16 RemoveResetFunction

int RemoveResetFunction(resetItemName);
char *resetItemName;

Purpose: Removes a named function from the list of functions to be called

during a reset command.

Arguments: The name associated with the user-defined reset function. This is

the same name that was used when the reset function was added

with the function AddResetFunction.

Returns: Returns the integer value 1 if the named function was found and

removed, otherwise 0 is returned.

4.1.17 Reset

void Reset();

Purpose: Resets the CLIPS environment (the C equivalent of the CLIPS **reset**

command).

Arguments: None.

Returns: No meaningful return value.

4.1.18 Save

```
int Save(fileName);
char *fileName;
```

Purpose: Saves a set of constructs to the specified file (the C equivalent of

the CLIPS save command).

Arguments: A string representing the name of the file.

Returns: Returns an integer; if zero, an error occurred while opening the file.

If non-zero no errors were detected while performing the save.

4.1.19 SetAutoFloatDividend

int SetAutoFloatDividend(value);

int value;

Purpose: Sets the auto-float dividend behavior (the C equivalent of the

CLIPS **set-auto-float-dividend** command). When this behavior is enabled (by default) the dividend of the division function is

automatically converted to a floating point number.

Arguments: The new value for the behavior: TRUE (1) to enable the behavior

and FALSE (0) to disable it.

Returns: Returns the old value for the behavior.

4.1.20 SetDynamicConstraintChecking

int SetDynamicConstraintChecking(value);

int value;

Purpose: Sets the value of the dynamic constraint checking behavior (the C

equivalent of the CLIPS command **set-dynamic-constraint-checking**). When this behavior is disabled (FALSE by default), newly created data objects (such as deftemplate facts and instances) do not have their slot values checked for constraint violations. When this behavior is enabled (TRUE), the slot values are checked for constraint violations. The return value for this function is the old

value for the behavior.

Arguments: The new value for the behavior: TRUE (1) to enable the behavior

and FALSE (0) to disable it.

Returns: Returns the old value for the behavior.

4.1.21 SetSequenceOperator Recognition

int SetSequenceOperatorRecognition(value);

int value;

Purpose: Sets the sequence operator recognition behavior (the C equivalent

of the CLIPS **set-sequence-operator-recognition** command). When this behavior is disabled (by default) multifield variables found in function calls are treated as a single argument. When this behaviour is enabled, multifield variables are expanded and passed

as separate arguments in the function call.

Arguments: The new value for the behavior: TRUE (1) to enable the behavior

and FALSE (0) to disable it.

Returns: Returns the old value for the behavior.

4.1.22 SetStaticConstraintChecking

int SetStaticConstraintChecking(value);
int value;

Purpose:

Sets the value of the static constraint checking behavior (the C equivalent of the CLIPS command **set-static-constraint-checking**). When this behavior is disabled (FALSE), constraint violations are not checked when function calls and constructs are parsed. When this behavior is enabled (TRUE by default), constraint violations are checked when function calls and constructs are parsed. The return value for this function is the old value for the behavior.

Arguments: The new value for the behavior: TRUE (1) to enable the behavior

and FALSE (0) to disable it.

Returns: Returns the old value for the behavior.

4.1.23 BatchStar

int BatchStar(fileName);
char *fileName;

Purpose: Evaluates the series of commands stored in the specified file

without replacing standard input (the C equivalent of the CLIPS

batch* command).

Arguments: A string representing the name of the file.

Returns: Returns an integer; Zero if the file couldn't be opened or 1 if the file

was opened.

Other: The BatchStar function is not available for use in run-time

programs.

4.1.24 Build

```
int Build(constructString,);
char *constructString;
```

Purpose: Allows a construct to be defined (the C equivalent of the CLIPS

build command).

Arguments: 1) A string containing the construct to be added.

Returns: Returns an integer. 1 if the construct was successfully parsed,

otherwise 0.

Other: The Build function is not available for use in run-time programs

(since individual constructs can't be added or deleted).

4.1.25 Eval

```
int Eval(expressionString, &result);
char *expressionString;
DATA_OBJECT result;
```

Purpose: Allows an expression to be evaluated (the C equivalent of the

CLIPS eval command).

Arguments: 1) A string containing the expression to be evaluated.

2) Caller's buffer for storing the result of the evaluation. See

sections 3.2.3 and 3.2.4 for information on getting the value

stored in a DATA_OBJECT.

Returns: Returns an integer. 1 if the expression was successfully evaluated,

otherwise 0.

Other: The Eval function is not available for use in run-time programs

4.2 DEBUGGING FUNCTIONS

The following function call controls the CLIPS debugging aids:

4.2.1 DribbleActive

int DribbleActive();

Purpose: Determines if the storing of dribble information is active.

Arguments: None.

Returns: Zero if dribbling is not active, non-zero otherwise.

4.2.2 DribbleOff

int DribbleOff();

Purpose: Turns off the storing of dribble information (the C equivalent of the

CLIPS dribble-off command).

Arguments: None.

Returns: A zero if an error occurred closing the file; otherwise a one.

4.2.3 DribbleOn

```
int DribbleOn(fileName);
char *fileName;
```

Purpose: Allows the dribble function of CLIPS to be turned on (the C

equivalent of the CLIPS dribble-on command).

Arguments: The name of the file in which to store dribble information. Only one

dribble file may be opened at a time.

Returns: A zero if an error occurred opening the file; otherwise a one.

4.2.4 GetWatchItem

```
int GetWatchItem(item);
char *item;
```

Purpose: Returns the current value of a watch item.

Arguments: The item to be activated or deactivated which should be one of the

following strings: facts, rules, activations, focus, compilations, statistics, globals, instances, slots, messages, message-handlers,

generic-functions, method, or deffunctions.

Returns: Returns 1 if the watch item is enabled, 0 if the watch item is

disabled, and -1 if the watch item does not exist.

4.2.5 Unwatch

int Unwatch(item);
char *item;

Purpose: Allows the tracing facilities of CLIPS to be deactivated (the C

equivalent of the CLIPS unwatch command).

Arguments: The item to be deactivated which should be one of the following

strings: facts, rules, activations, focus, compilations, statistics, globals, deffunctions, instances, slots, messages, message-handlers, generic-functions, methods, or all. If all is selected, all possible

watch items will not be traced.

Returns: A one if the watch item was successfully set; otherwise a zero.

4.2.6 Watch

int Watch(item);
char *item;

Purpose: Allows the tracing facilities of CLIPS to be activated (the C

equivalent of the CLIPS watch command).

Arguments: The item to be activated which should be one of the following

strings: facts, rules, activations, focus, compilations, statistics, globals, deffunctions, instances, slots, messages, message-handlers, generic-functions, methods, or all. If all is selected, all possible

watch items will be traced.

Returns: A one if the watch item was successfully set; otherwise a zero.

4.3 DEFTEMPLATE FUNCTIONS

The following function calls are used for manipulating deftemplates.

4.3.1 DeftemplateModule

```
char *Deftempl ateModule(deftempl atePtr);
void *deftempl atePtr;
```

Purpose: Returns the module in which a deftemplate is defined (the C

equivalent of the CLIPS deftemplate-module command).

Arguments: A generic pointer to a deftemplate.

Returns: A string containing the name of the module in which the

deftemplate is defined.

4.3.2 FindDeftemplate

```
void *FindDeftemplate(deftemplateName);
char *deftemplateName;
```

Purpose: Returns a generic pointer to a named deftemplate.

Arguments: The name of the deftemplate to be found.

Returns: A generic pointer to the named deftemplate if it exists, otherwise

NULL.

4.3.3 GetDeftemplateList

```
void GetDeftemplateList(&returnValue, theModule);
DATA_OBJECT returnValue;
void *theModule;
```

Purpose: Returns the list of deftemplates in the specified module as a

multifield value in the returnValue DATA_OBJECT (the C

equivalent of the CLIPS **get-deftemplate-list** function).

Arguments: 1) A pointer to the caller's DATA_OBJECT in which the return

value will be stored. The multifield functions described in section 3.2.4 can be used to retrieve the deftemplate names from

the list.

2) A generic pointer to the module from which the list will be extracted. A NULL pointer indicates that the list is to be extracted from all modules.

Returns: No meaningful return value.

4.3.4 GetDeftemplateName

```
char *GetDeftemplateName(deftemplatePtr);
void *deftemplatePtr;
```

Purpose: Returns the name of a deftemplate.

Arguments: A generic pointer to a deftemplate data structure.

Returns: A string containing the name of the deftemplate.

4.3.5 GetDeftemplatePPForm

```
char *GetDeftemplatePPForm(deftemplatePtr);
void *deftemplatePtr;
```

Purpose: Returns the pretty print representation of a deftemplate.

Arguments: A generic pointer to a deftemplate data structure.

Returns: A string containing the pretty print representation of the deftemplate

(or the NULL pointer if no pretty print representation exists).

4.3.6 GetDeftemplateWatch

```
int GetDeftemplateWatch(deftemplatePtr);
void *deftemplatePtr;
```

Purpose: Indicates whether or not a particular deftemplate is being watched.

Arguments: A generic pointer to a deftemplate data structure.

Returns: An integer; one (1) if the deftemplate is being watched, otherwise a

zero (0).

4.3.7 GetNextDeftemplate

```
void *GetNextDeftemplate(deftemplatePtr);
```

void *deftemplatePtr;

Purpose: Provides access to the list of deftemplates.

Arguments: A generic pointer to a deftemplate data structure (or NULL to get

the first deftemplate).

Returns: A generic pointer to the first deftemplate in the list of deftemplates

if deftemplatePtr is NULL, otherwise a generic pointer to the deftemplate immediately following deftemplatePtr in the list of deftemplates. If deftemplatePtr is the last deftemplate in the list of

deftemplates, then NULL is returned.

4.3.8 IsDeftemplateDeletable

```
int IsDeftemplateDeletable(deftemplatePtr);
void *deftemplatePtr;
```

Purpose: Indicates whether or not a particular deftemplate can be deleted.

Arguments: A generic pointer to a deftemplate data structure.

Returns: An integer; zero (0) if the deftemplate cannot be deleted, otherwise

a one (1).

4.3.9 ListDeftemplates

```
void ListDeftemplates(logicalName, theModule);
char *logicalName;
void *theModule;
```

Purpose: Prints the list of deftemplates (the C equivalent of the CLIPS

list-deftemplates command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module containing the deftemplates to be listed. A NULL pointer indicates that deftemplate in all

modules should be listed.

Returns: No meaningful return value.

4.3.10 SetDeftemplateWatch

void SetDeftemplateWatch(newState, deftemplatePtr);

```
int newState;
void *deftemplatePtr;
```

Purpose: Sets the facts watch item for a specific deftemplate.

Arguments: The new facts watch state and a generic pointer to a deftemplate

data structure.

4.3.11 Undeftemplate

```
int Undeftemplate(deftemplatePtr);
void *deftemplatePtr;
```

Purpose: Removes a deftemplate from CLIPS (the C equivalent of the CLIPS

undeftemplate command).

Arguments: A generic pointer to a deftemplate data structure. If the NULL

pointer is used, then all deftemplates will be deleted.

Returns: An integer; zero (0) if the deftemplate could not be deleted,

otherwise a one (1).

4.4 FACT FUNCTIONS

The following function calls manipulate and display information about facts.

4.4.1 Assert

```
void *Assert(factPtr);
void *factPtr;
```

Purpose: Adds a fact created using the function **CreateFact** to the fact-list. If

the fact was asserted successfully, **Assert** will return a pointer to the fact. Otherwise, it will return NULL (i.e., the fact was already in the

fact-list).

Arguments: A generic pointer to the fact created using **CreateFact**. The values

of the fact should be initialized before calling **Assert**.

Returns: A generic pointer to a fact structure. If the fact was asserted

successfully, **Assert** will return a generic pointer to the fact. Otherwise, it will return NULL (i.e., the fact was already in the

fact-list).

WARNING:

If the return value from **Assert** is stored as part of a persistent data structure or in a static data area, then the function **IncrementFactCount** should be called to insure that the fact cannot be disposed while external references to the fact still exist.

4.4.2 AssertString

```
void *AssertString(string);
char *string;
```

Purpose: Asserts a fact into the CLIPS fact-list (the C equivalent of the

CLIPS **assert-string** command).

Arguments: One argument; a pointer to a string containing a list of primitive

data types (symbols, strings, integers, floats, and/or instance

names).

Returns: A generic pointer to a fact structure.

Examples

If the following deftemplate has been processed by CLIPS,

```
(deftemplate example
   (multislot v)
   (slot w (default 9))
   (slot x)
   (slot y)
   (multislot z))
```

then the following fact

```
(example (x 3) (y red) (z 1.5 b))
```

can be added to the fact-list using the function shown below.

```
void AddExampleFact1()
  {
   AssertString("(example (x 3) (y red) (z 1.5 b))");
  }
```

To construct a string based on variable data, use the C library function **sprintf** as shown following.

```
void VariableFactAssert(
  int number,
  char *status)
  {
```

```
char tempBuffer[50];
sprintf(tempBuffer, "(example (x %d) (y %s))", number, status);
AssertString(tempBuffer);
}
```

4.4.3 AssignFactSlotDefaults

```
int AssignFactSlotDefaults(theFact);
void *theFact;
```

Purpose: Assigns default values to a fact.

Arguments: A generic pointer to a fact data structure.

Returns: Boolean value. TRUE if the default values were successfully set,

otherwise FALSE.

4.4.4 CreateFact

```
void *CreateFact(deftemplatePtr);
void *deftemplatePtr;
```

Purpose: Function CreateFact returns a pointer to a fact structure with

factSize fields. Once this fact structure is obtained, the fields of the fact can be given values by using **PutFactSlot** and **AssignFactSlotDefaults**. Function **AddFact** should be called when

the fact is ready to be asserted.

Arguments: A generic pointer to a deftemplate data structure (which indicates

the type of fact being created).

Returns: A generic pointer to a fact data structure.

Other: Use the CreateFact function to create a new fact and then the

PutFactSlot function to set one or more slot values. The **AssignFactSlotDefaults** function is then used to assign default values for slots not set with the PutFactSlot function. Finally, the

Assert function is called with the new fact.

Since **CreateFact** requires a generic deftemplate pointer, it is not possible to use it to create ordered facts unless the associated implied deftemplate has already been created. In cases where the implied deftemplate has not been created, the function **AssertString**

can be used to create ordered facts.

This function allows individual fields of a fact to be assigned under programmer control. This is useful, for example, if a fact asserted from an external function needs to contain an external address or an instance address (since the function **AssertString** does not permit these data types). For most situations in which a fact needs to be asserted, however, the **AssertString** function should be preferred (it is slighter slower than using the **CreateFact** and **Assert** functions, but it is much easier to use and less prone to being used incorrectly).

Examples

(deftemplate example

If the following deftemplate has been processed by CLIPS,

```
(multislot v)
   (slot w (default 9))
   (slot x)
   (slot y)
   (multislot z))
then the following fact
(example (x 3) (y red) (z 1.5 b))
can be added to the fact-list using the function shown below.
void AddExampleFact2()
   void *newFact;
   void *templatePtr;
   void *theMultifield;
   DATA_OBJECT theValue;
   /*======*/
   /* Create the fact. */
   /*=======*/
   templatePtr = FindDeftemplate("example");
   newFact = CreateFact(templatePtr);
   if (newFact == NULL) return;
   /*=======*/
   /* Set the value of the x slot. */
   /*=======*/
   theValue.type = INTEGER;
   theValue. value = AddLong(3);
   PutFactSlot(newFact, "x", &theValue);
   /*======*/
   /* Set the value of the y slot. */
```

```
/*=======*/
theValue.type = SYMBOL;
theValue.value = AddSymbol("red");
PutFactSlot(newFact, "y", &theValue);
/*=======*/
/* Set the value of the z slot. */
/*=======*/
theMultifield = CreateMultifield(2);
SetMFType(theMultifield, 1, FLOAT);
SetMFValue(theMultifield, 1, AddDouble(1.5));
SetMFType(theMultifield, 2, SYMBOL);
SetMFValue(theMultifield, 2, AddSymbol("b"));
SetDOBegin(theValue, 1);
SetDOEnd(theValue, 2);
theValue.type = MULTIFIELD;
the Value. value = the Multifield;
PutFactSlot(newFact, "z", &theValue);
/*========*/
/* Assign default values since all */
/* slots were not initialized.
/*=======*/
AssignFactSlotDefaults(newFact);
/*=======*/
/* Assert the fact. */
/*=======*/
Assert(newFact);
```

4.4.5 DecrementFactCount

```
void DecrementFactCount(factPtr);
void *factPtr:
```

Purpose: This function should *only* be called to reverse the effects of a

previous call to **IncrementFactCount**. As long as an fact's count is greater than zero, the memory allocated to it cannot be released for

other use.

Arguments: A generic pointer to a fact.

Returns: No meaningful return value.

4.4.6 FactIndex

```
long int FactIndex(factPtr);
void *factPtr;
```

Purpose: Returns the fact index of a fact (the C equivalent of the CLIPS fact-

index command).

Arguments: A generic pointer to a fact data structure.

Returns: A long integer (the fact-index of the fact).

4.4.7 Facts

```
void Facts(logical Name, the Module, start, end, max);
char *logical Name;
void *theModule;
long start, end, max;
```

Purpose:

Prints the list of all facts currently in the fact-list (the C equivalent of the CLIPS facts command). Output is sent to the logical name wdisplay.

Arguments:

- 1) The logical name to which the listing output is sent.
- 2) A generic pointer to the module containing the facts to be listed (all facts visible to that module). A NULL pointer indicates that all facts in all modules should be listed.
- 3) The start index of the facts to be listed. Facts with indices less than this value are not listed. A value of -1 indicates that the argument is unspecified and should not restrict the facts printed.
- 4) The end index of the facts to be listed. Facts with indices greater than this value are not listed. A value of -1 indicates that the argument is unspecified and should not restrict the facts printed.
- 5) The maximum number of facts to be listed. Facts in excess of this limit are not listed. A value of -1 indicates that the argument is unspecified and should not restrict the facts printed.

Returns: No meaningful return value.

4.4.8 GetFactDuplication

```
int
      GetFactDuplication();
```

Returns the current value of the fact duplication behavior (the C **Purpose:**

equivalent of the CLIPS get-fact-duplication command).

Arguments: None.

Returns: An integer; FALSE (0) if the behavior is disabled and TRUE (1) if

the behavior is enabled.

4.4.9 GetFactListChanged

int GetFactListChanged();

Purpose: Determines if any changes to the fact list have occurred. If this

function returns a non-zero integer, it is the user's responsibility to call SetFactListChanged(0) to reset the internal flag. Otherwise, this function will continue to return non-zero even when no changes have occurred. This function is primarily used to determine when to

update a display tracking the fact list.

Arguments: None.

Returns: 0 if no changes to the fact list have occurred, non-zero otherwise.

4.4.10 GetFactPPForm

```
void GetFactPPForm(buffer, bufferLength, factPtr);
char *buffer;
int bufferLength;
void *factPtr;
```

Purpose: Returns the pretty print representation of a fact in the caller's buffer.

Arguments: 1) A pointer to the caller's character buffer.

- 2) The maximum number of characters which could be stored in the caller's buffer (not including space for the terminating null character).
- 3) A generic pointer to a fact data structure.

Returns: No meaningful return value. The fact pretty print form is stored in

the caller's buffer.

4.4.11 GetFactSlot

```
int GetFactSlot(factPtr, slotName, &theValue);
void *factPtr;
char *slotName;
DATA_OBJECT theValue;
```

Purpose: Retrieves a slot value from a fact.

Arguments: 1) A generic pointer to a fact data structure.

2) The name of the slot to be retrieved (NULL should be used for the implied multifield slot of an implied deftemplate).

3) A pointer to a DATA_OBJECT in which to place the slot's value. See sections 3.2.3 and 3.2.4 for information on getting the value stored in a DATA_OBJECT.

Returns: Boolean value. TRUE if the slot value was successfully retrieved,

otherwise FALSE.

4.4.12 GetNextFact

```
void *GetNextFact(factPtr);
void *factPtr;
```

Purpose: Provides access to the fact-list.

Arguments: A generic pointer to a fact data structure (or NULL to get the first

fact in the fact-list).

Returns: A generic pointer to the first fact in the fact-list if *factPtr* is NULL,

otherwise a generic pointer to the fact immediately following factPtr in the fact-list. If factPtr is the last fact in the fact-list, then

NULL is returned.

Other: Once this generic pointer to the fact structure is obtained, the fields

of the fact can be examined by using the macros **GetMFType** and **GetMFValue**. The values of a fact obtained using this function should never be changed. See **CreateFact** for details on accessing

deftemplate facts.

WARNING: Do not call this function with a pointer to a fact that has been

retracted. If the return value from **GetNextFact** is stored as part of a persistent data structure or in a static data area, then the function **IncrementFactCount** should be called to insure that the fact cannot

be disposed while external references to the fact still exist.

4.4.13 IncrementFactCount

```
void IncrementFactCount(factPtr);
void *factPtr;
```

Purpose:

This function should be called for each external copy of pointer to a fact to let CLIPS know that such an outstanding external reference exists. As long as an fact's count is greater than zero, CLIPS will not release its memory because there may be outstanding pointers to the fact. However, the fact can still be *functionally* retracted, i.e. the fact will *appear* to no longer be in the fact-list. The fact address always can be safely *examined* using the fact access functions as long as the count for the fact is greater than zero. Retracting an already retracted fact will have no effect, however, the function **AddFact** should not be called twice for the same pointer created using **CreateFact**. Note that this function only needs to be called if you are storing pointers to facts that may later be referenced by external code after the fact has been retracted.

Arguments: A generic pointer to a fact.

Returns: No meaningful return value.

4.4.14 LoadFacts

```
int LoadFacts(fileName);
char *fileName;
```

Purpose: Loads a set of facts into the CLIPS data base (the C equivalent of

the CLIPS load-facts command).

Arguments: A string representing the name of the file.

Returns: Returns an integer; if zero, an error occurred while opening the file.

If non-zero no errors were detected while performing the load.

4.4.15 PutFactSlot

```
int PutFactSlot(factPtr, slotName, &theValue);
void *factPtr;
char *slotName;
DATA_OBJECT theValue;
```

Purpose: Sets the slot value of a fact.

Arguments: 1) A generic pointer to a fact data structure.

2) The name of the slot to be set (NULL should be used for the implied multifield slot of an implied deftemplate).

3) A pointer to a DATA_OBJECT that contains the slot's new value. A multifield or implied multifield slot should only be passed a multifield value. A single field slot should only be passed a single field value. See sections 3.3.3 and 3.3.4 for information on setting the value stored in a DATA_OBJECT.

Returns:

Boolean value. TRUE if the slot value was successfully set, otherwise FALSE.

Warning:

Do *not* use this function to change the slot value of a fact that has already been asserted. This function should only be used on facts created using **CreateFact**.

4.4.16 Retract

Purpose:

```
int Retract(factPtr);
void *factPtr;
```

,

Retracts a fact from the CLIPS fact-list (the C equivalent of the

CLIPS **retract** command).

Arguments: A generic pointer to a fact structure (usually captured as the return

value from a call to AssertString or Assert). If the NULL pointer is

used, then all facts will be retracted.

Returns: An integer; zero (0) if fact already has been retracted, otherwise a

one (1).

Other: The caller of **RetractFact** is responsible for insuring that the fact

passed as an argument is still valid. The functions IncrementFactCount and DecrementFactCount can be used to

inform CLIPS whether a fact is still in use.

4.4.17 SaveFacts

int SaveFacts(fileName, saveScope, NULL);
char *fileName;
int saveScope;

Purpose: Saves the facts in the fact-list to the specified file (the C equivalent

of the CLIPS save-facts command).

Arguments: A string representing the name of the file and an integer constant

representing the scope for the facts being saved which should be

either LOCAL_SAVE or VISIBLE_SAVE. The third argument is used internally by the CLIPS save-facts command and should be set

to NULL when called from user code.

Returns: Returns an integer; if zero, an error occurred while opening the file.

If non-zero no errors were detected while performing the save.

4.4.18 SetFactDuplication

int SetFactDuplication(value);
int value;

Purpose: Sets the fact duplication behavior (the C equivalent of the CLIPS

set-fact-duplication command). When this behavior is disabled (by default), asserting a duplicate of a fact already in the fact-list produces no effect. When enabled, the duplicate fact is asserted

with a new fact-index.

Arguments: The new value for the behavior: TRUE (1) to enable the behavior

and FALSE (0) to disable it.

Returns: Returns the old value for the behavior.

4.4.19 SetFactListChanged

void SetFactListChanged(changedFlag);
int changedFlag;

Purpose: Sets the internal boolean flag which indicates when changes to the

fact list have occurred. This function is normally used to reset the

flag to zero after GetFactListChanged() returns non-zero.

Arguments: An integer indicating whether changes in the fact list have occurred

(non-zero) or not (0).

Returns: Nothing useful.

4.4.20 FactExistp

```
long FactExistp(factPtr);
void *factPtr;
```

Purpose: Indicates whether a fact is still in the fact-list or has been retracted

(the C equivalent of the CLIPS **fact-existp** function).

Arguments: 1) A generic pointer to a fact data structure.

Returns: An integer; zero (0) if the fact is not in the fact-list, otherwise a one

(1).

4.4.21 FactSlotNames

void FactSlotNames(factPtr, &theValue);
DATA_OBJECT slotNames;

Purpose: Retrieves the list of slot names associated with a fact (the C

equivalent of the CLIPS fact-slot-names function).

Arguments: 1) A generic pointer to a fact data structure.

2) A pointer to a DATA_OBJECT in which to place a multifield value containing the fact's slot name symbols. For ordered facts, a multifield value containing the single symbol *implied* is returned. See sections 3.2.3 and 3.2.4 for information on getting

the value stored in a DATA_OBJECT.

Returns: No meaningful value.

4.4.22 GetFactList

void GetFactList(&returnValue, theModule);
DATA_OBJECT returnValue;
void *theModule:

Purpose:

Returns the list of facts visible to the specified module as a multifield value in the returnValue DATA_OBJECT (the C equivalent of the CLIPS **get-fact-list** function).

Arguments:

- 1) A pointer to the caller's DATA_OBJECT in which the return value will be stored. The multifield functions described in section 3.2.4 can be used to retrieve the deffacts names from the list.
- 2) A generic pointer to the module from which the list will be extracted. A NULL pointer indicates that the list is to be extracted from all modules.

Returns: No meaningful return value.

CLIPS Advanced Programming Guide

4.4.23 LoadFactsFromString

int LoadFactsFromString(inputString, maxi mumPosition);
char *inputString;
int maxi mumPosition;

Purpose: Loads a set of facts into the CLIPS data base using a string as the

input source (in a manner similar to the CLIPS load-facts

command).

Arguments: 1) A string containing the fact definitions to be loaded.

2) The maximum number of characters to be read from the string.

A value of -1 indicates the entire string.

Returns: Returns an integer; if zero, an error occurred while processing the

string.

4.5 DEFFACTS FUNCTIONS

The following function calls are used for manipulating deffacts.

4.5.1 DeffactsModule

```
char *DeffactsModule(theDeffacts);
void *theDeffacts;
```

Purpose: Returns the module in which a deffacts is defined (the C equivalent

of the CLIPS deffacts-module command).

Arguments: A generic pointer to a deffacts.

Returns: A string containing the name of the module in which the deffacts is

defined.

4.5.2 FindDeffacts

```
void *FindDeffacts(deffactsName);
char *deffactsName;
```

Purpose: Returns a generic pointer to a named deffacts.

Arguments: The name of the deffacts to be found.

Returns: A generic pointer to the named deffacts if it exists, otherwise

NULL.

4.5.3 GetDeffactsList

void GetDeffactsList(&returnValue, theModule);
DATA_OBJECT returnValue;
void *theModule:

Purpose:

Returns the list of deffacts in the specified module as a multifield value in the returnValue DATA_OBJECT (the C equivalent of the CLIPS **get-deffacts-list** function).

Arguments:

- 1) A pointer to the caller's DATA_OBJECT in which the return value will be stored. The multifield functions described in section 3.2.4 can be used to retrieve the deffacts names from the list.
- 2) A generic pointer to the module from which the list will be extracted. A NULL pointer indicates that the list is to be extracted from all modules.

Returns: No meaningful return value.

4.5.4 GetDeffactsName

char *GetDeffactsName(deffactsPtr);
void *deffactsPtr;

Purpose: Returns the name of a deffacts.

Arguments: A generic pointer to a deffacts data structure.

Returns: A string containing the name of the deffacts.

4.5.5 GetDeffactsPPForm

char *GetDeffactsPPForm(deffactsPtr);
void *deffactsPtr;

Purpose: Returns the pretty print representation of a deffacts.

Arguments: A generic pointer to a deffacts data structure.

Returns: A string containing the pretty print representation of the deffacts (or

the NULL pointer if no pretty print representation exists).

4.5.6 GetNextDeffacts

void *GetNextDeffacts(deffactsPtr);
void *deffactsPtr;

Purpose: Provides access to the list of deffacts.

Arguments: A generic pointer to a deffacts data structure (or NULL to get the

first deffacts).

Returns: A generic pointer to the first deffacts in the list of deffacts if

deffactsPtr is NULL, otherwise a generic pointer to the deffacts immediately following deffactsPtr in the list of deffacts. If deffactsPtr is the last deffacts in the list of deffacts, then NULL is

returned.

4.5.7 IsDeffactsDeletable

```
int IsDeffactsDeletable(deffactsPtr);
void *deffactsPtr;
```

Purpose: Indicates whether or not a particular deffacts can be deleted.

Arguments: A generic pointer to a deffacts data structure.

Returns: An integer; zero (0) if the deffacts cannot be deleted, otherwise a

one (1).

4.5.8 ListDeffacts

```
void ListDeffacts(logical Name, theModule);
char *logical Name;
void *theModule;
```

Purpose: Prints the list of deffacts (the C equivalent of the CLIPS

list-deffacts command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module containing the deffacts to be listed. A NULL pointer indicates that deffacts in all modules

should be listed.

Returns: No meaningful return value.

4.5.9 Undeffacts

```
int Undeffacts(deffactsPtr);
void *deffactsPtr;
```

Purpose: Removes a deffacts construct from CLIPS (the C equivalent of the

CLIPS undeffacts command).

Arguments: A generic pointer to a deffacts data structure. If the NULL pointer is

used, then all deffacts will be deleted.

Returns: An integer; zero (0) if the deffacts could not be deleted, otherwise a

one (1).

4.6 DEFRULE FUNCTIONS

The following function calls are used for manipulating defrules.

4.6.1 DefruleHasBreakpoint

```
int DefruleHasBreakpoint(defrulePtr);
void *defrulePtr;
```

Purpose: Indicates whether or not a particular defrule has a breakpoint set.

Arguments: A generic pointer to a defrule data structure.

Returns: An integer; one (1) if a breakpoint exists for the rule, otherwise a

zero (0).

4.6.2 DefruleModule

```
char *Defrul eModul e(theDefrul e);
voi d *theDefrul e;
```

Purpose: Returns the module in which a defrule is defined (the C equivalent

of the CLIPS defrule-module command).

Arguments: A generic pointer to a defrule.

Returns: A string containing the name of the module in which the defrule is

defined.

4.6.3 FindDefrule

```
void *FindDefrule(defruleName);
char *defruleName;
```

Purpose: Returns a generic pointer to a named defrule.

Arguments: The name of the defrule to be found.

Returns: A generic pointer to the named defrule if it exists, otherwise NULL.

4.6.4 GetDefruleList

```
void GetDefruleList(&returnValue, theModule);
DATA_OBJECT returnValue;
void *theModule:
```

Purpose:

Returns the list of defrules in the specified module as a multifield value in the returnValue DATA_OBJECT (the C equivalent of the CLIPS **get-defrule-list** function)..

Arguments:

- 1) A pointer to the caller's DATA_OBJECT in which the return value will be stored. The multifield functions described in section 3.2.4 can be used to retrieve the defrule names from the list.
- 2) A generic pointer to the module from which the list will be extracted. A NULL pointer indicates that the list is to be extracted from all modules.

Returns: No meaningful return value.

4.6.5 GetDefruleName

```
char *GetDefruleName(defrulePtr);
void *defrulePtr;
```

Purpose: Returns the name of a defrule.

Arguments: A generic pointer to a defrule data structure.

Returns: A string containing the name of the defrule.

4.6.6 GetDefrulePPForm

```
char *GetDefrulePPForm(defrulePtr);
```

void *defrulePtr;

Purpose: Returns the pretty print representation of a defrule.

Arguments: A generic pointer to a defrule data structure.

Returns: A string containing the pretty print representation of the defrule (or

the NULL pointer if no pretty print representation exists).

4.6.7 GetDefruleWatchActivations

int GetDefruleWatchActivations(defrulePtr);
void *defrulePtr;

Purpose: Indicates whether or not a particular defrule is being watched for

activations.

Arguments: A generic pointer to a defrule data structure.

Returns: An integer; one (1) if the defrule is being watched for activations,

otherwise a zero (0).

4.6.8 GetDefruleWatchFirings

int GetDefruleWatchFirings(defrulePtr);
void *defrulePtr;

Purpose: Indicates whether or not a particular defrule is being watched for

rule firings.

Arguments: A generic pointer to a defrule data structure.

Returns: An integer; one (1) if the defrule is being watched for rule firings,

otherwise a zero (0).

4.6.9 GetIncrementalReset

int GetIncrementalReset();

Purpose: Returns the current value of the incremental reset behavior (the C

equivalent of the CLIPS get-incremental-reset command).

Arguments: None.

Returns: An integer; FALSE (0) if the behavior is disabled and TRUE (1) if

the behavior is enabled.

4.6.10 GetNextDefrule

void *GetNextDefrule(defrulePtr);
void *defrulePtr;

Purpose: Provides access to the list of defrules.

Arguments: A generic pointer to a defrule data structure (or NULL to get the

first defrule).

Returns: A generic pointer to the first defrule in the list of defrules if

defrulePtr is NULL, otherwise a generic pointer to the defrule immediately following defrulePtr in the list of defrules. If defrulePtr is the last defrule in the list of defrules, then NULL is

returned.

4.6.11 IsDefruleDeletable

```
int IsDefruleDeletable(defrulePtr);
void *defrulePtr;
```

Purpose: Indicates whether or not a particular defrule can be deleted.

Arguments: A generic pointer to a defrule data structure.

Returns: An integer; zero (0) if the defrule cannot be deleted, otherwise a one

(1).

4.6.12 ListDefrules

```
void ListDefrules(logical Name, theModule);
char *logical Name;
void *theModule;
```

Purpose: Prints the list of defrules (the C equivalent of the CLIPS

list-defrules command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module containing the defrules to be listed. A NULL pointer indicates that defrules in all modules

should be listed.

Returns: No meaningful return value.

4.6.13 Matches

```
int Matches(defrulePtr);
void *defrulePtr;
```

Purpose: Prints the partial matches and activations of a defrule (the C

equivalent of the CLIPS matches command).

Arguments: A generic pointer to a defrule data structure.

Returns: An integer; zero (0) if the rule was not found, otherwise a one (1).

4.6.14 Refresh

```
int Refresh(defrulePtr);
void *defrulePtr;
```

Purpose: Refreshes a rule (the C equivalent of the CLIPS **refresh** command).

Arguments: A generic pointer to a defrule data structure.

Returns: An integer; zero (0) if the rule was not found, otherwise a one (1).

4.6.15 RemoveBreak

```
int RemoveBreak(defrulePtr);
void *defrulePtr;
```

Purpose: Removes a breakpoint for the specified defrule (the C equivalent of

the CLIPS remove-break command).

Arguments: A generic pointer to a defrule data structure.

Returns: An integer; zero (0) if a breakpoint did not exist for the rule,

otherwise a one (1).

4.6.16 SetBreak

```
void SetBreak(defrulePtr);
void *defrulePtr;
```

Purpose: Adds a breakpoint for the specified defrule (the C equivalent of the

CLIPS set-break command).

Arguments: A generic pointer to a defrule data structure.

Returns: No meaningful return value.

4.6.17 SetDefruleWatchActivations

```
void SetDefruleWatchActivations(newState, defrulePtr);
int         newState;
void *defrulePtr;
```

Purpose: Sets the activations watch item for a specific defrule.

Arguments: The new activations watch state and a generic pointer to a defrule

data structure.

4.6.18 SetDefruleWatchFirings

```
void SetDefruleWatchFirings(newState, defrulePtr);
int     newState;
void *defrulePtr;
```

Purpose: Sets the rule firing watch item for a specific defrule.

Arguments: The new rule firing watch state and a generic pointer to a defrule

data structure.

4.6.19 SetIncrementalReset

```
int SetIncrementalReset(value);
int value:
```

Purpose: Sets the incremental reset behavior. When this behavior is enabled

(by default), newly defined rules are update based upon the current state of the fact-list. When disabled, newly defined rules are only updated by facts added after the rule is defined (the C equivalent of

the CLIPS **set-incremental-reset** command).

Arguments: The new value for the behavior: TRUE (1) to enable the behavior

and FALSE (0) to disable it.

Returns: Returns the old value for the behavior.

4.6.20 ShowBreaks

```
void ShowBreaks(logicalName, theModule);
char *logicalName;
void *theModule;
```

Purpose: Prints the list of all rule breakpoints (the C equivalent of the CLIPS

show-breaks command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module for which the breakpoints are to be listed. A NULL pointer indicates that the breakpoints in

all modules should be listed.

Returns: No meaningful return value.

4.6.21 Undefrule

```
int Undefrule(defrulePtr);
void *defrulePtr;
```

Purpose: Removes a defrule from CLIPS (the C equivalent of the CLIPS

undefrule command).

Arguments: A generic pointer to a defrule data structure. If the NULL pointer is

used, then all defrules will be deleted.

Returns: An integer; zero (0) if the defrule could not be deleted, otherwise a

one (1).

4.7 AGENDA FUNCTIONS

The following function calls are used for manipulating the agenda.

4.7.1 AddRunFunction

```
int AddRunFunction(runItemName, runFunction, priority);
char *runItemName;
void (*runFunction)();
int priority;

void runFunction();
```

Purpose: Allows a user-defined function to be called after each rule firing.

Such a feature is useful, for example, when bringing data in from some type of external device which does not operate in a

synchronous manner. A user may define an external function which will be called by CLIPS after every rule is fired to check for the existence of new data.

Arguments:

- 1) The name associated with the user-defined run function. This name is used by the function **RemoveRunFunction**.
- 2) A pointer to the user-defined function which is to be called after every rule firing.
- 3) The priority of the run item which determines the order in which run items are called (higher priority items are called first). The values -2000 to 2000 are reserved for CLIPS system defined run items and should not be used for user defined run items.

Returns:

Returns a zero value if the run item could not be added, otherwise a non-zero value is returned.

Example

This following function checks to see if a key on the keyboard has been hit. If a key has been hit, then the fact (stop-processing) is asserted into the fact-list.

```
void CheckKB()
{
  if (CheckKeyboardStatus() == KB_HIT)
      { AssertString("stop-processing"); }
}
```

This function can now be added to the list of functions called after every rule firing by making the following function call.

AddRunFunction("check-kb", checkKB, 3000);

4.7.2 Agenda

```
void Agenda(logicalName, theModule)
char *logicalName;
void *theModule;
```

Purpose:

Prints the list of rules currently on the agenda (the C equivalent of the CLIPS **agenda** command).

Arguments:

- 1) The logical name to which the listing output is sent.
- 2) A generic pointer to the module containing the agenda to be listed. A NULL pointer indicates that the agendas of all modules should be listed.

Returns: No meaningful return value.

4.7.3 ClearFocusStack

void ClearFocusStack();

Purpose: Removes all modules from the focus stack (the C equivalent of the

CLIPS clear-focus-stack command).

Arguments: None.

Returns: No meaningful return value.

4.7.4 DeleteActivation

```
int DeleteActivation(activationPtr);
void *activationPtr;
```

Purpose: Removes an activation from the agenda.

Arguments: A generic pointer to an activation data structure. If the NULL

pointer is used, then all activations will be deleted.

Returns: An integer; zero (0) if the activation could not be deleted, otherwise

a one (1).

4.7.5 Focus

```
void Focus(defmodulePtr);
void *defmodulePtr;
```

Purpose: Sets the current focus (the C equivalent of the CLIPS focus

command).

Arguments: A generic pointer to a defmodule data structure.

Returns: No meaningful value.

4.7.6 GetActivationName

```
char *GetActivationName(activationPtr);
void *activationPtr;
```

Purpose: Returns the name of the defrule from which the activation was

generated.

Arguments: A generic pointer to an activation data structure.

Returns: A string containing a defrule name.

4.7.7 GetActivationPPForm

```
void GetActivationPPForm(buffer, bufferLength, activationPtr);
char *buffer;
int bufferLength;
void *activationPtr;
```

Purpose: Returns the pretty print representation of an agenda activation in the

caller's buffer.

Arguments: 1) A pointer to the caller's character buffer.

2) The maximum number of characters which could be stored in the caller's buffer (not including space for the terminating null

character).

3) A generic pointer to an activation data structure.

4.7.8 GetActivationSalience

```
int GetActivationSalience(activationPtr);
void *activationPtr;
```

Purpose: Returns the salience value associated with an activation. This

salience value may be different from the salience value of the defrule which generated the activation (due to dynamic salience).

Arguments: A generic pointer to an activation data structure.

Returns: The integer salience value of an activation.

4.7.9 GetAgendaChanged

```
int GetAgendaChanged();
```

Purpose: Determines if any changes to the agenda of rule activations have

occurred. If this function returns a non-zero integer, it is the user's responsibility to call SetAgendaChanged(0) to reset the internal flag. Otherwise, this function will continue to return non-zero even

when no changes have occurred. This function is primarily used to determine when to update a display tracking rule activations.

Arguments: None.

Returns: 0 if no changes to the agenda have occurred, non-zero otherwise.

4.7.10 GetFocus

void *GetFocus();

Purpose: Returns the module associated with the current focus (the C

equivalent of the CLIPS get-focus function).

Arguments: None.

Returns: A generic pointer to a defmodule data structure (or NULL if the

focus stack is empty).

4.7.11 GetFocusStack

void GetFocusStack(&returnValue);
DATA_OBJECT returnValue;

Purpose: Returns the module names in the focus stack as a multifield value in

the returnValue DATA_OBJECT (the C equivalent of the CLIPS

get-focus-stack function).

Arguments: A pointer to the caller's DATA_OBJECT in which the return value

will be stored. The multifield functions described in section 3.2.4

can be used to retrieve the defrule names from the list.

4.7.12 GetNextActivation

void *GetNextActivation(activationPtr);
void *activationPtr;

Purpose: Provides access to the list of activations on the agenda.

Arguments: A generic pointer to an activation data structure (or NULL to get

the first activation on the agenda).

Returns: A generic pointer to the first activation on the agenda if

activationPtr is NULL, otherwise a generic pointer to the activation

immediately following *activationPtr* on the agenda. If *activationPtr* is the last activation on the agenda, then NULL is returned.

4.7.13 GetSalienceEvaluation

int GetSalienceEvaluation();

Purpose: Returns the current salience evaluation behavior (the C equivalent

of the CLIPS get-salience-evaluation command).

Arguments: None.

Returns: An integer (see SetSalienceEvaluation for the list of defined

constants).

4.7.14 GetStrategy

int GetStrategy();

Purpose: Returns the current conflict resolution strategy (the C equivalent of

the CLIPS get-strategy command).

Arguments: None.

Returns: An integer (see SetStrategy for the list of defined strategy

constants).

4.7.15 ListFocusStack

```
void ListFocusStack(logicalName);
char *logicalName;
```

Purpose: Prints the current focus stack (the C equivalent of the CLIPS **list-**

focus-stack command).

Arguments: The logical name to which the listing output is sent.

Returns: No meaningful return value.

4.7.16 PopFocus

```
voi d *PopFocus();
```

Purpose: Removes the current focus from the focus stack and returns the

module associated with that focus (the C equivalent of the CLIPS

pop-focus function).

Arguments: None.

Returns: A generic pointer to a defmodule data structure.

4.7.17 RefreshAgenda

```
void RefreshAgenda(theModule);
void *theModule;
```

Purpose: Recomputes the salience values for all activations on the agenda

and then reorders the agenda (the C equivalent of the CLIPS

refresh-agenda command).

Arguments: A generic pointer to the module containing the agenda to be

refreshed. A NULL pointer indicates that the agendas of all

modules should be refreshed.

Returns: No meaningful return value.run

4.7.18 RemoveRunFunction

```
int RemoveRunFunction(runItemName);
char *runItemName;
```

Purpose: Removes a named function from the list of functions to be called

after every rule firing.

Arguments: The name associated with the user-defined run function. This is the

same name that was used when the run function was added with the

function AddRunFunction.

Returns: Returns the integer value 1 if the named function was found and

removed, otherwise 0 is returned.

4.7.19 ReorderAgenda

```
void ReorderAgenda(theModule);
void *theModule;
```

Purpose: Reorders the agenda based on the current conflict resolution

strategy and current activation saliences.

Arguments: A generic pointer to the module containing the agenda to be

reordered. A NULL pointer indicates that the agendas of all

modules should be reordered.

Returns: No meaningful return value.

4.7.20 Run

```
long int Run(runLimit);
long int runLimit;
```

Purpose: Allows rules to execute (the C equivalent of the CLIPS run

command).

Arguments: An integer which defines how many rules should fire before

returning. If runLimit is a negative integer, rules will fire until the

agenda is empty.

Returns: Returns an integer value; the number of rules that were fired.

4.7.21 SetActivationSalience

```
int SetActivationSalience(activationPtr, newSalience);
void *activationPtr;
int newSalience;
```

Purpose: Sets the salience value of an activation. The salience value of the

defrule which generated the activation is unchanged.

Arguments: 1) A generic pointer to an activation data structure.

2) The new salience value (which is not restricted to the -10000 to

+10000 range).

Returns: The old salience value of the activation.

Other: The function **ReorderAgenda** should be called after salience values

have been changed to update the agenda.

4.7.22 SetAgendaChanged

void SetAgendaChanged(changedFlag);
int changedFlag;

Purpose: Sets the internal boolean flag which indicates when changes to the

agenda of rule activations have occurred. This function is normally used to reset the flag to zero after GetAgendaChanged() returns

non-zero.

Arguments: An integer indicating whether changes in the agenda have occurred

(non-zero) or not (0).

Returns: Nothing useful.

4.7.23 SetSalienceEvaluation

int SetSalienceEvaluation(value);

int value;

Purpose: Sets the salience evaluation behavior (the C equivalent of the

CLIPS set-salience-evaluation command).

Arguments: The new value for the behavior – one of the following defined

integer constants:

WHEN_DEFINED
WHEN_ACTIVATED
EVERY_CYCLE

Returns: Returns the old value for the behavior.

4.7.24 SetStrategy

int SetStrategy(value);
int value;

Purpose: Sets the conflict resolution strategy (the C equivalent of the CLIPS

set-strategy command).

Arguments: The new value for the behavior – one of the following defined

integer constants:

DEPTH_STRATEGY BREADTH_STRATEGY LEX_STRATEGY MEA STRATEGY

COMPLEXITY_STRATEGY SIMPLICITY_STRATEGY RANDOM_STRATEGY

Returns: Returns the old value for the strategy.

4.8 DEFGLOBAL FUNCTIONS

The following function calls are used for manipulating defglobals.

4.8.1 DefglobalModule

```
char *Defgl obal Modul e(theDefgl obal);
voi d *theDefgl obal;
```

Purpose: Returns the module in which a defglobal is defined (the C

equivalent of the CLIPS defglobal-module command).

Arguments: A generic pointer to a defglobal.

Returns: A string containing the name of the module in which the defglobal

is defined.

4.8.2 FindDefglobal

```
void *FindDefglobal(globalName);
char *globalName;
```

Purpose: Returns a generic pointer to a named defglobal.

Arguments: The name of the defglobal to be found (e.g. x for ?*x*).

Returns: A generic pointer to the named defglobal if it exists, otherwise

NULL.

4.8.3 GetDefglobalList

```
void GetDefglobalList(&returnValue, theModule);
DATA_OBJECT returnValue;
void *theModule;
```

Purpose:

Returns the list of defglobals in the specified module as a multifield value in the returnValue DATA_OBJECT (the C equivalent of the CLIPS **get-defglobal-list** function).

Arguments:

- 1) A pointer to the caller's DATA_OBJECT in which the return value will be stored. The multifield functions described in section 3.2.4 can be used to retrieve the defglobal names from the list.
- 2) A generic pointer to the module from which the list will be extracted. A NULL pointer indicates that the list is to be extracted from all modules.

Returns: No meaningful return value.

4.8.4 GetDefglobalName

```
char *GetDefglobalName(defglobalPtr);
void *defglobalPtr;
```

Purpose: Returns the name of a defglobal.

Arguments: A generic pointer to a defglobal data structure.

Returns: A string containing the name of the defglobal (e.g. x for ?*x*).

4.8.5 GetDefglobalPPForm

```
char *GetDefglobal PPForm(defglobal Ptr);
void *defglobal Ptr;
```

Purpose: Returns the pretty print representation of a defglobal.

Arguments: A generic pointer to a defglobal data structure.

Returns: A string containing the pretty print representation of the defglobal

(or the NULL pointer if no pretty print representation exists).

4.8.6 GetDefglobalValue

```
int GetDefglobalValue(globalName, &vPtr);
char *globalName;
DATA_OBJECT vPtr;
```

Purpose: Returns the value of a defglobal.

Arguments: 1) The name of the global variable to be retrieved (e.g. y for ?*y*).

2) A pointer to a DATA_OBJECT in which the value is stored (see sections 3.2.3 and 3.3.4 for details on this data structure).

Returns: An integer; zero (0) if the defglobal was not found, otherwise a one

(1). The DATA_OBJECT vPtr is assigned the current value of the

defglobal.

4.8.7 GetDefglobalValueForm

```
void GetDefgl obal Val ueForm(buffer, bufferLength, defgl obal Ptr);
char *buffer;
int bufferLength;
void *defgl obal Ptr;
```

Purpose:

Returns a printed representation of a defglobal and its current value in the caller's buffer. For example,

?*x* = 5

Arguments:

- 1) A pointer to the caller's character buffer.
- 2) The maximum number of characters which could be stored in the caller's buffer (not including space for the terminating null character).
- 3) A generic pointer to a defglobal data structure.

4.8.8 GetDefglobalWatch

```
int GetDefglobalWatch(defglobalPtr);
void *defglobalPtr;
```

Purpose: Indicates whether or not a particular defglobal is being watched.

Arguments: A generic pointer to a defglobal data structure.

Returns: An integer; one (1) if the defglobal is being watched, otherwise a

zero (0).

4.8.9 GetGlobalsChanged

int GetGlobalsChanged();

Purpose: Determines if any changes to global variables have occurred. If this

function returns a non-zero integer, it is the user's responsibility to call SetGlobalsChanged(0) to reset the internal flag. Otherwise, this function will continue to return non-zero even when no changes have occurred. This function is primarily used to determine when to

update a display tracking global variables.

Arguments: None.

Returns: 0 if no changes to global variables have occurred, non-zero

otherwise.

4.8.10 GetNextDefglobal

void *GetNextDefglobal(defglobalPtr);
void *defglobalPtr;

Purpose: Provides access to the list of defglobals.

Arguments: A generic pointer to a defglobal data structure (or NULL to get the

first defglobal).

Returns: A generic pointer to the first defglobal in the list of defglobals if

defglobalPtr is NULL, otherwise a generic pointer to the defglobal immediately following defglobalPtr in the list of defglobals. If defglobalPtr is the last defglobal in the list of defglobals, then

NULL is returned.

4.8.11 GetResetGlobals

int GetResetGlobals();

Purpose: Returns the current value of the reset global variables behavior (the

C equivalent of the CLIPS **get-reset-globals** command).

Arguments: None.

Returns: An integer; FALSE (0) if globals are not reset and TRUE (1) if

globals are reset.

4.8.12 IsDefglobalDeletable

int IsDefglobalDeletable(defglobalPtr);
void *defglobalPtr;

Purpose: Indicates whether or not a particular defglobal can be deleted.

Arguments: A generic pointer to a defglobal data structure.

Returns: An integer; zero (0) if the defglobal cannot be deleted, otherwise a

one (1).

4.8.13 ListDefglobals

```
void ListDefglobals(logicalName, theModule);
char *logicalName;
void *theModule;
```

Purpose: Prints the list of defglobals (the C equivalent of the CLIPS

list-defglobals command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module containing the defglobals to be listed. A NULL pointer indicates that defglobals in all modules

should be listed.

Returns: No meaningful return value.

4.8.14 SetDefglobalValue

```
int SetDefglobalValue(globalName, &vPtr);
char *globalName;
DATA_OBJECT vPtr;
```

Purpose: Sets the value of a defglobal.

Arguments: 1) The name of the global variable to be set (e.g. y for ?*y*).

2) A pointer to a DATA_OBJECT in which the new value is contained (see sections 3.2.3 and 3.3.4 for details on this data

structure).

Returns: An integer; zero (0) if the defglobal was not found, otherwise a one

(1).

4.8.15 SetDefglobalWatch

```
void SetDefglobalWatch(newState, defglobalPtr);
int         newState;
void *defglobalPtr;
```

Purpose: Sets the globals watch item for a specific defglobal.

Arguments: The new globals watch state and a generic pointer to a defglobal

data structure.

4.8.16 SetGlobalsChanged

```
void SetGlobalsChanged(changedFlag);
int changedFlag;
```

Purpose: Sets the internal boolean flag which indicates when changes to

global variables have occurred. This function is normally used to reset the flag to zero after GetGlobalsChanged() returns non-zero.

Arguments: An integer indicating whether changes in global variables have

occurred (non-zero) or not (0).

Returns: Nothing useful.

4.8.17 SetResetGlobals

```
int SetResetGlobals(value);
int value;
```

Purpose: Sets the reset-globals behavior (the C equivalent of the CLIPS

set-reset-globals command). When this behavior is enabled (by default) global variables are reset to their original values when the

reset command is performed.

Arguments: The new value for the behavior: TRUE (1) to enable the behavior

and FALSE (0) to disable it.

Returns: Returns the old value for the behavior.

4.8.18 ShowDefglobals

```
void ShowDefglobals(logicalName, theModule);
char *logicalName;
void *theModule;
```

Purpose: Prints the list of defglobals and their current values (the C

equivalent of the CLIPS show-defglobals command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module containing the defglobals to be displayed. A NULL pointer indicates that defglobals in all

modules should be displayed.

Returns: No meaningful return value.

4.8.19 Undefglobal

```
int Undefgl obal (defgl obal Ptr);
void *defgl obal Ptr;
```

Purpose: Removes a defglobal from CLIPS (the C equivalent of the CLIPS

undefglobal command).

Arguments: A generic pointer to a defglobal data structure. If the NULL pointer

is used, then all defglobals will be deleted.

Returns: An integer; zero (0) if the defglobal could not be deleted, otherwise

a one (1).

4.9 DEFFUNCTION FUNCTIONS

The following function calls are used for manipulating deffunctions.

4.9.1 DeffunctionModule

```
char *DeffunctionModule(theDeffunction);
void *theDeffunction:
```

Purpose: Returns the module in which a deffunction is defined (the C

equivalent of the CLIPS **deffunction-module** command).

Arguments: A generic pointer to a deffunction.

Returns: A string containing the name of the module in which the

deffunction is defined.

4.9.2 FindDeffunction

void *FindDeffunction(deffunctionName);
char *deffunctionName;

Purpose: Returns a generic pointer to a named deffunction.

Arguments: The name of the deffunction to be found.

Returns: A generic pointer to the named deffunction if it exists, otherwise

NULL.

4.9.3 GetDeffunctionList

void GetDeffunctionList(&returnValue, theModule);
DATA_OBJECT returnValue;
void *theModule;

Purpose:

Returns the list of deffunctions in the specified module as a multifield value in the returnValue DATA_OBJECT (the C equivalent of the CLIPS **get-deffunction-list** function).

Arguments:

- 1) A pointer to the caller's DATA_OBJECT in which the return value will be stored. The multifield functions described in section 3.2.4 can be used to retrieve the deffunction names from the list.
- 2) A generic pointer to the module from which the list will be extracted. A NULL pointer indicates that the list is to be extracted from all modules.

Returns: No meaningful return value.

4.9.4 GetDeffunctionName

char *GetDeffunctionName(deffunctionPtr);
void *deffunctionPtr;

Purpose: Returns the name of a deffunction.

Arguments: A generic pointer to a deffunction data structure.

Returns: A string containing the name of the deffunction.

4.9.5 GetDeffunctionPPForm

```
char *GetDeffunctionPPForm(deffunctionPtr);
void *deffunctionPtr;
```

Purpose: Returns the pretty print representation of a deffunction.

Arguments: A generic pointer to a deffunction data structure.

Returns: A string containing the pretty print representation of the deffunction

(or the NULL pointer if no pretty print representation exists).

4.9.6 GetDeffunctionWatch

```
int GetDeffunctionWatch(deffunctionPtr);
void *deffunctionPtr;
```

Purpose: Indicates whether or not a particular deffunction is being watched.

Arguments: A generic pointer to a deffunction data structure.

Returns: An integer; one (1) if the deffunction is being watched, otherwise a

zero (0).

4.9.7 GetNextDeffunction

```
void *GetNextDeffunction(deffunctionPtr);
void *deffunctionPtr;
```

Purpose: Provides access to the list of deffunctions.

Arguments: A generic pointer to a deffunction data structure (or NULL to get

the first deffunction).

Returns: A generic pointer to the first deffunction in the list of deffunctions

if deffunctionPtr is NULL, otherwise a generic pointer to the deffunction immediately following deffunctionPtr in the list of deffunctions. If deffunctionPtr is the last deffunction in the list of

deffunctions, then NULL is returned.

4.9.8 IsDeffunctionDeletable

```
int IsDeffunctionDeletable(deffunctionPtr);
void *deffunctionPtr;
```

Purpose: Indicates whether or not a particular deffunction can be deleted.

Arguments: A generic pointer to a deffunction data structure.

Returns: An integer; zero (0) if the deffunction cannot be deleted, otherwise

a one (1).

4.9.9 ListDeffunctions

```
void ListDeffunctions(logicalName, theModule);
char *logicalName;
void *theModule;
```

Purpose: Prints the list of deffunction (the C equivalent of the CLIPS

list-deffunctions command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module containing the deffunctions to be listed. A NULL pointer indicates that deffunctions in all

modules should be listed.

Returns: No meaningful return value.

4.9.10 SetDeffunctionWatch

```
void SetDeffunctionWatch(newState, deffunctionPtr);
int        newState;
void *deffunctionPtr;
```

Purpose: Sets the deffunctions watch item for a specific deffunction.

Arguments: The new deffunctions watch state and a generic pointer to a

deffunction data structure.

4.9.11 Undeffunction

```
int Undeffunction(deffunctionPtr);
void *deffunctionPtr;
```

Purpose: Removes a deffunction from CLIPS (the C equivalent of the CLIPS

undeffunction command).

Arguments: A generic pointer to the deffunction (NULL means to delete all

deffunctions).

Returns: An integer; zero (0) if the deffunction could not be deleted,

otherwise a one (1).

4.10 DEFGENERIC FUNCTIONS

The following function calls are used for manipulating generic functions.

4.10.1 DefgenericModule

```
char *DefgenericModule(theDefgeneric);
void *theDefgeneric;
```

Purpose: Returns the module in which a defgeneric is defined (the C

equivalent of the CLIPS defgeneric-module command).

Arguments: A generic pointer to a defgeneric.

Returns: A string containing the name of the module in which the defgeneric

is defined.

4.10.2 FindDefgeneric

```
void *FindDefgeneric(defgenericName);
char *defgenericName;
```

Purpose: Returns a generic pointer to a named generic function.

Arguments: The name of the generic to be found.

Returns: A generic pointer to the named generic function if it exists,

otherwise NULL.

4.10.3 GetDefgenericList

```
void GetDefgenericList(&returnValue, theModule);
DATA_OBJECT returnValue;
void *theModule;
```

Purpose: Returns the list of defgenerics in the specified module as a

multifield value in the returnValue DATA_OBJECT (the C

equivalent of the CLIPS get-defgeneric-list function).

Arguments: 1) A pointer to the caller's DATA_OBJECT in which the return

value will be stored. The multifield functions described in

section 3.2.4 can be used to retrieve the defgeneric names from the list.

2) A generic pointer to the module from which the list will be extracted. A NULL pointer indicates that the list is to be extracted from all modules.

Returns: No meaningful return value.

4.10.4 GetDefgenericName

```
char *GetDefgenericName(defgenericPtr);
void *defgenericPtr;
```

Purpose: Returns the name of a generic function.

Arguments: A generic pointer to a defgeneric data structure.

Returns: A string containing the name of the generic function.

4.10.5 GetDefgenericPPForm

```
char *GetDefgenericPPForm(defgenericPtr);
void *defgenericPtr;
```

Purpose: Returns the pretty print representation of a generic function.

Arguments: A generic pointer to a defgeneric data structure.

Returns: A string containing the pretty print representation of the generic

function (or the NULL pointer if no pretty print representation

exists).

4.10.6 GetDefgenericWatch

```
int GetDefgenericWatch(defgenericPtr);
void *defgenericPtr;
```

Purpose: Indicates whether or not a particular defgeneric is being watched.

Arguments: A generic pointer to a defgeneric data structure.

Returns: An integer; one (1) if the defgeneric is being watched, otherwise a

zero (0).

4.10.7 GetNextDefgeneric

void *GetNextDefgeneric(defgenericPtr);
void *defgenericPtr;

Purpose: Provides access to the list of generic functions.

Arguments: A generic pointer to a defgeneric data structure (or NULL to get the

first generic function).

Returns: A generic pointer to the first generic function in the list of generic

functions if *defgenericPtr* is NULL, otherwise a generic pointer to the generic function immediately following *defgenericPtr* in the list of generic functions. If *defgenericPtr* is the last generic function in

the list of generic functions, then NULL is returned.

4.10.8 IsDefgenericDeletable

```
int IsDefgenericDeletable(defgenericPtr);
void *defgenericPtr;
```

Purpose: Indicates whether or not a particular generic function and all its

methods can be deleted.

Arguments: A generic pointer to a defgeneric data structure.

Returns: An integer: zero (0) if the generic function and all its methods

cannot be deleted, otherwise a one (1).

4.10.9 ListDefgenerics

```
void ListDefgenerics(logical Name, theModule);
char *logical Name;
void *theModule:
```

Purpose: Prints the list of defgenerics (the C equivalent of the CLIPS

list-defgenerics command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module containing the defgenerics to be listed. A NULL pointer indicates that defgenerics in all modules

should be listed.

Returns: No meaningful return value.

4.10.10 SetDefgenericWatch

```
void SetDefgenericWatch(newState, defgenericPtr);
      newState;
void *defgenericPtr;
```

Purpose: Sets the defgenerics watch item for a specific defgeneric.

Arguments: The new generic-functions watch state and a generic pointer to a

defgeneric data structure.

4.10.11 Undefgeneric

```
i nt
      Undefgeneric(defgenericPtr);
void *defgenericPtr;
```

Purpose: Removes a generic function and all its methods from CLIPS (the C

equivalent of the CLIPS undefgeneric command).

Arguments: A generic pointer to the generic function (NULL means to delete all

generic functions).

Returns: An integer: zero (0) if the generic function and all its methods could

not be deleted, otherwise a one (1).

4.11 DEFMETHOD FUNCTIONS

The following function calls are used for manipulating generic function methods.

4.11.1 GetDefmethodDescription

```
void GetDefmethodDescription(buffer, bufferLength,
                                   defgenericPtr, methodIndex);
char *buf;
int bufLength;
void *defgenericPtr;
unsigned methodIndex;
```

Purpose: Stores a synopsis of the method parameter restrictions in the caller's

buffer.

Arguments: 1) A pointer to the caller's buffer.

> 2) The maximum number of characters which could be stored in the caller's buffer (not including space for the terminating null character).

3) A generic pointer to a defgeneric data structure.

4) The index of the generic function method.

Returns: No meaningful return value.

4.11.2 GetDefmethodList

void GetDefmethodList(defgenericPtr, &returnValue);
void *defgenericPtr;
DATA_OBJECT returnValue;

Purpose:

Returns the list of currently defined defmethods for the specified defgeneric. This function is the C equivalent of the CLIPS **get-defmethod-list** command).

Arguments:

- 1) A generic pointer to the defgeneric (NULL for all defgenerics).
- 2) A pointer to the DATA_OBJECT in which the list of defmethod constructs is to be stored.

Returns:

A multifield value containing the list of defmethods constructs for the specified defgeneric. The multifield functions described in section 3.2.4 can be used to retrieve the defmethod names and indices from the list. Note that the name and index for each defmethod are stored as pairs in the return multifield value.

4.11.3 GetDefmethodPPForm

char *GetDefmethodPPForm(defgenericPtr, methodIndex);
void *defgenericPtr;
unsigned methodIndex;

Purpose: Returns the pretty print representation of a generic function method.

Arguments: 1) A generic pointer to a defgeneric data structure.

2) The index of the generic function method.

Returns: A string containing the pretty print representation of the generic

function method (or the NULL pointer if no pretty print

representation exists).

4.11.4 GetDefmethodWatch

int GetDefmethodWatch(defgenericPtr, methodIndex);
void *defgenericPtr;
unsigned methodIndex

Purpose: Indicates whether or not a particular definethod is being watched.

Arguments: A generic pointer to a defgeneric data structure and the index of the

generic function method.

Returns: An integer; one (1) if the definethod is being watched, otherwise a

zero (0).

4.11.5 GetMethodRestrictions

Purpose: Returns the restrictions for the specified method. This function is

the C equivalent of the CLIPS get-method-restrictions function.

Arguments: 1) A generic pointer to the defgeneric (NULL for all defgenerics).

2) The index of the generic function method.

3) A pointer to the DATA_OBJECT in which the method

restrictions are stored.

Returns: A multifield value containing the restrictions for the specified

method (the description of the **get-method-restrictions** function in the Basic Programming Guide explains the meaning of the fields in the multifield value). The multifield functions described in section 3.2.4 can be used to retrieve the method restrictions from the list.

4.11.6 GetNextDefmethod

unsigned GetNextDefmethod(defgenericPtr, methodIndex);
void *defgenericPtr;
unsigned methodIndex;

Purpose: Provides access to the list of methods for a particular generic

function.

Arguments: 1) A generic pointer to a defgeneric data structure.

2) The index of a generic function method (0 to get the first method of the generic function).

Returns:

The index of the first method in the list of methods for the generic function if *methodIndex* is 0, otherwise the index of the method immediately following *methodIndex* in the list of methods for the generic function. If *methodIndex* is the last method in the list of methods for the generic function, then 0 is returned.

4.11.7 IsDefmethodDeletable

```
int IsDefmethodDeletable(defgenericPtr, methodIndex);
void *defgenericPtr;
unsigned methodIndex;
```

Purpose: Indicates whether or not a particular generic function method can be

deleted.

Arguments: 1) A generic pointer to a defgeneric data structure.

2) The index of the generic function method.

Returns: An integer: zero (0) if the method cannot be deleted, otherwise a

one (1).

4.11.8 ListDefmethods

```
void ListDefmethods(logicalName, defgenericPtr);
char *logicalName;
void *defgenericPtr;
```

Purpose: Prints the list of methods for a particular generic function (the C

equivalent of the CLIPS list-defmethods command).

Arguments: 1) The logical name of the output destination to which tosend the

method listing

2) A generic pointer to the generic function (NULL to list methods

for all generic functions).

Returns: No meaningful return value.

4.11.9 SetDefmethodWatch

```
void SetDefmethodWatch(newState, defgenericPtr, methodIndex);
int          newState;
void *defgenericPtr;
```

unsigned methodIndex

Purpose: Sets the methods watch item for a specific defmethod.

Arguments: The new methods watch state, a generic pointer to a defgeneric data

structure, and the index of the generic function method.

4.11.10 Undefmethod

```
int Undefmethod(defgenericPtr, methodIndex);
void *defgenericPtr;
unsigned methodIndex;
```

Purpose: Removes a generic function method from CLIPS (the C equivalent

of the CLIPS undefmethod command).

Arguments:1) A generic pointer to a defgeneric data structure (NULL to delete

all methods for all generic functions).

2) The index of the generic function method (0 to delete all methods of the generic function - must be 0 if *defgenericPtr* is

NULL).

Returns: An integer: zero (0) if the method could not be deleted, otherwise a

one (1).

4.12 DEFCLASS FUNCTIONS

The following function calls are used for manipulating defclasses.

4.12.1 BrowseClasses

```
void BrowseClasses(logicalName, defclassPtr);
char *logicalName;
void *defclassPtr;
```

Purpose: Prints a "graph" of all classes which inherit from the specified class.

This function is the C equivalent of the CLIPS browse-classes

command.

Arguments: 1) The logical name of the output destination to which to send the

browse display.

2) A generic pointer to the class which is to be browsed.

Returns: No meaningful return value.

4.12.2 ClassAbstractP

int ClassAbstractP(defclassPtr);
void *defclassPtr;

Purpose: Determines if a class is concrete or abstract, i.e. if a class can have

direct instances or not. This function is the C equivalent of the

CLIPS class-abstractp command.

Arguments: A generic pointer to the class.

Returns: The integer 1 if the class is abstract, or 0 if the class is concrete.

4.12.3 ClassReactiveP

```
int ClassReactiveP(defclassPtr);
void *defclassPtr;
```

Purpose: Determines if a class is reactive or non-reactive, i.e. if objects of the

class can match object patterns. This function is the C equivalent of

the CLIPS class-reactivep command.

Arguments: A generic pointer to the class.

Returns: The integer 1 if the class is reactive, or 0 if the class is non-reactive.

4.12.4 ClassSlots

```
void ClassSlots(defclassPtr, &result, inheritFlag);
void *defclassPtr;
DATA_OBJECT result;
int inheritFlag;
```

Purpose: Groups the names of slots of a class into a multifield data object.

This function is the C equivalent of the CLIPS class-slots

command.

Arguments: 1) A generic pointer to the class.

2) Pointer to the data object in which to store the multifield. See sections 3.3.3 and 3.3.4 for information on getting the value stored

Sections 5.5.5 and 5.5.4 for information on getting the value st

in a DATA_OBJECT.

3) The integer 1 to include inherited slots or 0 to only include

explicitly defined slots.

Returns: No meaningful return value.

4.12.5 ClassSubclasses

void ClassSubclasses(defclassPtr, &result, inheritFlag);
void *defclassPtr;
DATA_OBJECT result;
int inheritFlag;

Purpose:

Groups the names of subclasses of a class into a multifield data object. This function is the C equivalent of the CLIPS **class-subclasses** command.

Arguments:

- 1) A generic pointer to the class.
- 2) Pointer to the data object in which to store the multifield. See sections 3.3.3 and 3.3.4 for information on setting the value stored in a DATA_OBJECT.
- 3) The integer 1 to include inherited subclasses or 0 to only include direct subclasses

direct subclasses.

Returns:

No meaningful return value.

4.12.6 ClassSuperclasses

```
void ClassSuperclasses(defclassPtr, &result, inheritFlag);
void *defclassPtr;
DATA_OBJECT result;
int inheritFlag;
```

Purpose:

Groups the names of superclasses of a class into a multifield data object. This function is the C equivalent of the CLIPS class-superclasses command.

Arguments:

- 1) A generic pointer to the class.
- 2) Pointer to the data object in which to store the multifield.
- 3) The integer 1 to include inherited superclasses or 0 to only

include direct superclasses.

Returns:

No meaningful return value.

4.12.7 DefclassModule

```
char *DefclassModule(theDefclass);
void *theDefclass;
```

Purpose:

Returns the module in which a defclass is defined (the C equivalent

of the CLIPS defclass-module command).

Arguments: A generic pointer to a defclass.

Returns: A string containing the name of the module in which the defclass is

defined.

4.12.8 DescribeClass

```
void DescribeClass(logicalName, defclassPtr);
char *logicalName;
void *defclassPtr;
```

Purpose: Prints a summary of the specified class including: abstract/concrete

behavior, slots and facets (direct and inherited) and recognized message-handlers (direct and inherited). This function is the C

equivalent of the CLIPS describe-class command.

Arguments: 1) The logical name of the output destination to which to send the

description.

2) A generic pointer to the class which is to be described.

Returns: No meaningful return value.

4.12.9 FindDefclass

```
void *FindDefclass(defclassName);
char *defclassName;
```

Purpose: Returns a generic pointer to a named class.

Arguments: The name of the class to be found.

Returns: A generic pointer to the named class if it exists, otherwise NULL.

4.12.10 GetDefclassList

```
void GetDefclassList(&returnValue, theModule);
DATA_OBJECT returnValue;
void *theModule:
```

Purpose: Returns the list of defclasses in the specified module as a multifield

value in the returnValue DATA_OBJECT (the C equivalent of the

CLIPS **get-defclass-list** function).

Arguments:

- 1) A pointer to the caller's DATA_OBJECT in which the return value will be stored. The multifield functions described in section 3.2.4 can be used to retrieve the defclass names from the list.
- 2) A generic pointer to the module from which the list will be extracted. A NULL pointer indicates that the list is to be extracted from all modules.

Returns: No meaningful return value.

4.12.11 GetDefclassName

```
char *GetDefclassName(defclassPtr);
void *defclassPtr;
```

Purpose: Returns the name of a class.

Arguments: A generic pointer to a defclass data structure.

Returns: A string containing the name of the class.

4.12.12 GetDefclassPPForm

```
char *GetDefclassPPForm(defclassPtr);
void *defclassPtr;
```

Purpose: Returns the pretty print representation of a class.

Arguments: A generic pointer to a defclass data structure.

Returns: A string containing the pretty print representation of the class (or

the NULL pointer if no pretty print representation exists).

4.12.13 GetDefclassWatchInstances

```
int GetDefclassWatchInstances(defclassPtr);
void *defclassPtr;
```

Purpose: Indicates whether or not a particular defclass is being watched for

instance creation and deletions.

Arguments: A generic pointer to a defclass data structure.

Returns: An integer; one (1) if the defclass is being watched, otherwise a

zero (0).

4.12.14 GetDefclassWatchSlots

int GetDefclassWatchSlots(defclassPtr);
void *defclassPtr;

Purpose: Indicates whether or not a particular defclass is being watched for

slot changes.

Arguments: A generic pointer to a defclass data structure.

Returns: An integer; one (1) if the defclass is being watched for slot changes,

otherwise a zero (0).

4.12.15 GetNextDefclass

```
void *GetNextDefclass(defclassPtr);
void *defclassPtr;
```

Purpose: Provides access to the list of classes.

Arguments: A generic pointer to a defclass data structure (or NULL to get the

first class).

Returns: A generic pointer to the first class in the list of classes if *defclassPtr*

is NULL, otherwise a generic pointer to the class immediately following *defclassPtr* in the list of classes. If *defclassPtr* is the last

class in the list of classes, then NULL is returned.

4.12.16 IsDefclassDeletable

int IsDefclassDeletable(defclassPtr);
void *defclassPtr;

Purpose: Indicates whether or not a particular class and all its subclasses can

be deleted.

Arguments: A generic pointer to a defclass data structure.

Returns: An integer; zero (0) if the class cannot be deleted, otherwise a one

(1).

4.12.17 ListDefclasses

```
void ListDefclasses(logicalName, theModule);
char *logicalName;
void *theModule;
```

Purpose: Prints the list of defclasses (the C equivalent of the CLIPS

list-defclasses command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module containing the defclasses to be listed. A NULL pointer indicates that defclasses in all modules

should be listed.

Returns: No meaningful return value.

4.12.18 SetDefclassWatchInstances

```
void SetDefclassWatchInstances(newState, defclassPtr);
int        newState;
void *defclassPtr:
```

Purpose: Sets the instances watch item for a specific defclass.

Arguments: The new instances watch state and a generic pointer to a defclass

data structure.

4.12.19 SetDefclassWatchSlots

```
void SetDefclassWatchSlots(newState, defclassPtr);
int     newState;
void *defclassPtr;
```

Purpose: Sets the slots watch item for a specific defclass.

Arguments: The new slots watch state and a generic pointer to a defclass data

structure.

4.12.20 SlotAllowedValues

```
void SlotAllowedValues(defclassPtr, slotName, &result);
void *defclassPtr;
char *slotName;
DATA_OBJECT result;
```

Purpose: Groups the allowed-values for a slot into a multifield data object.

This function is the C equivalent of the CLIPS slot-allowed-values

function.

Arguments: 1) A generic pointer to the class.

2) Name of the slot.

3) Pointer to the data object in which to store the multifield. The multifield functions described in section 3.2.4 can be used to

retrieve the allowed values from the list.

Returns: No meaningful return value.

4.12.21 SlotCardinality

```
void SlotCardinality(defclassPtr, slotName, result);
void *defclassPtr;
char *slotName;
DATA_OBJECT *result;
```

Purpose: Groups the cardinality information for a slot into a multifield data

object. This function is the C equivalent of the CLIPS slot-

cardinality function.

Arguments: 1) A generic pointer to the class.

2) Name of the slot.

3) Pointer to the data object in which to store the multifield.

Returns: No meaningful return value.

4.12.22 SlotDirectAccessP

```
int SlotDirectAccessP(defclassPtr, slotName);
void *defclassPtr,
char *slotName;
```

Purpose: Determines if the specified slot is directly accessible.

Arguments: 1) A generic pointer to a defclass data structure.

2) The name of the slot.

Returns: An integer: 1 if the slot is directly accessible, otherwise 0.

4.12.23 SlotExistP

int SlotExistP(defclassPtr, slotName, inheritFlag);
void *defclassPtr,
char *slotName;
int inheritFlag;

Purpose: Determines if the specified slot exists.

Arguments: 1) A generic pointer to a defclass data structure.

2) The name of the slot.

Returns: An integer: If inheritFlag is 0 and the slot is directly defined in the

specified class, then 1 is returned, otherwise 0 is returned. If inheritFlag is 1 and the slot is defined either in the specified class or

an inherited class, then 1 is returned, otherwise 0 is returned.

4.12.24 SlotFacets

```
void SlotFacets(defclassPtr, slotName, result);
void *defclassPtr;
char *slotName;
DATA_OBJECT *result;
```

Purpose: Groups the facet values of a class slot into a multifield data object.

This function is the C equivalent of the CLIPS **slot-facets** command. See section 10.8.1.11 in the Basic Programming Guide

for more detail.

Arguments: 1) A generic pointer to the class.

2) Name of the slot.

3) Pointer to the data object in which to store the multifield.

Returns: No meaningful return value.

4.12.25 SlotInitableP

```
int SlotInitableP(defclassPtr, slotName);
void *defclassPtr,
char *slotName;
```

Purpose: Determines if the specified slot is initable.

Arguments: 1) A generic pointer to a defclass data structure.

2) The name of the slot.

Returns: An integer: 1 if the slot is initable, otherwise 0.

4.12.26 SlotPublicP

```
int SlotPublicP(defclassPtr, slotName);
void *defclassPtr,
char *slotName;
```

Purpose: Determines if the specified slot is public.

Arguments: 1) A generic pointer to a defclass data structure.

2) The name of the slot.

Returns: An integer: 1 if the slot is public, otherwise 0.

4.12.27 SlotRange

```
void SlotRange(defclassPtr, slotName, result);
void *defclassPtr;
char *slotName;
DATA_OBJECT *result;
```

Purpose: Groups the numeric range information for a slot into a multifield

data object. This function is the C equivalent of the CLIPS

slot-range function.

Arguments: 1) A generic pointer to the class.

2) Name of the slot.

3) Pointer to the data object in which to store the multifield.

Returns: No meaningful return value.

4.12.28 SlotSources

```
void SlotSources(defclassPtr, slotName, result);
void *defclassPtr;
char *slotName;
DATA_OBJECT *result;
```

Purpose: Groups the names of the class sources of a slot into a multifield data

object. This function is the C equivalent of the CLIPS **slot-sources** command. See section 10.8.1.12 in the Basic Programming Guide

for more detail.

Arguments: 1) A generic pointer to the class.

- 2) Name of the slot.
- 3) Pointer to the data object in which to store the multifield.

Returns: No meaningful return value.

4.12.29 SlotTypes

```
void SlotTypes(defclassPtr, slotName, result);
void *defclassPtr;
char *slotName;
DATA_OBJECT *result;
```

Purpose: Groups the names of the primitive data types allowed for a slot into

a multifield data object. This function is the C equivalent of the

CLIPS **slot-types** function.

Arguments: 1) A generic pointer to the class.

2) Name of the slot.

3) Pointer to the data object in which to store the multifield.

Returns: No meaningful return value.

4.12.30 SlotWritableP

```
int SlotWritableP(defclassPtr, slotName);
void *defclassPtr,
char *slotName;
```

Purpose: Determines if the specified slot is writable.

Arguments: 1) A generic pointer to a defclass data structure.

2) The name of the slot.

Returns: An integer: 1 if the slot is writable, otherwise 0.

4.12.31 SubclassP

```
int SubclassP(defclassPtr1, defclassPtr2);
void *defclassPtr1, *defclassPtr2;
```

Purpose: Determines if a class is a subclass of another class.

Arguments: 1) A generic pointer to a defclass data structure.

2) A generic pointer to a defclass data structure.

Returns: An integer: 1 if the first class is a subclass of the second class.

4.12.32 SuperclassP

```
int SuperclassP(defclassPtr1, defclassPtr2);
void *defclassPtr1, *defclassPtr2;
```

Purpose: Determines if a class is a superclass of another class.

Arguments: 1) A generic pointer to a defclass data structure.

2) A generic pointer to a defclass data structure.

Returns: An integer: 1 if the first class is a superclass of the second class.

4.12.33 Undefclass

```
int Undefclass(defclassPtr);
void *defclassPtr;
```

Purpose: Removes a class and all its subclasses from CLIPS (the C

equivalent of the CLIPS undefclass command).

Arguments: A generic pointer to a defclass data structure.

Returns: An integer; zero (0) if the class could not be deleted, otherwise a

one (1).

4.13 INSTANCE FUNCTIONS

The following function calls are used for manipulating instances.

4.13.1 BinaryLoadInstances

```
long BinaryLoadInstances(fileName);
char *fileName;
```

Purpose: Loads a set of instances from a binary file into the CLIPS data base

(the C equivalent of the CLIPS **bload-instances** command).

Arguments: A string representing the name of the binary file.

Returns: Returns the number of instances restored or -1 if the file could not

be accessed.

4.13.2 BinarySaveInstances

long BinarySaveInstances(fileName, saveCode, NULL, TRUE);
char *fileName;
int saveCode;

Purpose: Saves the instances in the system to the specified binary file (the C

equivalent of the CLIPS bsave-instances command).

Arguments: 1) A string representing the name of the binary file.

2) An integer flag indicating whether to save local (current module only) or visible instances. Use either the constant

LOCAL_SAVE or VISIBLE_SAVE.

3) Should always be NULL.4) Should always be TRUE.

Returns: Returns the number of instances saved.

4.13.3 CreateRawInstance

```
void *CreateRawInstance(defclassPtr,instanceName);
void *defclassPtr;
char *instanceName;
```

Purpose: Creates an empty instance with the specified name of the specified

class. No slot overrides or class default initializations are performed

for the instance.

Arguments: 1) A generic pointer to the class of the new instance.

2) The name of the new instance.

Returns: A generic pointer to the new instance, NULL on errors.

WARNING: This function bypasses message-passing.

4.13.4 DecrementInstanceCount

```
void DecrementInstanceCount(instancePtr);
void *instancePtr;
```

Purpose: This function should *only* be called to reverse the effects of a

previous call to IncrementInstanceCount(). As long as an instance's count is greater than zero, the memory allocated to it cannot be

released for other use.

Arguments: A generic pointer to the instance.

Returns: No meaningful return value.

4.13.5 DeleteInstance

```
int DeleteInstance(instancePtr);
void *instancePtr;
```

Purpose: Deletes the specified instance(s).

Arguments: A generic pointer to the instance to be deleted. If the pointer is

NULL, all instances in the system are deleted.

Returns: Non-zero if successful, 0 otherwise.

WARNING: This function bypasses message-passing.

4.13.6 DirectGetSlot

```
void DirectGetSlot(instancePtr, slotName, result);
void *instancePtr;
char *slotName;
DATA_OBJECT *result;
```

Purpose: Stores the value of the specified slot of the specified instance in the

caller's buffer (the C equivalent of the CLIPS dynamic-get

function).

Arguments: 1) A generic pointer to the instance.

2) The name of the slot.

3) The caller's buffer for the slot value. See sections 3.2.3 and 3.2.4 for information on getting the value stored in a

DATA_OBJECT.

Returns: No meaningful return value.

WARNING: This function bypasses message-passing.

4.13.7 DirectPutSlot

```
int DirectPutSlot(instancePtr, slotName, newValue);
void *instancePtr;
char *slotName;
```

DATA_OBJECT *newValue;

Purpose:

Stores a value in the specified slot of the specified instance (the C equivalent of the CLIPS **dynamic-put** function).

Arguments:

- 1) A generic pointer to the instance.
- 2) The name of the slot.
- 3) The caller's buffer containing the new value (an error is generated if this value is NULL). See sections 3.3.3 and 3.3.4 for information on setting the value stored in a DATA_OBJECT.

Returns:

Returns an integer; if zero, an error occurred while setting the slot. If non-zero, no errors occurred.

WARNING:

This function bypasses message-passing.

4.13.8 FindInstance

```
void *FindInstance(theModule, instanceName, searchImports);
void *theModule;
char *instanceName;
int searchImports;
```

Purpose:

Returns the address of the specified instance.

Arguments:

- 1) A generic pointer to the module to be searched (NULL to search the current module).
- 2) The name of the instance (should not include a module specifier).
- 3) A boolean flag indicating whether imported modules should also be searched: TRUE to search imported modules, otherwise FALSE.

Returns:

A generic pointer to the instance, NULL if the instance does not exist.

4.13.9 GetInstanceClass

```
void *GetInstanceClass(instancePtr);
void *instancePtr;
```

Purpose:

Determines the class of an instance.

Arguments: A generic pointer to an instance.

Returns: A generic pointer to the class of the instance.

4.13.10 GetInstanceName

```
char *GetInstanceName(instancePtr);
void *instancePtr;
```

Purpose: Determines the name of an instance.

Arguments: A generic pointer to an instance.

Returns: The name of the instance.

4.13.11 GetInstancePPForm

```
void GetInstancePPForm(buffer, bufferLength, instancePtr);
char *buffer;
int bufferLength;
void *instancePtr;
```

Purpose: Returns the pretty print representation of an instance in the caller's

buffer.

Arguments: 1) A pointer to the caller's character buffer.

2) The maximum number of characters which could be stored in the caller's buffer (not including space for the terminating null

character).

3) A generic pointer to an instance.

Returns: No meaningful return value. The instance pretty print form is stored

in the caller's buffer.

4.13.12 GetInstancesChanged

int GetInstancesChanged();

Purpose: Determines if any changes to instances of user-defined instances

have occurred, e.g. instance creations/deletions or slot value changes. If this function returns a non-zero integer, it is the user's responsibility to call SetInstancesChanged(0) to reset the internal flag. Otherwise, this function will continue to return non-zero even

when no changes have occurred. This function is primarily used to determine when to update a display tracking instances.

Arguments: None.

Returns: 0 if no changes to instances of user-defined classes have occurred,

non-zero otherwise.

4.13.13 GetNextInstance

```
void *GetNextInstance(instancePtr);
void *instancePtr;
```

Purpose: Provides access to the list of instances.

Arguments: A generic pointer to an instance (or NULL to get the first instance

in the list).

Returns: A generic pointer to the first instance in the list of instances if

instancePtr is NULL, otherwise a pointer to the instance immediately following instancePtr in the list. If instancePtr is the

last instance in the list, then NULL is returned.

4.13.14 GetNextInstanceInClass

```
void *GetNextInstanceInClass(defclassPtr,instancePtr);
void *defclassPtr,*instancePtr;
```

Purpose: Provides access to the list of instances for a particular class.

Arguments: 1) A generic pointer to a class.

2) A generic pointer to an instance (or NULL to get the first

instance in the specified class).

Returns: A generic pointer to the first instance in the list of instances for the

specified class if *instancePtr* is NULL, otherwise a pointer to the instance immediately following *instancePtr* in the list. If *instancePtr* is the last instance in the class, then NULL is returned.

4.13.15 GetNextInstanceInClassAndSubclasses

void *GetNextInstanceInClassAndSubclasses(defclassPtr,instancePtr,

iterationData);
void **defclassPtr, *instancePtr;
DATA_OBJECT *iterationData;

Purpose:

Provides access to the list of instances for a particular class and its subclasses.

Arguments:

- 1) A generic pointer to a generic pointer to a class.
- 2) A generic pointer to an instance (or NULL to get the first instance in the specified class).
- 3) A pointer to a DATA_OBJECT in which instance iteration is stored. No initialization of this argument is required and the values stored in this argument are not intended for examination by the calling function.

Returns:

A generic pointer to the first instance in the list of instances for the specified class and its subclasses if *instancePtr* is NULL, otherwise a pointer to the instance immediately following *instancePtr* in the list or the next instance in a subclass of the class. If *instancePtr* is the last instance in the class and all its subclasses, then NULL is returned.

As the subclasses of the specified class are iterated through to find instances, the value stored in defclassPtr is updated to indicate the class of the instance returned by this function.

Example

4.13.16 IncrementInstanceCount

```
void IncrementInstanceCount(instancePtr);
void *instancePtr;
```

Purpose:

This function should be called for each external copy of an instance address to let CLIPS know that such an outstanding external reference exists. As long as an instance's count is greater than zero, CLIPS will not release its memory because there may be outstanding pointers to the instance. However, the instance can still be *functionally* deleted, i.e. the instance will *appear* to no longer be in the system. The instance address always can be safely passed to instance access functions as long as the count for the instance is greater than zero. These functions will recognize when an instance has been functionally deleted.

Arguments: A generic pointer to the instance.

Returns: No meaningful return value.

Example

```
/*=======*/
/* Incorrect */
/*======*/
void InstanceReferenceExample()
  void *myInstancePtr;
  myInstancePtr = FindInstance(NULL, "my-instance", TRUE);
  /*========*/
  /* Instance my-instance could be potentially */
  /* deleted during the run.
  /*=======*/
  Run(-1L);
  /*=======*/
  /* This next function call could dereference */
  /* a dangling pointer and cause a crash. */
  /*======*/
  Del eteInstance(myInstancePtr);
/*======*/
/* Correct */
/*======*/
void InstanceReferenceExample()
  void *myInstancePtr;
  myInstancePtr = FindInstance(NULL, "my-instance", TRUE);
  /*-----*/
```

4.13.17 Instances

```
void Instances(logicalName, modulePtr, className, subclassFlag);
char *logicalName;
void *defmodulePtr;
char *className;
int subclassFlag;
```

Purpose:

Prints the list of all direct instances of a specified class currently in the system (the C equivalent of the CLIPS **instances** command).

Arguments:

- 1) The logical name to which output is sent.
- 2) A generic pointer to a defmodule data structure (NULL indicates to list all instances of all classes in all modules—the third and fourth arguments are ignored).
- 3) The name of the class for which to list instances (NULL indicates to list all instances of all classes in the specified module—the fourth argument is ignored).
- 4) A flag indicating whether or not to list recursively direct instances of subclasses of the named class in the specified module. 0 indicates no, and any other value indicates yes.

Returns:

No meaningful return value.

4.13.18 LoadInstances

```
long LoadInstances(fileName);
char *fileName;
```

Purpose:

Loads a set of instances into the CLIPS data base (the C equivalent

of the CLIPS load-instances command).

Arguments:

A string representing the name of the file.

Returns: Returns the number of instances loaded or -1 if the file could not be

accessed.

4.13.19 MakeInstance

void *MakeInstance(makeCommand);
char *makeCommand;

Purpose: Creates and initializes an instance of a user-defined class (the C

equivalent of the CLIPS make-instance function).

Arguments: A string containing a make-instance command in the format

below:

(<instance-name> of <class-name> <slot-override>*)
<slot-override> :== (<slot-name> <constant>*)

Returns: A generic pointer to the new instance, NULL on errors.

Example

```
MakeInstance("(henry of boy (age 8))");
```

4.13.20 RestoreInstances

```
long RestoreInstances(fileName);
char *fileName;
```

Purpose: Loads a set of instances into the CLIPS data base (the C equivalent

of the CLIPS restore-instances command).

Arguments: A string representing the name of the file.

Returns: Returns the number of instances restored or -1 if the file could not

be accessed.

4.13.21 SaveInstances

```
long SaveInstances(fileName, saveCode, NULL, TRUE);
char *fileName;
int saveCode;
```

Purpose: Saves the instances in the system to the specified file (the C

equivalent of the CLIPS save-instances command).

Arguments:

- 1) A string representing the name of the file.
- 2) An integer flag indicating whether to save local (current module only) or visible instances. Use either the constant LOCAL SAVE or VISIBLE SAVE.
- 3) Should always be NULL.
- 4) Should always be TRUE.

Returns:

Returns the number of instances saved.

4.13.22 Send

```
void Send(instanceBuffer, msg, msgArgs, result);
DATA_OBJECT *instanceBuffer, *result;
char *msg, *msgArgs;
```

Purpose:

Message-passing from C Sends a message with the specified arguments to the specified object and stores the result in the caller's buffer (the C equivalent of the CLIPS **send** function).

Arguments:

- 1) A data value holding the object (instance, symbol, float, etc.) which will receive the message.
- 2) The message.
- 3) A string containing any *constant* arguments separated by blanks (this argument can be NULL).
- 4) Caller's buffer for storing the result of the message. See sections 3.2.3 and 3.2.4 for information on getting the value stored in a DATA_OBJECT.

Returns:

No meaningful return value.

Example

```
void SendMessageExample()
  {
    DATA_0BJECT insdata, rtn;
    void *myInstancePtr;

    myInstancePtr = MakeInstance("(my-instance of MY-CLASS");
    SetType(insdata, INSTANCE_ADDRESS);
    SetValue(insdata, myInstancePtr);
    Send(&insdata, "my-msg", "1 abc 3", &rtn);
}
```

4.13.23 SetInstancesChanged

void SetInstancesChanged(changedFlag);
int changedFlag;

Purpose: Sets the internal boolean flag which indicates when changes to

instances of user-defined classes have occurred. This function is normally used to reset the flag to zero after GetInstancesChanged()

returns non-zero.

Arguments: An integer indicating whether changes in instances of user-defined

classes have occurred (non-zero) or not (0).

Returns: Nothing useful.

4.13.24 UnmakeInstance

```
int UnmakeInstance(instancePtr);
void *instancePtr;
```

Purpose: This function is equivalent to DeleteInstance except that it uses

message-passing instead of directly deleting the instance(s).

Arguments: A generic pointer to the instance to be deleted. If the pointer is

NULL, all instances in the system are deleted.

Returns: Non-zero if successful, 0 otherwise.

4.13.25 ValidInstanceAddress

```
int ValidInstanceAddress(instancePtr);
void *instancePtr;
```

Purpose: Determines if an instance referenced by an address still exists. See

the description of IncrementInstanceCount.

Arguments: The address of the instance.

Returns: The integer 1 if the instance still exists, 0 otherwise.

4.13.26 LoadInstancesFromString

```
int LoadInstancesFromString(inputString, maximumPosition);
char *inputString;
int maximumPosition;
```

Purpose: Loads a set of instances into the CLIPS data base using a string as

the input source (in a manner similar to the CLIPS load-instances

command).

Arguments: 1) A string containing the instance definitions.

2) The maximum number of characters to be read from the string.

A value of -1 indicates the entire string.

Returns: Returns the number of instances loaded or -1 if there were problems

using the string as an input source.

4.13.27 RestoreInstancesFromString

```
int RestoreInstancesFromString(inputString, maximumPosition);
char *inputString;
int maximumPosition:
```

Purpose: Loads a set of instances into the CLIPS data base using a string as

the input source (in a manner similar to the CLIPS restore-

instances command).

Arguments: 1) A string containing the instance definitions.

2) The maximum number of characters to be read from the string.

A value of -1 indicates the entire string.

Returns: Returns the number of instances loaded or -1 if there were problems

using the string as an input source.

4.14 DEFMESSAGE-HANDLER FUNCTIONS

The following function calls are used for manipulating defmessage-handlers.

4.14.1 FindDefmessageHandler

Purpose: Returns an index to the specified message-handler within the list of

handlers for a particular class.

Arguments:

- 1) A generic pointer to the class to which the handler is attached.
- 2) The name of the handler.
- 3) The type of the handler: around, before, primary or after.

Returns:

An index to the specified handler if it exists, otherwise 0.

4.14.2 GetDefmessageHandlerList

int includeInheritedp

 $void\ GetDefmessageHandlerList(defclassPtr,\&returnValue,\\includeInheritedp);\\void\ *defclassPtr;\\DATA_0BJECT\ returnValue;$

Purpose:

Returns the list of currently defined defmessage-handlers for the specified class. This function is the C equivalent of the CLIPS **get-defmessage-handler-list** command).

Arguments:

- 1) A generic pointer to the class (NULL for all classes).
- 2) A pointer to the DATA_OBJECT in which the list of defmessage-handler constructs is to be stored.
- 3) An integer flag indicating whether to list inherited handlers (TRUE to list them or FALSE to not list them).

Returns:

No meaningful value. The second argument to this function is set to a multifield value containing the list of defmessage-handler constructs for the specified class. The multifield functions described in section 3.2.4 can be used to retrieve the defmessage-handler class, name, and type from the list. Note that the class, name, and type for each defmessage-handler are stored as triplets in the return multifield value.

4.14.3 GetDefmessageHandlerName

char *GetDefmessageHandlerName(defclassPtr, handlerIndex);
void *defclassPtr;
unsigned handlerIndex;

Purpose: Returns the name of a message-handler.

Arguments: 1) A generic pointer to a defclass data structure.

2) The index of a message-handler.

Returns: A string containing the name of the message-handler.

4.14.4 GetDefmessageHandlerPPForm

char *GetDefmessageHandlerPPForm(defclassPtr, handlerIndex);
void *defclassPtr;
unsigned handlerIndex;

Purpose: Returns the pretty print representation of a message-handler.

Arguments: 1) A generic pointer to a defclass data structure.

2) The index of a message-handler.

Returns: A string containing the pretty print representation of the

message-handler (or the NULL pointer if no pretty print

representation exists).

4.14.5 GetDefmessageHandlerType

char *GetDefmessageHandlerType(defclassPtr, handlerIndex);
void *defclassPtr;
unsigned handlerIndex;

Purpose: Returns the type (around, before, primary or after) of a

message-handler.

Arguments: 1) A generic pointer to a defclass data structure.

2) The index of a message-handler.

Returns: A string containing the type of the message-handler.

4.14.6 GetDefmessageHandlerWatch

int GetDefmessageHandlerWatch(defclassPtr, handlerIndex);
void *defclassPtr;
unsigned handlerIndex

Purpose: Indicates whether or not a particular defmessage-handler is being

watched.

Arguments: A generic pointer to a defclass data structure and the index of the

message-handler.

Returns: An integer; one (1) if the defmessage-handler is being watched,

otherwise a zero (0).

4.14.7 GetNextDefmessageHandler

unsigned GetNextDefmessageHandler(defclassPtr, handlerIndex);
void *defclassPtr;
unsigned handlerIndex;

Purpose: Provides access to the list of message-handlers.

Arguments: 1) A generic pointer to a defclass data structure.

2) An index to a particular message-handler for the class (or 0 to get the first message-handler).

Returns: An index to the first handler in the list of handlers if *handlerIndex* is

0, otherwise an index to the handler immediately following *handlerIndex* in the list of handlers for the class. If *handlerIndex* is the last handler in the list of handlers for the class, then 0 is

returned.

4.14.8 IsDefmessageHandlerDeletable

int IsDefmessageHandlerDeletable(defclassPtr, handlerIndex);
void *defclassPtr;
unsigned handlerIndex;

Purpose: Indicates whether or not a particular message-handler can be

deleted.

Arguments: 1) A generic pointer to a defclass data structure.

2) The index of a message-handler.

Returns: An integer; zero (0) if the message-handler cannot be deleted,

otherwise a one (1).

4.14.9 ListDefmessageHandlers

Purpose: Prints the list of message-handlers for the specified class. This

function is the C equivalent of the CLIPS

list-defmessage-handlers command).

Arguments: 1) The logical name to which the listing output is sent.

- 2) A generic pointer to the class (NULL for all classes).
- 3) An integer flag indicating whether to list inherited handlers (TRUE to list them or FALSE to not list them).

Returns:

No meaningful return value.

4.14.10 PreviewSend

```
void PreviewSend(logicalName, defclassPtr, messageName);
char *logicalName;
void *defclassPtr;
char *messageName;
```

Purpose:

Prints a list of all applicable message-handlers for a message sent to an instance of a particular class (the C equivalent of the CLIPS **preview-send** command). Output is sent to the logical name **wdisplay**.

Arguments:

- 1) The logical name to which output is sent.
- 2) A generic pointer to the class.
- 3) The message name.

Returns:

No meaningful return value.

4.14.11 SetDefmessageHandlerWatch

Purpose:

Sets the message-handlers watch item for a specific defmessage-

handler.

Arguments:

The new message-handlers watch state, a generic pointer to a

defclass data structure, and the index of the message-handler.

4.14.12 UndefmessageHandler

```
int UndefmessageHandler(defclassPtr, handlerIndex);
void *defclassPtr;
unsigned handlerIndex;
```

Purpose: Removes a message-handler from CLIPS (similar but not

equivalent to the CLIPS undefmessage-handler command - see

WildDeleteHandler).

Arguments: 1) A generic pointer to a defclass data structure (NULL to delete

all message-handlers in all classes).

2) The index of the message-handler (0 to delete all message-handlers in the class - must be 0 if *defclassPtr* is

NULL).

Returns: An integer; zero (0) if the message-handler could not be deleted,

otherwise a one (1).

4.15 DEFINSTANCES FUNCTIONS

The following function calls are used for manipulating definstances.

4.15.1 DefinstancesModule

char *DefinstancesModule(theDefinstances);
void *theDefinstances;

Purpose: Returns the module in which a definstances is defined (the C

equivalent of the CLIPS definstances-module command).

Arguments: A generic pointer to a definstances.

Returns: A string containing the name of the module in which the

definstances is defined.

4.15.2 FindDefinstances

void *FindDefinstances(definstancesName);
char *definstancesName;

Purpose: Returns a generic pointer to a named definstances.

Arguments: The name of the definstances to be found.

Returns: A generic pointer to the named definstances if it exists, otherwise

NULL.

4.15.3 GetDefinstancesList

void GetDefinstancesList(&returnValue, theModule);
DATA_OBJECT returnValue;
void *theModule;

Purpose:

Returns the list of definstances in the specified module as a multifield value in the returnValue DATA_OBJECT (the C equivalent of the CLIPS **get-definstances-list** function).

Arguments:

- 1) A pointer to the caller's DATA_OBJECT in which the return value will be stored. The multifield functions described in section 3.2.4 can be used to retrieve the definstances names from the list.
- 2) A generic pointer to the module from which the list will be extracted. A NULL pointer indicates that the list is to be extracted from all modules.

Returns: No meaningful return value.

4.15.4 GetDefinstancesName

char *GetDefinstancesName(definstancesPtr);
void *definstancesPtr;

Purpose: Returns the name of a definstances.

Arguments: A generic pointer to a definstances data structure.

Returns: A string containing the name of the definstances.

4.15.5 GetDefinstancesPPForm

char *GetDefinstancesPPForm(definstancesPtr);
void *definstancesPtr;

Purpose: Returns the pretty print representation of a definitances.

Arguments: A generic pointer to a definstances data structure.

Returns: A string containing the pretty print representation of the

definstances (or the NULL pointer if no pretty print representation

exists).

4.15.6 GetNextDefinstances

void *GetNextDefinstances(definstancesPtr);
void *definstancesPtr;

Purpose: Provides access to the list of definstances.

Arguments: A generic pointer to a definstances data structure (or NULL to get

the first definstances).

Returns: A generic pointer to the first definstances in the list of definstances

if definstancesPtr is NULL, otherwise a generic pointer to the definstances immediately following definstancesPtr in the list of definstances. If definstancesPtr is the last definstances in the list of

definstances, then NULL is returned.

4.15.7 IsDefinstancesDeletable

int IsDefinstancesDeletable(definstancesPtr);
void *definstancesPtr;

Purpose: Indicates whether or not a particular class definstances can be

deleted.

Arguments: A generic pointer to a definstances data structure.

Returns: An integer; zero (0) if the definstances cannot be deleted, otherwise

a one (1).

4.15.8 ListDefinstances

void ListDefinstances(logicalName, theModule);
char *logicalName;
void *theModule:

Purpose: Prints the list of definstances (the C equivalent of the CLIPS

list-definstances command).

Arguments: 1) The logical name to which the listing output is sent.

2) A generic pointer to the module containing the definstances to be listed. A NULL pointer indicates that definstances in all

modules should be listed.

Returns: No meaningful return value.

4.15.9 Undefinstances

int Undefinstances(definstancesPtr);
void *definstancesPtr;

Purpose: Removes a definstances from CLIPS (the C equivalent of the

CLIPS **undefinstances** command).

Arguments: A generic pointer to a definstances data structure.

Returns: An integer; zero (0) if the definstances could not be deleted,

otherwise a one (1).

4.16 DEFMODULE FUNCTIONS

The following function calls are used for manipulating defmodules.

4.16.1 FindDefmodule

```
void *FindDefmodule(defmoduleName);
char *defmoduleName;
```

Purpose: Returns a generic pointer to a named defmodule.

Arguments: The name of the defmodule to be found.

Returns: A generic pointer to the named defmodule if it exists, otherwise

NULL.

4.16.2 GetCurrentModule

voi d *GetCurrentModule();

Purpose: Returns the current module (the C equivalent of the CLIPS get-

current-module function).

Arguments: None.

Returns: A generic pointer to the generic defmodule data structure that is the

current module.

4.16.3 GetDefmoduleList

void GetDefmoduleList(&returnValue);

DATA_OBJECT returnValue;

Purpose: Returns the list of defmodules as a multifield value in the

returnValue DATA_OBJECT (the C equivalent of the CLIPS get-

defmodule-list function).

Arguments: A pointer to the caller's DATA_OBJECT in which the return value

will be stored. The multifield functions described in section 3.2.4

can be used to retrieve the defmodule names from the list.

Returns: No meaningful return value.

4.16.4 GetDefmoduleName

```
char *GetDefmodul eName(defmodul ePtr);
voi d *defmodul ePtr;
```

Purpose: Returns the name of a defmodule.

Arguments: A generic pointer to a defmodule data structure.

Returns: A string containing the name of the defmodule.

4.16.5 GetDefmodulePPForm

```
char *GetDefmodul ePPForm(defmodul ePtr);
voi d *defmodul ePtr;
```

Purpose: Returns the pretty print representation of a defmodule.

Arguments: A generic pointer to a defmodule data structure.

Returns: A string containing the pretty print representation of the defmodule

(or the NULL pointer if no pretty print representation exists).

4.16.6 GetNextDefmodule

```
voi d *GetNextDefmodul e(defmodul ePtr);
voi d *defmodul ePtr;
```

Purpose: Provides access to the list of defmodules.

Arguments: A generic pointer to a defmodule data structure (or NULL to get the

first defmodule).

Returns: A generic pointer to the first defmodule in the list of defmodules if

defmodulePtr is NULL, otherwise a generic pointer to the defmodule immediately following defmodulePtr in the list of defmodules. If defmodulePtr is the last defmodule in the list of

defmodules, then NULL is returned.

4.16.7 ListDefmodules

```
void ListDefmodules(logical Name);
char *logical Name;
```

Purpose: Prints the list of defmodules (the C equivalent of the CLIPS

list-defmodules command).

Arguments: 1) The logical name to which the listing output is sent.

Returns: No meaningful return value.

4.16.8 SetCurrentModule

```
void *SetCurrentModule(defmodulePtr);
void *defmodulePtr;
```

Purpose: Sets the current module to the specified module (the C equivalent of

the CLIPS **set-current-module** function).

Arguments: A generic pointer to a defmodule data structure.

Returns: A generic pointer to the previous current defmodule data structure.

4.17 EMBEDDED APPLICATION EXAMPLES

4.17.1 User-Defined Functions

This section lists the steps needed to define and use an embedded CLIPS application. The example given is the same system used in section 3.4, now set up to run as an embedded application.

1) Copy all of the CLIPS source code file to the user directory.

2) Define the user function (TripleNumber), a new main routine, and UserFunctions in a new file. These could go in separate files if desired. For this example, they will all be included in a single file.

```
#include "clips.h"
main()
  InitializeEnvironment();
  Load("constructs.clp");
  Reset():
  Run(-1L)
void TripleNumber(
  DATA_OBJECT_PTR returnValuePtr)
  {
              *value:
  voi d
              longValue;
  long
  doubl e
               doubl eVal ue:
   /*-----*/
  /* If illegal arguments are passed, return zero. */
  /*_____*/
  if (ArgCountCheck("triple", EXACTLY, 1) == -1)
     SetpType(returnValuePtr, INTEGER);
     SetpValue(returnValuePtr, AddLong(0L));
     return;
    }
  if (! ArgTypeCheck("triple", 1, INTEGER_OR_FLOAT, returnValuePtr))
     SetpType(returnValuePtr, INTEGER);
     SetpValue(returnValuePtr, AddLong(0L));
     return:
    }
  /* Triple the number. */
  /*----*/
  if (GetpType(returnValuePtr) == INTEGER)
     value = GetpValue(returnValuePtr);
     longValue = 3 * ValueToLong(value);
     SetpValue(returnValuePtr, AddLong(longValue));
  else /* the type must be FLOAT */
     value = GetpValue(returnValuePtr);
     doubleValue = 3.0 * ValueToDouble(value);
     SetpValue(returnValuePtr, AddDouble(doubleValue));
    }
```

3) Define constructs which use the new function in a file called **constructs.clp** (or any file; just be sure the call to **Load** loads all necessary constructs prior to execution).

```
(deffacts init-data
    (data 34)
    (data 13.2))

(defrule get-data
    (data ?num)
=>
    (printout t "Tripling " ?num crlf)
    (assert (new-value (triple ?num))))

(defrule get-new-value
    (new-value ?num)
=>
    (printout t crlf "Now equal to " ?num crlf))
```

- 4) Compile all CLIPS files, *except* main.c, along with all user files.
- 5) Link all object code files.
- 6) Execute new CLIPS executable.

4.17.2 Manipulating Objects and Calling CLIPS Functions

This section lists the steps needed to define and use an embedded CLIPS application. The example illustrates how to call deffunctions and generic functions as well as manipulate objects from C.

- 1) Copy all of the CLIPS source code file to the user directory.
- 2) Define a new main routine in a new file.

```
#include <stdio.h>
#include "clips.h"
```

```
main()
  void *c1, *c2, *c3;
  DATA_OBJECT insdata, result;
  char numbuf[20];
  InitializeEnvironment();
  /*-----*/
  /* Load the classes, message-handlers, generic functions */
  /* and generic functions necessary for handling complex */
  /* numbers.
  /*----*/
  Load("compl ex. cl p");
  /*----*/
  /* Create two complex numbers. Message-passing is used to */
  /* create the first instance c1, but c2 is created and has */
  /* its slots set directly.
  /*----*/
  c1 = MakeInstance("(c1 of COMPLEX (real 1) (imag 10))");
  c2 = CreateRawInstance(FindDefclass("COMPLEX"), "c2");
  result.type = INTEGER;
  result.value = AddLong(3L);
  DirectPutSlot(c2, "real", &result);
  result.type = INTEGER;
  result. value = AddLong(-7L);
  DirectPutSlot(c2, "i mag", &result);
  /*-----*/
  /st Call the function '+' which has been overloaded to handle st/
  /* complex numbers. The result of the complex addition is */
  /* stored in a new instance of the COMPLEX class.
  FunctionCall("+", "[c1] [c2]", &result);
  c3 = FindInstance(NULL, DOToString(result), TRUE);
  /*----*/
  /* Print out a summary of the complex addition using the */
  /st "print" and "magnitude" messages to get information st/
  /* about the three complex numbers.
  /*----*/
  PrintRouter("stdout", "The addition of \n');
  SetType(insdata, INSTANCE_ADDRESS);
  SetValue(insdata, c1);
  Send(&i nsdata, "pri nt", NULL, &result);
  PrintRouter("stdout", "\nand\n\n");
  SetType(insdata, INSTANCE_ADDRESS);
  SetValue(insdata, c2);
```

```
Send(&insdata, "print", NULL, &result);
PrintRouter("stdout", "\nis\n\n");
SetType(insdata, INSTANCE_ADDRESS);
SetValue(insdata, c3);
Send(&insdata, "print", NULL, &result);
PrintRouter("stdout", "\nand the resulting magnitude is\n\n");
SetType(insdata, INSTANCE_ADDRESS);
SetValue(insdata, c3);
Send(&insdata, "magnitude", NULL, &result);
sprintf(numbuf, "%lf\n", DOToDouble(result));
PrintRouter("stdout", numbuf);
}
UserFunctions()
{}
```

3) Define constructs which use the new function in a file called **complex.clp** (or any file; just be sure the call to **Load** loads all necessary constructs prior to execution).

```
(defclass COMPLEX (is-a USER)
  (role concrete)
  (slot real (create-accessor read-write))
  (slot imag (create-accessor read-write)))
(defmethod + ((?a COMPLEX) (?b COMPLEX))
  (make-instance of COMPLEX
        (real (+ (send ?a get-real) (send ?b get-real)))
        (imag (+ (send ?a get-imag) (send ?b get-imag)))))
(defmessage-handler COMPLEX magnitude ()
        (sqrt (+ (** ?self:real 2) (** ?self:imag 2))))
```

- 4) Compile all CLIPS files, *except* main.c, along with all user files.
- 5) Link all object code files.
- 6) Execute new CLIPS executable.

Section 5 - Creating a CLIPS Run-time Program

5.1 COMPILING THE CONSTRUCTS

This section describes the procedure for creating a CLIPS run-time module. A run-time program compiles all of the constructs (defrule, deffacts, deftemplate, etc.) into a single executable and reduces the size of the executable image. A run-time program will not run any faster than a program loaded using the **load** or **bload** commands. The **constructs-to-c** command used to generate a run-time program creates files containing the C data structures that would dynamically be allocated if the **load** or **bload** command was used. With the exception of some initialization routines, the **constructs-to-c** command does not generate any executable code. The primary benefits of creating a run-time program are: applications can be delivered as a single executable file; loading constructs as part of an executable is faster than loading them from an text or binary file; the CLIPS portion of the run-time program is smaller because the code needed to parse constructs can be discarded; and less memory is required to represent your program's constructs since memory for them is statically rather than dynamically allocated.

Creating a run-time module can be achieved with the following steps:

1) Start CLIPS and load in all of the constructs that will constitute a run-time module. Call the **constructs-to-c** command using the following syntax:

```
(constructs-to-c <file-name> <id> [<max-elements>])
```

where <file-name> is a string or a symbol, <id> is an integer, and the optional argument <max-elements> is also an integer. For example, if the construct file loaded was named "expert.clp", the conversion command might be

```
(constructs-to-c exp 1)
```

This command would store the converted constructs in several output files ("exp1_1.c", "exp1_2.c", ..., "exp7_1.c") and use a module id of 1 for this collection of constructs. The use of the module id will be discussed in greater detail later. Once the conversion is complete, exit CLIPS. For large systems, this output may be *very* large (> 200K). It is possible to limit the size of the generated files by using the <max-elements> argument. This argument indicates the maximum number of structures which may be placed in a single array stored in a file. Where possible, if this number is exceeded new files will be created to store additional information. This feature is useful for compilers that may place a limitation on the size of a file that may be compiled.

Note that the .c extension is added by CLIPS. When giving the file name prefix, users should consider the maximum number of characters their system allows in a file name. For example, under MS-DOS, only eight characters are allowed in the file name. For very large systems, it is possible for CLIPS to add up to 5 characters to the file name prefix. Therefore, for system which allow only 8 character file names, the prefix should be no more than 3 characters.

Constraint information associated with constructs is not saved to the C files generated by the **constructs-to-c** command unless dynamic constraint checking is enabled (using the **set-dynamic-constraint-checking** command).

The **constructs-to-c** command is not available in the standard CLIPS distribution executable. Users wishing to create a run-time program must recompile CLIPS to include this capability (see section 2.2 for information on tailoring CLIPS and the CONSTRUCT_COMPILER setup flag).

- 2) Set the RUN_TIME setup flag in the **setup.h** header file to 1 and compile all of the c files just generated.
- 3) Modify the main.c module for embedded operation. Unless the user has other specific uses, the argc and argv arguments to the main function should be eliminated. The user still must call the function InitializeEnvironment in the main module. It will have been modified to make appropriate initializations for the run-time version. Do not call the CommandLoop or RerouteStdin functions which are normally called from the main function of a command line version of CLIPS. Do not define any functions in the UserFunctions function. The function UserFunctions is not called during initialization. All of the function definitions have already been compiled in the 'C' constructs code. In addition to calling InitializeEnvironment, a function must be called to initialize the constructs module. This function is defined in the 'C' constructs code, and its name is dependent upon the id used when translating the constructs to 'C' code. The name of the function is InitCImage_<id>where <id> is the integer used as the construct module <id> In the example above, the function name would be InitCImage_1. These two initialization steps probably would be followed by any user initialization, then by a reset and run. An example main.c file would be

- 4) Recompile all of the CLIPS source code (the RUN_TIME flag should still be 1). This causes several modifications in the CLIPS code. The run-time CLIPS module does not have the capability to load new constructs. Do NOT change any other compiler flags! Because of the time involved in recompiling CLIPS, it may be appropriate to recompile the run-time version of CLIPS into a separate library from the full version of CLIPS.
- 5) Link all regular CLIPS modules together with any user-defined function modules and the 'C' construct modules. Make sure that any user-defined functions have global scope. *Do not* place the construct modules within a library for the purposes of linking (the regular CLIPS modules, however, can be placed in a library). Some linkers (most notably the VAX VMS linker) will not correctly resolve references to global data that is stored in a module consisting only of global data.
- 6) The run-time module which includes user constructs is now ready to run.

Note that individual constructs may not be added or removed in a run-time environment. Because of this, the **load** function is not available for use in run-time programs. The clear command will also not remove any constructs (although it will clear facts and instances). Use calls to the InitCImage_... functions to clear the environment and replace it with a new set of constructs. In addition, the **eval** and **build** functions do not work in a run-time environment.

Since new constructs can't be added, a run-time program can't dynamically load a deffacts or definstances construct. To dynamically load facts and/or instances in a run-time program, the CLIPS load-facts and load-instances functions or the C LoadFacts and LoadInstances functions should be used in place of deffacts and definstances constructs.

Switching between different images created using the constructs-to-c function is now supported. Switching, however, may not occur while a CLIPS program is executing (e.g. you cannot call a function from the RHS of a rule which switches a different image into memory). Note that switching between construct images will clear all facts and instances from the CLIPS environment. It is possible to switch to the same image more than once. An example main program which switches between two different construct images is shown following.

```
main()
  extern int failure;
 InitializeEnvironment();
  /*======*/
 /* Set up and run the first portion */
 /* of the expert system. */
 /*=======*/
 InitCI mage_1();
 Reset():
 Run(-1L);
  /*=======*/
 /* Check a global variable that was defined to */
 /* indicate which portion of the expert system */
 if (failure) InitCImage_2();
 else InitCImage_3();
  /*========*/
  /* Run the remaining portion of the expert system. */
 /*=======*/
 Reset();
 Run(-1L);
```

Section 6 - Combining CLIPS with Languages Other Than C

CLIPS is developed in C and is most easily combined with user functions written in C. However, other languages can be used for user-defined functions, and CLIPS even may be embedded within a program written in another language. Users wishing to embed CLIPS with Ada should consider using CLIPS/Ada (see the *CLIPS/Ada_Advanced Programming Guide*).

6.1 INTRODUCTION

This section will describe how to combine CLIPS with Ada or FORTRAN routines. Specific code examples will be used to illustrate the concepts. The code used in these examples is valid for VAX VMS systems which have the DEC C compiler, the DEC FORTRAN compiler, and the DEC Ada compiler.

Three basic capabilities are needed for complete language mixing.

- A program in another language may be used as the main program.
- The C access functions to CLIPS can be called from the other language and have parameters passed to them.
- Functions written in the other language can be called by CLIPS and have parameters passed to them.

The integration of CLIPS (and C) with other languages requires an understanding of how each language passes parameters between routines. In general, interface functions will be needed to pass parameters from C to another language and from another language to C. The basic concepts of mixed language parameter passing are the same regardless of the language or machine. However, since every machine and operating system passes parameters differently, specific details (and code) may differ from machine to machine. To improve usability and to minimize the amount of recoding needed for each machine, interface packages can be developed which allow user routines to call the standard CLIPS embedded command functions. The details of passing information *from* external routines to CLIPS generally are handled inside of the interface package. To pass parameters from CLIPS to an external routine, users will have to write interface functions. Example interface packages for VMS FORTRAN and VMS Ada to selected CLIPS functions are listed in appendix A. Section 6.9 will discuss how to construct an interface package for other machines/compilers.

6.2 ADA AND FORTRAN INTERFACE PACKAGE FUNCTION LIST

The Ada and FORTRAN interface packages in appendix A provide many of the embedded CLIPS commands discussed in section 4 of this manual. Each function in the interface package

prepends an *x* to the beginning of the corresponding C function name. A list of the C functions and their FORTRAN or Ada corollaries which are provided in the interface packages listed in the appendices appears below.

C Function	Ada/FORTRAN Function
InitializeEnvironment	xInitializeEnvironment
Reset	xReset
Load	xLoad
Run	xRun
Facts	xFacts
Watch	xWatch
Unwatch	xUnwatch
AssertString	xAssertString
Retract	xRetract
PrintRouter	xPrintRouter
FindDefrule	xFindDefrule
Undefrule	xUndefrule

The arguments to these functions are the same as described in section 4, however, the corresponding data type in either Ada or FORTRAN should be passed as a parameter. For example, when using Ada, the function xLoad should be passed an Ada string, not a C string (the function xLoad will perform the conversion). FORTRAN function names defined above do *not* follow ANSI 77 name standards. The VMS FORTRAN implementation described in this section allows long function names.

6.3 EMBEDDED CLIPS - USING AN EXTERNAL MAIN PROGRAM

Any program may be used as the main program for embedded CLIPS applications. The main program works essentially the same as in C.

Example Ada Main Program

```
with CLIPS; use CLIPS;
with TEXT_IO; use TEXT_IO;
procedure MAIN is

File_Name : string (1..50);
File_Open_Status : integer;
Rules_Fired : integer;
begin

xInitializeEnvironment;

File_Name (1..7) := "mab.clp";
    -- Load rules
```

```
File_Open_Status := xLoad (File_Name);

if File_Open_Status = 1 then
    xReset;
    Rules_Fired := xRun (-1);
    PUT (integer'IMAGE (Rules_Fired));
    PUT_LINE (" Rules Fired");
else
    PUT_LINE ("Unable to open rules file");
end if;
```

Example FORTRAN Main Program

```
PROGRAM MAIN
C
      INTEGER xLoad, FILE_OPEN_STATUS
      CHARACTER *8 FILE_NAME
      INTEGER xRun, RULES_FIRED
C
      CALL xInitializeEnvironment
C
      FILE_NAME = 'mab.clp'
      FILE_OPEN_STATUS = xLoad (FILE_NAME)
      IF (FILE_OPEN_STATUS . EQ. 1) THEN
        CALL xReset
        RULES_FIRED = xRun (-1)
        WRITE (6, 100) RULES_FIRED
      ELSE
        WRITE (6, 101)
      END IF
 100
      FORMAT (I8, ' RULES FIRED')
      FORMAT (' UNABLE TO OPEN RULES FILE')
      ST<sub>0</sub>P
      END
      SUBROUTINE UserFunctions
      RETURN
      END
```

6.4 ASSERTING FACTS INTO CLIPS

An external function may assert a fact into CLIPS by calling **xAssertString**. External functions also may retract a fact previously asserted from outside of CLIPS. Note that the parameter passed to xRetract must have been received from a call to xAssertString. Any other value will cause unpredictable results.

Ada Example

```
Fact_Pointer : integer;
Not_Previously_Retracted : boolean;

Fact_Pointer := xAssertString ("dummy hello");
Not_Previously_Retracted := xRetract (Fact_Pointer);

FORTRAN Example
CHARACTER *20 FACT_STRING
INTEGER xAssertString, FACT_POINTER
INTEGER xRetract, NOT_PREVIOUSLY_RETRACTED

FACT_STRING = 'dummy hello'
FACT_POINTER = xAssertString (FACT_STRING)
```

NOT_PREVIOUSLY_RETRACTED = xRetract (FACT_POINTER)

6.5 CALLING A SUBROUTINE FROM CLIPS

Like any other user-defined functions, subroutines written in other languages may be called from CLIPS. Depending on the language, the return value from the function call may or may not be useful. For example, most FORTRAN implementations allow a return value from a function but not from a subroutine. In these instances, the subroutine may be called for side effect only. As with defined functions written in C, the user must create an entry in **UserFunctions** for the subroutine (see section 3.1). An **extern** definition also must appear in the same file as the **UserFunctions** function, defining the type of data that the function will return. If the function does not return a value (Ada procedures or FORTRAN subroutines), it should be defined as returning a void value. See section 3.1 for the allowed return values for user-defined functions.

Ada Example

```
1: procedure DISPLAY is
2: -- Standard Ada definitions and declarations
3: begin
4: --
5: -- Any kind of normal Ada code may be used
6: --

•
•
•
•
•
•
7: --
8: end DISPLAY;
```

FORTRAN Example

```
subroutine display
C
C Any kind of normal FORTRAN code may be used
C
.
.
.
C
return
end
```

UserFunctions entry for either example

6.6 PASSING ARGUMENTS FROM CLIPS TO AN EXTERNAL FUNCTION

Arguments may be passed from CLIPS to an external function. CLIPS does not actually pass arguments to the function; instead arguments must be pulled from internal CLIPS buffers by using the functions described in section 3. Although the argument access functions could be called directly from Ada or FORTRAN, it probably is easier to write an interface function in C. CLIPS will call the C routine, which gathers the arguments and passes them in the proper manner to the external subprogram.

In this situation, the user must ensure argument compatibility. In particular, string variables must be converted from C arrays to FORTRAN or Ada string descriptors. The actual code used in the interface routine for argument conversion will depend on the language. Examples are given below for Ada and FORTRAN. Each example assumes the subroutine is called as follows:

```
(dummy 3.7 "An example string")
```

VMS Ada Example

Note the procedure definition in line 2 of the Ada routine. The numerical value is defined as an IN OUT type and the string as an IN. Also note the compiler PRAGMA on line 4-5. PRAGMA is DEC-Ada-specific, and a similar statement will be needed for other compilers. Following the Ada routine is an example of a C interface function that calls the Ada subroutine. The C routine must convert a C string into an Ada string descriptor using the **MakeStringDsc** (see section 6.7 for more on string conversion) function as shown in line 16 of the C routine. Note that the C function passes the *address* of the numerical parameters to the Ada subprogram (line 16) and a pointer to a descriptor for the string parameter. Note also that the **UserFunctions** definition (lines 21-24) calls the dummy C routine, not the Ada program.

```
package DUMMY_PKG is
  procedure DUMMY (Value : in out float ;
                   Name : in
                                  string);
     (The following two lines are DEC Ada specific)
  pragma EXPORT_PROCEDURE (DUMMY
                          PARAMETER_TYPES => (float, string));
end DUMMY_PKG;
-- Ada interface to CLIPS internal functions, see Appendix A
with CLIPS_INTERNALS; use CLIPS_INTERNALS;
PACKAGE Dummy_PKG IS
package body DUMMY_PKG is
 procedure DUMMY (Value : in out float ;
                  Name : in
                                 string) is
  begi n
   Value and Name may be used as normal Ada variables.
   Name should not be modified by this procedure since
   it has a direct pointer to a CLIPS C string.
  end DUMMY;
end DUMMY_PKG;
```

C interface routine

```
#include <stdio.h>
#include "clips.h"
   (The following two lines are VAX VMS specific)
#include <descrip.h>
struct dsc$descriptor_s *MakeStringDsc();
c_dummy()
   double value:
   char *name;
   extern int dummy();
   value = RtnDouble(1);
   name = RtnLexeme(2);
  dummy(&value, MakeStringDsc(name));
  return(0);
  }
UserFunctions()
  DefineFunction("dummy", 'i', c_dummy, "c_dummy");
```

VMS FORTRAN Example

The VMS FORTRAN routine looks very similar to the Ada routine and, in fact, uses the same C interface function listed for VMS Ada.

```
subroutine dummy(value, name)

C

REAL value
CHARACTER *80 name

C

value and name may now be used as normal FORTRAN variables

C

return
end
```

Note that the previous two examples performed the string conversion in C, not in the language (Ada or FORTRAN) to which the string was being passed. On some machines, it may be easier to convert the string in the language (Ada or FORTRAN) to which the string is being passed rather than in the language (C) from which the string is being passed.

6.7 STRING CONVERSION

Much of the information that needs to be passed between CLIPS and another language typically is stored as strings. The storage of string variables can differ radically between languages. Both Ada and FORTRAN use a special (machine-dependent) string descriptor for string data types, whereas C uses simple arrays. Because of this difference, special functions must be defined to convert FORTRAN or Ada strings to C strings and back. The implementation of these functions will be different for every language and computer. Typically, two functions are needed: one to convert an Ada or a FORTRAN string to a C string, and one to convert a C string to an Ada or a FORTRAN string descriptor. When converting C strings that have been provided by CLIPS to strings suitable for other languages, *do not* modify the original C string. The following table shows the string conversion routines provided in the interface packages in appendix A.

Environment	Function to Convert TO a C string	Function to Convert FROM a C string	
VMS Ada	ADA_TO_C_STRING	MakeStringDsc	
VMS FORTRAN	CONVERT_TO_C_STRING	MakeStringDsc	

The interface package does all of the converting from Ada or FORTRAN strings to C strings. Users will have to convert from C when defining functions that are passed parameters from CLIPS. Appendix A.3 has a listing for a function that will convert C strings to Ada or FORTRAN character strings under VAX VMS.

6.8 COMPILING AND LINKING

After all routines are defined, they must be compiled and linked to execute. The manner of compilation will depend on the machine on which the user is working. Two examples are given below: one for VMS Ada and one for VMS FORTRAN.

6.8.1 VMS Ada Version

1) Copy all of the CLIPS include files and Ada interface package to the user directory.

```
$copy [{CLIPS master directory}]*.h [{user directory}]
$copy [{CLIPS master directory}]*.ada [{user directory}]
```

2) Create an object file from the file holding the **UserFunctions** definition.

\$cc usrfuncs.c

3) Set up the Ada library and compile the Ada routine(s).

\$acs create library [{user directory}.adalib]
\$acs set library [{user directory}.adalib]
\$ada {Ada files, including the interface packages}

4) Export the Ada object code from the DEC ACS library.

\$acs export/main {Ada files, including the interface package}

5) Define the link libraries and link all of the files together. Note that, prior to linking, each user must define the standard link libraries with the **define lnk\$library** command. This usually is done once in the **login.com** file during login. This definition may be different for each VMS system.

\$link/executable={exec name} {Ada files}, usrfuncs, [{CLIPS master directory}] clipslib/library

This will create an embedded version of CLIPS using an Ada routine as the main program. To create a program that uses the CLIPS interface but calls Ada subprograms, modify step 4 to read

\$acs export {user's Ada packages}

5) Copy the CLIPS **main.c** file from the CLIPS master directory and remove the **UserFunctions** definition from the CLIPS **main.c** routine. Then recompile

\$cc main

6) Link with the following command:

\$link/executable={exec name} {Ada files}, main, usrfuncs, [{CLIPS master directory}] clipslib/library

6.8.2 VMS FORTRAN Version

1) Copy all of the CLIPS include files to the user directory.

\$copy [{CLIPS master directory}]*.h [{user directory}]

2) Create an object file from the file holding the **UserFunctions** definition.

\$cc usrfuncs.c

3) Compile the FORTRAN routine(s).

\$fortran {FORTRAN files}

4) Link all of the files together.

\$link/executable={exec name} {FORTRAN files}, usrfuncs, [{CLIPS master directory}] clipslib/library, clipsforlib/library

Note that one of the FORTRAN programs *must* be a main program.

6.8.3 CLIPS Library

All of the previous examples assume a CLIPS library has been created on the user's machine. A CLIPS library can be made with any standard object code library program and should include all of the CLIPS object code files *except* the **main.c** file. A library also may be made for the interface packages.

6.9 BUILDING AN INTERFACE PACKAGE

To develop an interface package for CLIPS and FORTRAN, Ada, or any other language, the primary need is the string conversion routines. Once these have been developed, the rest of the interface package should look very similar to the examples shown in appendices A.1 to A.3. The majority of the conversion work should be done in the interface package. Note that if a CLIPS function takes no arguments then it is not necessary to write an interface function for it. For example, the function ListFacts takes no arguments and has no return value and can therefore be called directly (however, some languages, such as Ada, will require the function to be declared). The Ada listing in appendix A.1 use pragmas to map the C ListFacts function to the Ada xListFacts function (for consistency with the other functions which are proceeded by an x). The FORTRAN listings in appendix A include interface routines to function which do not require them as well. The functions listed in appendix A also directly mimic the equivalent C functions. That is, functions which return the integer 0 or 1 in C have the exact same value returned by their Ada and FORTRAN counterparts (rather than a boolean or logical value). It would normally be more useful to directly map these integers values into their boolean counterparts (TRUE or FALSE) in the other language.

Section 7 - I/O Router System

The **I/O router** system provided in CLIPS is quite flexible and will allow a wide variety of interfaces to be developed and easily attached to CLIPS. The system is relatively easy to use and is explained fully in sections 7.1 through 7.4. The CLIPS I/O functions for using the router system are described in sections 7.5 and 7.6, and finally, in appendix B, some examples are included which show how I/O routing could be used for simple interfaces.

7.1 INTRODUCTION

The problem that originally inspired the idea of I/O routing will be considered as an introduction to I/O routing. Because CLIPS was designed with portability as a major goal, it was not possible to build a sophisticated user interface that would support many of the features found in the interfaces of commercial expert system building tools. A prototype was built of a semi-portable interface for CLIPS using the CURSES screen management package. Many problems were encountered during this effort involving both portability concerns and CLIPS internal features. For example, every statement in the source code which used the C print function, **printf**, for printing to the terminal had to be replaced by the CURSES function, **wprintw**, which would print to a window on the terminal. In addition to changing function call names, different types of I/O had to be directed to different windows. The tracing information was to be sent to one window, the command prompt was to appear in another window, and output from printout statements was to be sent to yet another window.

This prototype effort pointed out two major needs: First, the need for generic I/O functions that would remain the same regardless of whether I/O was directed to a standard terminal interface or to a more complex interface (such as windows); and second, the need to be able to specify different sources and destinations for I/O. I/O routing was designed in CLIPS to handle these needs. The concept of I/O routing will be further explained in the following sections.

7.2 LOGICAL NAMES

One of the key concepts of I/O routing is the use of **logical names**. An analogy will be useful in explaining this concept. Consider the Acme company which has two computers: computers X and Y. The Acme company stores three data sets on these two computers: a personnel data set, an accounting data set, and a documentation data set. One of the employees, Joe, wishes to update the payroll information in the accounting data set. If the payroll information was located in directory A on computer Y, Joe's command would be

update Y: [A] payroll

If the data were moved to directory B on computer X, Joe's command would have to be changed to

```
update X: [B] payroll
```

To update the payroll file, Joe must know its location. If the file is moved, Joe must be informed of its new location to be able to update it. From Joe's point of view, he does not care where the file is located physically. He simply wants to be able to specify that he wants the information from the accounting data set. He would rather use a command like

```
update accounting: payroll
```

By using logical names, the information about where the accounting files are located physically can be hidden from Joe while still allowing him to access them. The locations of the files are equated with logical names as shown here.

```
accounting = X: [A]
documentation = X: [C]
personnel = Y: [B]
```

Now, if the files are moved, Joe does not have to be informed of their relocation so long as the logical names are updated. This is the power of using logical names. Joe does not have to be aware of the physical location of the files to access them; he only needs to be aware that accounting is the logical name for the location of the accounting data files. Logical names allow reference to an object without having to understand the details of the implementation of the reference.

In CLIPS, logical names are used to send I/O requests without having to know which device and/or function is handling the request. Consider the message that is printed in CLIPS when rule tracing is turned on and a rule has just fired. A typical message would be

```
FIRE 1 example-rule: f-0
```

The routine that requests this message be printed should not have to know where the message is being sent. Different routines are required to print this message to a standard terminal, a window interface, or a printer. The tracing routine should be able to send this message to a logical name (for example, **trace-out**) and should not have to know if the device to which the message is being sent is a terminal or a printer. The logical name **trace-out** allows tracing information to be sent simply to "the place where tracing information is displayed." In short, logical names allow I/O requests to be sent to specific locations without having to specify the details of how the I/O request is to be handled.

Many functions in CLIPS make use of logical names. Both the **printout** and **format** functions require a logical name as their first argument. The **read** function can take a logical name as an optional argument. The **open** function causes the association of a logical name with a file, and the **close** function removes this association.

Several logical names are predefined by CLIPS and are used extensively throughout the system code. These are

Name	Description		
stdin	The default for all user inputs. The read and readline functions		
	read from stdin if t is specified as the logical name.		
stdout	The default for all user outputs. The format and printout functions		
	send output to stdout if t is specified as the logical name.		
wprompt	The CLIPS prompt is sent to this logical name.		
wdialog	All informational messages are sent to this logical name.		
wdisplay	Requests to display CLIPS information, such as facts or rules, are sent to this logical name.		
werror	All error messages are sent to this logical name.		
wwarning	All warning messages are sent to this logical name.		
wtrace	All watch information is sent to this logical name (with the exception of compilations which is sent to wdialog).		
	one of the interior of the int		

7.3 ROUTERS

The use of logical names has solved two problems. Logical names make it easy to create generic I/O functions, and they allow the specification of different sources and destinations for I/O. The use of logical names allows CLIPS to ignore the specifics of an I/O request. However, such requests must still be specified at some level. I/O routers are provided to handle the specific details of a request.

A router consists of three components. The first component is a function which can determine whether the router can handle an I/O request for a given logical name. The router which recognizes I/O requests that are to be sent to the serial port may not recognize the same logical names as that which recognizes I/O requests that are to be sent to the terminal. On the other hand, two routers may recognize the same logical names. A router that keeps a log of a CLIPS session (a dribble file) may recognize the same logical names as that which handles I/O requests for the terminal.

The second component of a router is its priority. When CLIPS receives an I/O request, it begins to question each router to discover whether it can handle an I/O request. Routers with high priorities are questioned before routers with low priorities. Priorities are very important when dealing with one or more routers that can each process the same I/O request. This is particularly true when a router is going to redefine the standard user interface. The router associated with the standard interface will handle the same I/O requests as the new router; but, if the new router is given a higher priority, the standard router will never receive any I/O requests. The new router will "intercept" all of the I/O requests. Priorities will be discussed in more detail in the next section.

The third component of a router consists of the functions which actually handle an I/O request. These include functions for printing strings, getting a character from an input buffer, returning a character to an input buffer, and a function to clean up (e.g., close files, remove windows) when CLIPS is exited.

7.4 ROUTER PRIORITIES

Each I/O router has a priority. Priority determines which routers are queried first when determining the router that will handle an I/O request. Routers with high priorities are queried before routers with low priorities. Priorities are assigned as integer values (the higher the integer, the higher the priority). Priorities are important because more than one router can handle an I/O request for a single logical name, and they enable the user to define a custom interface for CLIPS. For example, the user could build a custom router which handles all logical names normally handled by the default router associated with the standard interface. The user adds the custom router with a priority higher than the priority of the router for the standard interface. The custom router will then intercept all I/O requests intended for the standard interface and specially process those requests to the custom interface.

Once the router system sends an I/O request out to a router, it considers the request satisfied. If a router is going to share an I/O request (i.e., process it) then allow other routers to process the request also, that router must deactivate itself and call **PrintRouter** again. These types of routers should use a priority of either 30 or 40. An example is given in appendix B.2.

Priority 50	Router Description Any router that uses "unique" logical names and does not want to share I/O with catch-all routers.
40	Any router that wants to grab standard I/O and is willing to share it with other routers. A dribble file is a good example of this type of router. The dribble file router needs to grab all output that normally would go to the terminal so it can be placed in the dribble file, but this same output also needs to be sent to the router which displays output on the terminal.

30	Any router that uses "unique" logical names and is willing to share I/O with catch-all routers.
20	Any router that wants to grab standard logical names and is not willing to share them with other routers.
10	This priority is used by a router which redefines the default user interface I/O router. Only one router should use this priority.
0	This priority is used by the default router for handling standard and file logical names. Other routers should not use this priority.

7.5 INTERNAL I/O FUNCTIONS

The following functions are called internally by CLIPS. These functions search the list of active routers and determine which router should handle an I/O request. Some routers may wish to deactivate themselves and call one of these functions to allow the next router to process an I/O request. Prototypes for these functions can be included by using the **clips.h** header file or the **router.h** header file.

7.5.1 ExitRouter

```
void ExitRouter(exitCode);
int exitCode;
```

Purpose: The function ExitRouter calls the exit function associated with

each active router before exiting CLIPS.

Arguments: The *exitCode* argument corresponds to the value that normally

would be sent to the system exit function. Consult a C system

manual for more details on the meaning of this argument.

Returns: No meaningful return value.

Info: The function **ExitRouter** calls the system function **exit** with the

argument num after calling all exit functions associated with I/O

routers.

7.5.2 GetcRouter

```
int GetcRouter(logicalName);
char *logicalName;
```

Purpose: The function **GetcRouter** queries all active routers until it finds a

router that recognizes the logical name associated with this I/O request to get a character. It then calls the get character function asso-

ciated with that router.

Arguments: The logical name associated with the get character I/O request.

Returns: An integer; the ASCII code of the character.

Info: This function should be used by any user-defined function in place

of **getc** to ensure that character input from the function can be received from a custom interface. On machines which default to unbuffered I/O, user code should be prepared to handle special

characters like the backspace.

7.5.3 PrintRouter

```
int PrintRouter(logical Name, str);
char *logical Name, *str;
```

Purpose: The

The function **PrintRouter** queries all active routers until it finds a router that recognizes the logical name associated with this I/O request to print a string. It then calls the print function associated with

that router.

Arguments: 1) The logical name associated with the location at which the string

is to be printed.

2) The string that is to be printed.

Returns: Returns a non-zero value if the logical name is recognized,

otherwise it returns zero.

Info: This function should be used by any user-defined function in place

of **printf** to ensure that output from the function can be sent to a

custom interface.

7.5.4 UngetcRouter

```
int UngetcRouter(ch, logical Name);
int ch;
char *logical Name;
```

Purpose: The function **UngetcRouter** queries all active routers until it finds a

router that recognizes the logical name associated with this I/O request. It then calls the ungetc function associated with that router.

Arguments: 1) The ASCII code of the character to be returned.

2) The logical name associated with the ungetc character I/O

request.

Returns: Returns *ch* if successful, otherwise -1.

Info: This function should be used by any user-defined function in place

of **UngetcRouter** to ensure that character input from the function can be received from a custom interface. As with **GetcRouter**, user code should be prepared to handle special characters like the

backspace on machines with unbuffered I/O.

7.6 ROUTER HANDLING FUNCTIONS

The following functions are used for creating, deleting, and handling I/O routers. They are intended for use within user-defined functions. Prototypes for these functions can be included by using the **clips.h** header file or the **router.h** header file.

7.6.1 ActivateRouter

int ActivateRouter(routerName);
char *routerName;

Purpose: The function **ActivateRouter** activates an existing I/O router. This

router will be queried to see if it can handle an I/O request. Newly

created routers do not have to be activated.

Arguments: The name of the I/O router to be activated.

Returns: Returns a non-zero value if the logical name is recognized,

otherwise it returns zero.

7.6.2 AddRouter

Purpose:

The function **AddRouter** adds a new I/O router to the list of I/O routers.

Arguments:

- 1) The name of the I/O router. This name is used to reference the router by the other I/O router handling functions.
- 2) The priority of the I/O router. I/O routers are queried in descending order of priorities.
- 3) A pointer to the query function associated with this router. This query function should accept a single argument, a logical name, and return either TRUE (1) or FALSE (0) depending upon whether the router recognizes the logical name.
- 4) A pointer to the print function associated with this router. This print function should accept two arguments: a logical name and a character string. The return value of the print function is not meaningful.
- 5) A pointer to the get character function associated with this router. The get character function should accept a single argument, a logical name. The return value of the get character function should be an integer which represents the character or end of file (EOF) read from the source represented by logical name.
- 6) A pointer to the ungete character function associated with this router. The ungete character function accepts two arguments: a logical name and a character. The return value of the unget character function should be an integer which represents the character which was passed to it as an argument if the ungete is successful or end of file (EOF) is the ungete is not successful.

7) A pointer to the exit function associated with this router. The exit function should accept a single argument: the exit code represented by num.

Returns: Returns a zero value if the router could not be added, otherwise a

non-zero value is returned.

Info: I/O routers are active upon being created. See the examples in ap-

pendix B for further information on how to use this function.

7.6.3 DeactivateRouter

int DeactivateRouter(routerName);
char *routerName;

Purpose: The function **DeactivateRouter** deactivates an existing I/O router.

This router will not be queried to see if it can handle an I/O request.

The syntax of the **DeactivateRouter** function is as follows.

Arguments: The name of the I/O router to be deactivated.

Returns: Returns a non-zero value if the logical name is recognized,

otherwise it returns zero.

7.6.4 DeleteRouter

int DeleteRouter(routerName);
char *routerName;

Purpose: The function **DeleteRouter** removes an existing I/O router from the

list of I/O routers.

Arguments: The name of the I/O router to be deleted.

Returns: Returns a non-zero value if the logical name is recognized,

otherwise it returns zero.

Section 8 - Memory Management

Efficient use of memory is a very important aspect of an expert system tool. Expert systems are highly memory intensive and require comparatively large amounts of memory. To optimize both storage and processing speed, CLIPS does much of its own memory management. Section 8.1 describes the basic memory management scheme used in CLIPS. Section 8.2 describes some functions that may be used to monitor/ control memory usage.

8.1 HOW CLIPS USES MEMORY

The CLIPS internal data structures used to represent constructs and other data entities require the allocation of dynamic memory to create and execute. Memory can also be released as these data structures are no longer needed and are removed. All requests, either to allocate memory or to free memory, are routed through the CLIPS memory management functions. These functions request memory from the operating system and store previously used memory for reuse. By providing its own memory management, CLIPS is able to reduce the number of **malloc** calls to the operating system. This is very important since **malloc** calls are handled differently on each machine, and some implementations of **malloc** are very inefficient.

When new memory is needed by any CLIPS function, CLIPS first checks its own data buffers for a pointer to a free structure of the type requested. If one is found, the stored pointer is returned. Otherwise, a call is made to **malloc** for the proper amount of data and a new pointer is returned.

When a data structure is no longer needed, CLIPS saves the pointer to that memory against the next request for a structure of that type. Memory actually is released to the operating system only under limited circumstances. If a **malloc** call in a CLIPS function returns NULL, *all* free memory internally stored by CLIPS is released to the operating system and the **malloc** call is tried again. This usually happens during rule execution, and the message

*** DEALLOCATING MEMORY ***

*** MEMORY DEALLOCATED ***

will be printed out to the **wdialog** stream. Users also may force memory to be released to the operating system (see section 8.2).

CLIPS uses the generic C function **malloc** to request memory. Some machines provide lower-level memory allocation/deallocation functions that are considerably faster than **malloc**. Generic CLIPS memory allocation and deallocation functions are stored in the **memory.c** file and are called **genalloc** and **genfree**. The call to **malloc** and **free** in these functions could be replaced to improve performance on a specific machine.

Some machines have very inefficient memory management services. When running on the such machines, CLIPS can be made to request very large chunks of memory and internally allocate smaller chunks of memory from the larger chunks. This technique bypasses numerous calls to **malloc** thus improving performance. This behavior can be enabled by setting the BLOCK_MEMORY compiler option in the **setup.h** header file to 1 (see section 2.2). In general, this option should not be enabled unless memory allocation routines are very slow since the CLIPS block memory routines tend to trade increased overhead for memory requests for faster speed.

Extensive effort has gone into making CLIPS garbage free. Theoretically, if an application can fit into the available memory on a machine, CLIPS should be able to run it forever. Of course, user-defined functions that use dynamic memory may affect this.

8.2 STANDARD MEMORY FUNCTIONS

CLIPS currently provides a few functions that can be used to monitor and control memory usage. Prototypes for these functions can be included by using the **clips.h** header file or the **memalloc.h** header file.

8.2.1 GetConserveMemory

int GetConserveMemory();

Purpose: Returns the current value of the conserve memory behavior.

Arguments: None.

Returns: An integer; FALSE (0) if the behavior is disabled and TRUE (1) if

the behavior is enabled.

8.2.2 MemRequests

long int MemRequests();

Purpose: The function **MemRequests** will return the number of times CLIPS

has requested memory from the operating system (the C equivalent

of the CLIPS **mem-requests** command).

Arguments: None.

Returns: A long integer representing the number of requests CLIPS has

made.

Other:

When used in conjunction with **MemoryUsed**, the user can estimate the number of bytes CLIPS requests per call to **malloc**.

8.2.3 MemUsed

long int MemUsed();

Purpose: The function **MemUsed** will return the number of bytes CLIPS has

currently in use or has held for later use (the C equivalent of the

CLIPS mem-used command).

Arguments: None.

Returns: A long integer representing the number of bytes requested.

Other: The number of bytes used does not include any overhead for

memory management or data creation. It does include all free memory being held by CLIPS for later use; therefore, it is not a completely accurate measure of the amount of memory actually used to store or process information. It is used primarily as a

minimum indication.

8.2.4 ReleaseMem

long int ReleaseMem(howMuch, printMessage);
long int howMuch;
int printMessage;

Purpose:

The function **ReleaseMem** will cause all free memory, or a specified amount, being held by CLIPS to be returned to the operating system (the C equivalent of the CLIPS **release-mem**

command).

Arguments: 1) The number of bytes to be released. If this argument is -1, all

memory will be released; otherwise, the specified number of

bytes will be released.

2) A non-zero value causes a memory deallocation message to be

printed when this function is called.

Returns: A long integer representing the actual amount of memory freed to

the operating system.

Other:

This function can be useful if a user-defined function requires memory but cannot get any from a **malloc** call. However, it should be used carefully. Excessive calls to **ReleaseMemory** will cause CLIPS to call **malloc** more often, which can reduce the performance of CLIPS.

8.2.5 SetConserveMemory

int SetConserveMemory(value);
int value:

Purpose:

The function **SetConserveMemory** allows a user to turn on or off the saving of pretty print information. Normally, this information is saved. If constructs are never going to be pretty printed or saved, a significant amount of memory can be saved by not keeping the pretty print representation.

Arguments:

A boolean value: FALSE (0) to keep pretty print information for newly loaded constructs and TRUE (1) to not keep this information for newly loaded constructs.

Returns:

Returns the old value for the behavior.

Other:

This function can save considerable memory space. It should be turned on before loading any constructs. It can be turned on or off as many times as desired. Constructs loaded while this is turned off can be displayed only by reloading the construct, even if the option is turned on subsequently.

8.2.6 SetOutOfMemoryFunction

```
int (*SetOutOfMemoryFunction(outOfMemoryFunction))();
int (*outOfMemoryFunction)();
int outOfMemoryFunction(size);
int size;
```

Purpose:

Allows the user to specify a function to be called when CLIPS cannot satisfy a memory request.

Arguments:

A pointer to the function to be called when CLIPS cannot satisfy a memory request. This function is passed the size of the memory request which could not be satisfied. It should return a non-zero value if CLIPS should not attempt to allocate the memory again

(and exit because of lack of available memory) or a zero value if CLIPS should attempt to allocate memory again.

Returns: Returns a pointer to the previously called out of memory function.

Other: Because the out of memory function can be called repeatedly for a

single memory request, any user-defined out of memory function

should return zero only if it has released memory.

Appendix A - Language Integration Listings

This appendix includes listings for various language interface packages described in section 6. The portability of these routines varies. Most of the code listed in the interface packages defined in sections A.1 and A.2 should be fairly portable. However, the string conversion routine in section A.3 is not as portable. For example, the Ada function **Convert_to_C_String** is probably portable to any Ada machine, yet the C function **MakeStringDsc** listed here is very specific to the DEC VMS. These functions should be typed in exactly as shown below.

A.1 ADA INTERFACE PACKAGE FOR CLIPS

The following listings are an Ada package specification and body for some of the CLIPS functions used in embedded CLIPS systems. The code is specific to the DEC Ada compiler because of the PRAGMA IMPORT_PROCEDURE. Other Ada compilers may provide a similar capability, and this package specification could be modified.

CLIPS Package Specification

```
package CLIPS is
 ______
-- Initializes the CLIPS environment upon program startup.
 procedure xInitializeEnvironment;
       -- Resets the CLIPS environment.
 procedure xReset;
      ______
-- Loads a set of constructs into the CLIPS database. If there are syntactic
-- error in the constructs, xLoad will still attempt to read the
-- entire file, and error notices will be sent to werror.
-- Returns: an integer, zero if an error occurs.
 function xLoad (File_Name : in string) return integer;
______
-- Allows Run_Limit rules to fire (execute).
-- -1 allows rules to fire until the agenda is empty.
-- Returns: Number of rules that were fired.
 function xRun (Run_Limit : in integer := -1) return integer;
-- Lists the facts in the fact-list.
 procedure xFacts (Logical_Name : in string;
                Module_Ptr : in integer;
                First: in integer;
                Last: in integer;
                Max : in integer);
-- Turns the watch facilities of CLIPS on.
```

```
function xWatch (Watch_Item : in string) return integer;
______
-- Turns the watch facilities of CLIPS off.
 function xUnwatch (Watch_Item : in string) return integer;
-- Asserts a fact into the CLIPS fact-list. The function version
-- returns the Fact_Pointer required by xRetractFact.
 function xAssertString (Pattern: in string) return integer;
-- Causes a fact asserted by the ASSERT_FACT function to be retracted.
-- Returns: false if fact has already been retracted, else true.
-- Input of any value not returned by ASSERT_FACT will
-- cause CLIPS to abort.
 function xRetract (Fact_Pointer : in integer) return integer;
______
-- Queries all active routers until it finds a router that
-- recognizes the logical name associated with this I/O request
-- to print a string. It then calls the print function associated
-- with that router.
 function xPrintRouter (Log_Name : in string ;
           Str : in string) return integer;
-- Removes a rule from CLIPS.
-- Returns: false if rule not found, else true.
 function xUndefrule (Rule_Name : in string) return integer;
pri vate
 pragma INTERFACE (C, xInitializeEnvironment);
 pragma IMPORT_PROCEDURE (INTERNAL => xInitializeEnvironment,
                     EXTERNAL => InitializeEnvironment);
 pragma INTERFACE (C, xReset);
 pragma IMPORT_PROCEDURE (INTERNAL => xReset,
                     EXTERNAL => Reset);
 function cLoad (File_Name : in string) return integer;
 pragma INTERFACE (C, cLoad);
 pragma IMPORT_FUNCTION (INTERNAL => cLoad,
                    EXTERNAL => Load,
                    MECHANISM => REFERENCE);
 pragma INTERFACE (C, xRun);
 pragma IMPORT_FUNCTION (INTERNAL => xRun,
                    EXTERNAL => Run,
                    MECHANISM => VALUE);
 procedure cFacts(Logical_Name : in string;
               Module_Ptr : in integer;
               First: in integer;
               Last: in integer;
```

```
Max : in integer);
  pragma INTERFACE (C, cFacts);
  pragma IMPORT_PROCEDURE (INTERNAL => cFacts,
                           EXTERNAL => Facts,
                           MECHANISM => (REFERENCE, VALUE,
                                          VALUE, VALUE, VALUE));
  function cWatch (Item: in string) return integer;
  pragma INTERFACE (C, cWatch);
  pragma IMPORT_FUNCTION (INTERNAL => cWatch,
                          EXTERNAL => Watch,
                          MECHANISM => REFERENCE);
  function cUnwatch (Item: in string) return integer;
  pragma INTERFACE (C, cUnwatch);
  pragma IMPORT_FUNCTION (INTERNAL => cUnwatch,
                          EXTERNAL => Unwatch,
                          MECHANISM => REFERENCE);
  function cAssertString (Pattern : in string) return integer;
  pragma INTERFACE (C, cAssertString);
  pragma IMPORT_FUNCTION (INTERNAL => cAssertString,
                          EXTERNAL => AssertString,
                          MECHANISM => REFERENCE);
  function cRetract (Fact_Pointer: in integer) return integer;
  pragma INTERFACE (C, cRetract);
  pragma IMPORT_FUNCTION (INTERNAL => cRetract,
                          EXTERNAL => Retract,
                          MECHANISM => VALUE);
  function cPrintRouter (Log_Name : in string ;
                        Str : in string) return integer;
  pragma INTERFACE (C, cPrintRouter);
  pragma IMPORT_FUNCTION (INTERNAL => cPrintRouter,
                           EXTERNAL => PrintRouter,
                           MECHANISM => REFERENCE);
  function cUndefrule (Rule_Name : in string) return integer;
  pragma INTERFACE (C, cUndefrule);
  pragma IMPORT_FUNCTION (INTERNAL => cUndefrule,
                          EXTERNAL => Undefrule,
                          MECHANISM => REFERENCE);
end CLIPS;
CLIPS Package Body
package body CLIPS is
 function ADA_TO_C_STRING (Input_String : in string)
           return string is
    Out_String : string (1..Input_String'LAST+1);
  begi n
```

```
for I in Input_String' RANGE loop
    if (Input_String (Ĭ) in ' '... '~' or
        Input\_String(I) = ASCII.Cr
                                    ) then
        Input\_String(I) = ASCII.Lf
      Out_String (I) := Input_String (I);
    else
      Out_String (I) := ASCII.Nul;
    end if;
  end loop;
  Out_String (Out_String'LAST) := ASCII.Nul;
  return Out_String;
 end ADA_TO_C_STRING;
function xLoad (File_Name : in string) return integer is
begi n
  return \ cLoad \ (ADA\_TO\_C\_STRING \ (File\_Name));
 end xLoad;
procedure xFacts (Logical_Name : in string;
                  Module_Ptr : in integer;
                  First: in integer;
                  Last : in integer;
                  Max: in integer) is
begi n
  cFacts (ADA_TO_C_STRING (Logical_Name), Module_Ptr, First, Last, Max);
end xFacts;
function xWatch (Watch_Item : in string) return integer is
begi n
  return cWatch (ADA_TO_C_STRING (Watch_Item));
end xWatch;
______
function xUnwatch (Watch_Item: in string) return integer is
begin
  return cUnwatch (ADA_TO_C_STRING (Watch_Item));
end xUnwatch;
function xAssertString (Pattern: in string) return integer is
  return cAssertString (ADA_TO_C_STRING (Pattern));
```

```
end xAssertString;
 function xRetract (Fact_Pointer: in integer) return integer is
 begi n
   return cRetract (Fact_Pointer);
 end xRetract;
 function xPrintRouter (Log_Name : in string ;
                       : in string ) return integer is
                   Str
 begi n
   return cPrintRouter (ADA_TO_C_STRING (Log_Name),
                   ADA_TO_C_STRING (Str));
 end xPrintRouter;
-----
 function xUndefrule (Rule_Name : in string) return integer is
 begi n
   return cUndefrule (ADA_TO_C_STRING (Rule_Name));
 end xUndefrule;
end CLIPS;
```

A.2 FORTRAN INTERFACE PACKAGE FOR VAX VMS

The following pages are listings of the FORTRAN interface functions for the VAX VMS plus the internal functions used to convert FORTRAN character strings to C character strings and vice versa. Many of these functions may work with minor modifications on other machines; note, however, the use of the VMS argument passing modifier, %VAL, in some functions.

```
C
     INTEGER FUNCTION xLoad (FILE_NAME)
     CHARACTER * (*) FILE_NAME
     CHARACTER *80 C_FILE_NAME
     INTEGER C_FILE_NAME_POINTER, Load
     EQUIVALENCE (C_FILE_NAME, C_FILE_NAME_POINTER)
     CALL CONVERT_TO_C_STRING (FILE_NAME, C_FILE_NAME)
     xLoad = Load (C_FILE_NAME_POINTER)
     RETURN
     END
C
C-
C
     INTEGER FUNCTION xRun (RUN_LIMIT)
     INTEGER RUN_LIMIT, Run
     xRun = Run (\%VAL (RUN_LIMIT))
     RETURN
     END
C
C-
C
     SUBROUTINE xFacts (LOGICAL_NAME, MODULE, BEGIN, END, MAX)
     CHARACTER * (*) LOGICAL_NAME
     INTEGER MODULE, BEGIN, END, MAX
     CHARACTER *80 C_LOGICAL_NAME
     INTEGER C_LOGICAL_NAME_POINTER
     EQUIVALENCE (C_LOGICAL_NAME, C_LOGICAL_NAME_POINTER)
     CALL CONVERT_TO_C_STRING (LOGICAL_NAME, C_LOGICAL_NAME)
     CALL Facts(C_LOGICAL_NAME_POINTER, %VAL (MODULE),
                %VAL (BEGIN), %VAL (END), %VAL (MAX))
     RETURN
     END
C
C-
     INTEGER FUNCTION xWatch (WATCH_ITEM)
     CHARACTER * (*) WATCH_ITEM
     CHARACTER *80 C_WATCH_ITEM
     INTEGER C_WATCH_ITEM_POINTER, Watch
     EQUIVALENCE (C_WATCH_ITEM, C_WATCH_ITEM_POINTER)
     CALL CONVERT_TO_C_STRING (WATCH_ITEM, C_WATCH_ITEM)
     xWatch = Watch (C_WATCH_ITEM_POINTER)
     RETURN
     END
C
         C
     INTEGER FUNCTION xUnwatch (WATCH_ITEM)
     CHARACTER * (*) WATCH_ITEM
```

```
CHARACTER *80 C_WATCH_ITEM
     INTEGER C_WATCH_ITEM_POINTER, Unwatch
     EQUIVALENCE (C_WATCH_ITEM, C_WATCH_ITEM_POINTER)
     CALL CONVERT_TO_C_STRING (WATCH_ITEM, C_WATCH_ITEM)
     xUnwatch = Unwatch (C_WATCH_ITEM_POINTER)
     RETURN
     END
C
C-
C
     INTEGER FUNCTION xAssertString (PATTERN)
C
     CHARACTER * (*) PATTERN
     CHARACTER *80 C_PATTERN
      INTEGER C_PATTERN_POINTER, AssertString
     EQUIVALENCE (C_PATTERN, C_PATTERN_POINTER)
C
     CALL CONVERT_TO_C_STRING (PATTERN, C_PATTERN)
     xAssertString = AssertString (C_PATTERN_POINTER)
     RETURN
     END
C
C---
C
     INTEGER FUNCTION xRetract (FACT_ADDRESS)
     INTEGER FACT_ADDRESS, Retract
     xRetract = Retract (%VAL (FACT_ADDRESS))
     RETURN
     END
C
C-
C
     INTEGER FUNCTION xPrintRouter (LOG_NAME, PRINT_LINE)
     CHARACTER * (*) LOG_NAME
     CHARACTER * (*) PRINT_LINE
      CHARACTER *80 C_LOG_NAME
     CHARACTER *80 C_PRINT_LINE
     INTEGER C_PRINT_LINE_POINTER, C_LOG_NAME_POINTER
     EQUIVALENCE (C_PRINT_LINE, C_PRINT_LINE_POINTER),
                  (C_LOG_NAME , C_LOG_NAME_POINTER )
     CALL CONVERT_TO_C_STRING (PRINT_LINE, C_PRINT_LINE)
     CALL CONVERT_TO_C_STRING (LOG_NAME, C_LOG_NAME)
     xPrintRouter = PrintRouter (C_LOG_NAME_POINTER,
                                C_PRINT_LINE_POINTER)
     RETURN
     END
C
C-
C
     INTEGER FUNCTION xFindDefrule (RULE_NAME)
     CHARACTER * (*) RULE_NAME
      CHARACTER *80 C_RULE_NAME
```

```
INTEGER C_RULE_NAME_POINTER, Undefrule
     EQUIVALENCE (C_RULE_NAME, C_RULE_NAME_POINTER)
     CALL CONVERT_TO_C_STRING (RULE_NAME, C_RULE_NAME)
     xFindDefrule = FindDefrule (C_RULE_NAME_POINTER)
     RETURN
     END
C
C-
C
     INTEGER FUNCTION xUndefrule (RULE_NAME)
     CHARACTER * (*) RULE_NAME
     CHARACTER *80 C_RULE_NAME
     INTEGER C_RULE_NAME_POINTER, Undefrule
     EQUIVALENCE (C_RULE_NAME, C_RULE_NAME_POINTER)
     CALL CONVERT_TO_C_STRING (RULE_NAME, C_RULE_NAME)
     xUndefrule = Undefrule (C_RULE_NAME_POINTER)
     RETURN
     END
C
            ______
     SUBROUTINE CONVERT_TO_C_STRING (F_STRING, C_STRING)
     CHARACTER * (*) F_STRING, C_STRING
     K = LENGTH (F_STRING)
     DO 100 I = 1, K
     C_STRING (I:I) = F_STRING (I:I)
 100 CONTINUE
     \mathbf{K} = \mathbf{K} + \mathbf{1}
     C_STRING (K: K) = CHAR (0)
     RETURN
     END
C
C-
C
     INTEGER FUNCTION LENGTH (STRING)
C
     CHARACTER * (*) STRING
C
     K = LEN (STRING)
     DO 100 I = K, 1, -1
     IF(STRING(I:I) . NE. ' ') GO TO 150
C
  100 CONTINUE
  150 CONTINUE
     LENGTH = I
     RETURN
     END
```

A.3 FUNCTION TO CONVERT C STRINGS FOR VMS ADA OR FORTRAN

This function converts a C string to an Ada string. The **MakeStringDsc** function normally is stored in the same file together with the **UserFunctions** definition and any C interface

subroutines. The function is not portable and is specific to the VAX VMS environment. The definition of Ada string descriptors is implementation dependent, and access to those definitions from C also is implementation dependent. However, a very similar function could be written for any environment that supports Ada and C.

C Function: MakeStringDsc

(Note: This function definition is VAX VMS specific)

Appendix B - I/O Router Examples

The following examples demonstrate the use of the I/O router system. These examples show the necessary C code for implementing the basic capabilities described.

B.1 DRIBBLE SYSTEM

Write the necessary functions that will divert all tracing information to the trace file named "trace.txt".

```
First of all, we need a file pointer to the dribble file which will contain
the tracing information.
#include <stdio.h>
#include "clips.h"
static FILE *TraceFP = NULL;
We want to recognize any output that is sent to the logical name "wtrace"
because all tracing information is sent to this logical name.
                                                                The recognizer
function for our router is defined below.
int FindTrace(
  char *logicalName)
   if (strcmp(logicalName, "wtrace") == 0) return(TRUE);
  return(FALSE);
  }
We now need to define a function which will print the tracing information to
our trace file. The print function for our router is defined below.
int PrintTrace(
 char *logicalName,
  char *str)
   fprintf(TraceFP, "%s", str);
When we exit CLIPS the trace file needs to be closed. The exit function for
our router is defined below.
int ExitTrace(
                                                /* unused */
 int exitCode)
   fclose(TraceFP);
```

}

```
/*
There is no need to define a get character or ungetc character function since
this router does not handle input.
A function to turn the trace mode on needs to be defined. This function will
check if the trace file has already been opened. If the file is already
open, then nothing will happen. Otherwise, the trace file will be opened and
the trace router will be created. This new router will intercept tracing
information intended for the user interface and send it to the trace file.
The trace on function is defined below.
int TraceOn()
  if (TraceFP == NULL)
      TraceFP = fopen("trace.txt", "w");
      if (TraceFP == NULL) return(FALSE);
   else
     { return(FALSE); }
   AddRouter("trace",
                                         /* Router name
                                         /* Priority
                                                             * /
             20,
             FindTrace,
                                         /* Query function
                                         /* Print function
             PrintTrace,
                                                             */
             NULL,
                                         /* Getc function
                                                             */
             NULL,
                                         /* Ungetc function */
                                         /* Exit function
             ExitTrace);
  return(TRUE);
A function to turn the trace mode off needs to be defined. This function
will check if the trace file is already closed. If the file is already
closed, then nothing will happen. Otherwise, the trace router will be
deleted and the trace file will be closed. The trace off function is defined
below.
*/
int TraceOff()
   if (TraceFP != NULL)
      Del eteRouter("trace");
      if (fclose(TraceFP) == 0)
         TraceFP = NULL;
         return(TRUE);
        }
    }
  TraceFP = NULL;
   return(FALSE);
```

B.2 BETTER DRIBBLE SYSTEM

Modify example 1 so the tracing information is sent to the terminal as well as to the trace dribble file.

```
This example requires a modification of the PrintTrace function. After the
trace string is printed to the file, the trace router must be deactivated.
The trace string can then be sent through the PrintRouter function so that
the next router in line can handle the output. After this is done, then the
trace router can be reactivated.
*/
int PrintTrace(
  char *logicalName,
  char *str)
   fprintf(TraceFP, "%s", str);
   DeactivateRouter("trace");
   PrintRouter(logical Name, str);
   ActivateRouter("trace");
  }
/*
The TraceOn function must also be modified. The priority of the router
should be 40 instead of 20 since the router passes the output along to other
routers.
int TraceOn()
   if (TraceFP == NULL)
      TraceFP = fopen("trace.txt", "w");
```

```
if (TraceFP == NULL) return(FALSE);
  }
else
  { return(FALSE); }
AddRouter("trace",
                                      /* Router name
                                                         */
                                      /* Priority
          40.
                                     /* Query function
          FindTrace,
                                     /* Print function */
          PrintTrace,
                                     /* Getc function
                                                         */
          NULL,
                                     /* Ungetc function */
          NULL,
          ExitTrace);
                                     /* Exit function
return(TRUE);
```

B.3 BATCH SYSTEM

Write the necessary functions that will allow batch input from the file "batch.txt" to the CLIPS top-level interface.

```
First of all, we need a file pointer to the batch file which will contain
the batch command information.
#include <stdio.h>
#include "clips.h"
static FILE *BatchFP = NULL;
We want to recognize any input requested from the logical name "stdin"
because all user input is received from this logical name. The recognizer
function for our router is defined below.
int FindMybatch(
  char *logicalName)
   if (strcmp(logicalName, "stdin") == 0) return(TRUE);
   return(FALSE);
  }
We now need to define a function which will get and unget characters from our
batch file. The get and ungetc character functions for our router are
defined below.
static char BatchBuffer[80];
static int BatchLocation = 0;
int GetcMybatch(
  char *logical Name)
```

```
int rv;
   rv = getc(BatchFP);
   if (rv == E0F)
      DeleteRouter("mybatch");
      fclose(BatchFP);
      return(GetcRouter(logical Name));
   BatchBuffer[BatchLocation] = (char) rv;
   BatchLocation++;
   BatchBuffer[BatchLocation] = EOS;
   if((rv == ' \ n') | (rv == ' \ r'))
      PrintRouter("wprompt", BatchBuffer);
      BatchLocation = 0;
   return(rv);
int UngetcMybatch(
  int ch,
  char *logicalName)
                                                 /* unused */
  {
   if (BatchLocation > 0) BatchLocation--;
   BatchBuffer[BatchLocation] = EOS;
   return(ungetc(ch, BatchFP));
/*
When we exit CLIPS the batch file needs to be closed. The exit function for
our router is defined below.
int ExitMybatch(
  int exitCode)
                                                 /* unused */
   fclose(BatchFP);
There is no need to define a print function since this router does not handle
output except for echoing the command line.
Now we define a function that turns the batch mode on.
* /
int MybatchOn()
   BatchFP = fopen("batch.txt", "r");
   if (BatchFP == NULL) return(FALSE);
   AddRouter("mybatch",
                                         /* Router name
```

```
/* Priority
               20,
                                          /* Query function */
              FindMybatch,
                                         /* Print function
               NULL,
                                       /* Getc function */
/* Ungetc function */
               GetcMybatch,
              UngetcMybatch,
                                         /* Exit function
              Exi t Mybatch);
   return(TRUE);
 }
Now add the definition for this function to the UserFunctions function in
file "main.c".
* /
extern int MybatchOn();
DefineFunction("mybatch", 'b', MybatchOn, "MybatchOn");
Compile and link the appropriate files. The batch function should now be
accessible within CLIPS as external function. For Example
   CLIPS> (mybatch)
```

B.4 SIMPLE WINDOW SYSTEM

Write the necessary functions using CURSES (a screen management function available in UNIX) that will allow a top/bottom split screen interface. Output sent to the logical name **top** will be printed in the upper window. All other screen I/O should go to the lower window. (NOTE: Use of CURSES may require linking with special libraries.)

```
First of all, we need some pointers to the windows and a flag to indicate
that the windows have been initialized.
#include <stdio.h>
#include <curses>
#include "clips.h"
WI NDOW *LowerWi ndow, *UpperWi ndow;
int WindowInitialized = FALSE;
/*
We want to intercept any I/0 requests that the standard interface would
handle. In addition, we also need to handle requests for the logical name
     The recognizer function for our router is defined below.
top.
*/
int FindScreen(
  char *logicalName)
   if ((strcmp(logicalName, "stdout") == 0) ||
       (strcmp(logical Name, "stdin") == 0) | |
```

```
(strcmp(logicalName, "wprompt") == 0) | |
        (strcmp(logical Name, "wdi spl ay") == 0) ||
(strcmp(logical Name, "wdi spl ay") == 0) ||
(strcmp(logical Name, "wdi al og") == 0) ||
(strcmp(logical Name, "werror") == 0) ||
(strcmp(logical Name, "wwarni ng") == 0) ||
         (strcmp(logicalName, "wtrace") == 0) | |
         (strcmp(logical Name, "top") == 0))
      { return(TRUE); }
   return(FALSE);
  }
We now need to define a function which will print strings to the two windows.
The print function for our router is defined below.
int PrintScreen(
  char *logicalName,
  char *str)
   if (strcmp(logicalName, "top") == 0)
       wpri ntw(UpperWi ndow, "%s", str);
       wrefresh(UpperWindow);
   else
      {
       wpri ntw(LowerWi ndow, "%s", str);
       wrefresh(LowerWindow);
  }
We now need to define a function which will get and unget characters from the
lower window. CURSES uses unbuffered input so we will simulate buffered
input for CLIPS. The get and ungetc character functions for our router are
defined below.
static int UseSave = FALSE;
static int SaveChar;
static int SendReturn = TRUE;
static char StrBuff[80] = \{' \setminus 0'\};
static int CharLocation = 0;
```

```
int GetcScreen(
  char *logicalName)
   int rv;
   if (UseSave == TRUE)
      UseSave = FALSE;
      return(SaveChar);
   if (StrBuff[CharLocation] == '\0')
      if (SendReturn == FALSE)
         SendReturn = TRUE;
         return('\n');
      wgetstr(LowerWindow, StrBuff[80] );
      CharLocation = 0;
   rv = StrBuff[CharLocation];
   if (rv == ' \setminus 0') return(' \setminus n');
   CharLocation++;
   SendReturn = FALSE;
   return(rv);
int UngetcScreen(
  char ch,
  char *logicalName)
   UseSave = TRUE;
   SaveChar = ch;
   return(ch);
When we exit CLIPS CURSES needs to be deactivated. The exit function for our
router is defined below.
int ExitScreen(
                                                  /* unused */
  int num)
   endwin();
  }
Now define a function that turns the screen mode on.
int ScreenOn()
   int halfLines, i;
```

```
/* Has initialization already occurred? */
   if (WindowInitialized == TRUE) return(FALSE);
   else WindowInitialized = TRUE;
   /* Reroute I/O and initialize CURSES. */
   initscr();
   echo();
   AddRouter("screen",
                                          /* Router name
                                          /* Priority
              10,
                                          /* Query function */
              FindScreen,
                                          /* Print function */
              PrintScreen,
                                          /* Getc function
              GetcScreen,
                                                              */
                                          /* Ungetc function */
              UngetcScreen,
              ExitScreen);
                                          /* Exit function
   /* Create the two windows. */
   halfLines = LINES / 2;
   UpperWindow = newwin(halfLines, COLS, 0, 0);
   LowerWindow = newwin(halfLines - 1, COLS, halfLines + 1, 0);
   /* Both windows should be scrollable. */
   scrollok(UpperWindow, TRUE);
   scrol l ok(LowerWi ndow, TRUE);
   /* Separate the two windows with a line. */
   for (i = 0 ; i < COLS ; i++)
     { mvaddch(halfLines, i, '-'); }
   refresh();
   wcl ear(UpperWi ndow);
   wclear(LowerWindow);
   wmove(LowerWindow, 0, 0);
   return(TRUE);
Now define a function that turns the screen mode off.
int ScreenOff()
   /* Is CURSES already deactivated? */
   if (WindowInitialized == FALSE) return(FALSE);
   WindowInitialized = FALSE;
   /* Remove I/O rerouting and deactivate CURSES. */
   DeleteRouter("screen");
   endwin();
```

Appendix C - Update Release Notes

The following sections denote the changes and bug fixes for CLIPS versions 6.01, 6.02, 6.03, and 6.04, 6.05, and 6.10.

C.1 VERSION 6.10

- C++ Compatible The CLIPS source code can now be compiled using either an ANSI C or C++ compiler. Minimally, non-ANSI C compilers must support full ANSI style function prototypes and the void data type in order to compile CLIPS.
- Obsolete External Function Interface Changes The following functions should be replaced with the specified functions. If clips.h is included in your C files, macros will automatically map these functions to their new names.

CLIPSFunctionCall (use FunctionCall instead)
ExitCLIPS (use ExitRouter instead)
GetcCLIPS (use GetcRouter instead)
InitializeCLIPS (use InitializeEnvironment instead)
PrintCLIPS (use PrintRouter instead)
UngetcCLIPS (use UngetcRouter instead)

• Obsolete Constants and Variables Changes - The following constants and variables should be replaced with the specified replacements. If clips.h is included in your C files, macros will automatically map the old names to their new names.

CLIPS_FALSE (use FALSE instead)
CLIPS_TRUE (use TRUE instead)
CLIPSFalseSymbol (use FalseSymbol instead)
CLIPSTrueSymbol (use TrueSymbol instead)
WCLIPS (use WPROMPT instead)

• Source File Name Changes - The names of the following source files have been changed:

clipsmem.h (use memalloc.h instead)
memory.c (use memalloc.c instead)

• Compiler Directives – Some of the compiler directive flags in the file setup.h have been changed. The CLP_TEXTPRO and CLP_HELP flags have been renamed to TEXTPRO_FUNCTIONS and HELP_FUNCTIONS. The ANSI_COMPILER flag has been removed.

• External Function Interface - Several new functions have been added including:

GetNextInstanceInClassAndSubclasses (see section 4.13.15)

• New Source Files – Several new source files have been added (see section 2.1 for a complete list of source files):

```
parsefun.c
parsefun.h
proflfun.c
proflfun.h
sortfun.c
sortfun.h
```

C.1 VERSION 6.05

- **Compiler Directives** The CLP_EDIT flag in the file setup.h has been renamed to EMACS_EDITOR.
- External Function Interface Several new functions have been added including:

```
BatchStar (see section 4.1.23)
Build (see section 4.1.24)
Eval (see section 4.1.25)
FactExistp (see section 4.4.20)
FactSlotNames (see section 4.4.21)
GetFactList (see section 4.4.22)
LoadFactsFromString (see section 4.4.23)
LoadInstancesFromString (see section 4.13.26)
RestoreInstancesFromString (see section 4.13.27)
```

Appendix D - Differences Between Versions 5.1 and 6.0

Numerous changes and additions to CLIPS were made between version 5.1 and the version 6.0. They are:

- Additional Files Several files have been added to provide the new capabilities for this release. The operation of CLIPS should not be affected for the user except in its installation. For details, see section 2.
- New Compiler Directives The setup.h header file contains several new compiler directive
 flags and several compiler directive flags have been removed. The STUDENT flag has been
 removed and the LOGICAL_DEPENDENCIES,

CONFLICT_RESOLUTION_STRATEGIES, DYNAMIC_SALIENCE,

INCREMENTAL_RESET, DEFMODULE_CONSTRUCT, IMPERATIVE_METHODS,

DEFINSTANCES_CONSTRUCT, IMPERATIVE_MESSAGE_HANDLERS,

AUXILIARY_MESSAGE_HANDLERS, INSTANCE_SET_QUERIES,

INSTANCE_PATTERN_MATCHING, BLOAD_INSTANCES and BSAVE_INSTANCES flags have been added. For details, see section 2.

- **User Defined Functions** Several new return types have been added for **DefineFunction**. The **DefineFunction2** function (see section 3.1) provides additional support for argument type checking.
- External Function Interface Several new functions have been added including:

AssignFactSlotDefaults (see section 4.4.3)

ClassReactiveP (see section 4.12.3)

ClearFocusStack (see section 4.7.3)

FindDefmodule (see section 4.16.1)

Focus (see section 4.7.5)

GetCurrentModule (see section 4.16.2)

GetDefclassList (see section 4.12.10)

GetDefclassWatchInstances see section 4.12.13)

GetDefclassWatchSlots (see section 4.12.14)

GetDeffactsList (see section 4.5.3)

GetDeffunctionList (see section 4.9.3)

GetDeffunctionWatch (see section 4.9.6)

GetDefgenericList (see section 4.10.3)

GetDefgenericWatch (see section 4.10.6)

GetDefglobalList (see section 4.8.3)

GetDefglobalWatch (see section 4.8.8)

GetDefinstancesList (see section 4.15.3)

GetDefmessageHandlerList (see section 4.14.2)

GetDefmessageHandlerWatch (see section 4.14.6)

GetDefmethodList (see section 4.11.2)

GetDefmethodWatch (see section 4.11.4)

GetDefmoduleList (see section 4.16.3)

GetDefmoduleName (see section 4.16.4)

GetDefmodulePPForm (see section 4.16.5)

GetDefruleList (see section 4.6.4)

GetDefruleWatchActivations (see section 4.6.7)

GetDefruleWatchFirings (see section 4.6.8)

GetDeftemplateList (see section 4.3.3)

GetDeftemplateWatch (see section 4.3.6)

GetDynamicConstraintChecking (see section 4.1.9)

GetFactSlot (see section 4.4.11)

GetFocus (see section 4.7.10)

GetFocusStack (see section 4.7.11)

GetMethodRestrictions (see section 4.11.5)

GetNextDefmodule (see section 4.16.6)

GetSequenceOperatorRecognition (see section 4.1.10)

GetStaticConstraintChecking (see section 4.1.11)

IsDefglobalDeletable (see section 4.8.12)

ListDefmodules (see section 4.16.7)

ListFocusStack (see section 4.7.15)

PopFocus (see section 4.7.16)

PutFactSlot (see section 4.4.15)

RestoreInstances (see section 4.13.20)

SaveFacts (see section 4.4.17)

SetCurrentModule (see section 4.16.8)

SetDefclassWatchInstances (see section 4.12.18)

SetDefclassWatchSlots (see section 4.12.19)

SetDeffunctionWatch (see section 4.9.10)

SetDefgenericWatch (see section 4.10.10)

SetDefglobalWatch (see section 4.8.15)

SetDefmessageHandlerWatch (see section 4.14.11)

SetDefmethodWatch (see section 4.11.9)

SetDefruleWatchActivations (see section 4.6.17)

SetDefruleWatchFirings (see section 4.6.18)

SetDynamicConstraintChecking (see section 4.1.20)

SetSequenceOperatorRecognition (see section 4.1.21)

SetStaticConstraintChecking (see section 4.1.22)

ShowDefglobals (see section 4.8.18)

SlotAllowedValues (see section 4.12.20)

SlotCardinality (see section 4.12.21)

SlotDirectAccessP (see section 4.12.22)

SlotExistp (see section 4.12.23)

SlotInitablep (see section 4.12.25)

SlotPublicP (see section 4.12.26)

SlotRange (see section 4.12.27)

SlotTypes (see section 4.12.29)

SlotWritablep (see section 4.12.30)

SubclassP (see section 4.12.31)

SuperclassP (see section 4.12.32)

Undefglobal (see section 4.8.19)

Unwatch (see section 4.2.5)

Watch (see section 4.2.6)

• External Function Interface Changes - Several old functions have been modified including:

Agenda (see section 4.7.2)

CLIPSPutSlot (see section 4.13.7)

CreateFact (see section 4.4.4)

Facts (see section 4.4.7)

FindInstance (see section 4.13.8)

GetDefglobalPPForm (see section 4.8.5)

ListDefclasses (see section 4.12.17)

ListDeffacts (see section 4.5.8)

ListDeffunctions (see section 4.9.9)

ListDefgenerics (see section 4.10.9)

ListDefglobals (see section 4.8.13)

ListDefinstances (see section 4.15.8)

ListDefmessageHandlers (see section 4.14.9)

ListDefmethods (see section 4.11.8)

ListDefrules (see section 4.6.12)

ListDeftemplates (see section 4.3.9)

RefreshAgenda (see section 4.7.17)

ReorderAgenda (see section 4.7.19)

SaveInstances (see section 4.13.21)

ShowBreaks (see section 4.6.20)

• Obsolete External Function Interface Changes - The following functions are no longer supported or should be replaced with the specified functions. The header file cmptblty.h provides macros for mapping many of these functions to their new names.

AddBreakpoint (use **SetBreak** instead)

AddFact (use Assert instead)

AddWatchItem

BrowseClass (use **BrowseClasses** instead)

ClearCLIPS (use **Clear** instead)

CLIPSDeleteInstance (use **DeleteInstance** instead)

CLIPSGetSlot (use **DirectGetSlot** instead)

CLIPSMakeInstance (use **MakeInstance** instead)

CLIPSPutSlot (use **DirectPutSlot** instead)

CLIPSSendMessage (use **Send** instead)

CLIPSTestSlot

CLIPSUnmakeInstance (use **UnmakeInstance** instead)

CloseCRSVTrace

CloseDribble (use DribbleOff instead)

CRSVTraceActive

DeleteDefclass (use **Undefclass** instead)

DeleteDeffacts (use **Undeffacts** instead)

DeleteDeffunction (use **Undeffunction** instead)

DeleteDefgeneric (use **Undefgeneric** instead)

DeleteDefinstances (use **Undefinstances** instead)

DeleteDefmessageHandler (use **UndefmessageHandler** instead)

DeleteDefmethod (use **Undefmethod** instead)

DeleteDefrule (use **Undefrule** instead)

DeleteDeftemplate (use **Undeftemplate** instead)

GetClassMessageHandlers (use GetDefmessageHandlerList instead)

GetClassSlots (use ClassSlots instead)

GetClassSubclasses (use ClassSubclasses instead)

GetClassSuperclasses (use ClassSuperclasses instead)

GetDynamicDeftemplateChecking (use GetDynamicConstraintChecking instead)

GetFactIndex (use **FactIndex** instead)

GetSlotFacets (use **SlotFacets** instead)

GetSlotSources (use **SlotSources** instead)

IsClassAbstract (use **ClassAbstractP** instead)

ListBreakpoints (use **ShowBreaks** instead)

ListAgenda (use **Agenda** instead)

ListFacts (use **Facts** instead)

ListInstances (use **Instances** instead)

ListMatches (use **Matches** instead)

LoadConstructs (use **Load** instead)

MemoryRequests (use MemRequests instead)

MemoryUsed (use MemUsed instead)

OpenCRSVTrace

OpenDribble (use **DribbleOn** instead)

PreviewMessage (use PreviewSend instead)

RefreshDefrule (use Refresh instead)

ReleaseMemory (use ReleaseMem instead)

RemoveBreakpoint (use RemoveBreak instead)

ResetCLIPS (use Reset instead)

RetractFact (use Retract instead)

RunCLIPS (use Run instead)

SaveConstructs (use Save instead)

SetDynamicDeftemplateChecking (use SetDynamicConstraintChecking instead)

SetWatchItem (use **Watch** and **Unwatch** instead)

WildDeleteHandler (use UndefmessageHandler instead)

ActivateRouter159	boolean	28
Adaxii, 143	FALSE	28
AddBreakpoint193	TRUE	28
AddClearFunction39	BrowseClass	194
AddDouble30 , 31	BrowseClasses	101 , 194
AddFact56 , 193	browse-classes	101
AddLong30 , 31	bsave	12, 41
AddPeriodicFunction40	BSAVE_INSTANCES	10
AddResetFunction40	bsave-instances	10, 113
AddRouter160	build	12, 48 , 141, 190
AddRunFunction75	C	xi, 143
AddSymbol	call-next-handler	10
AddWatchItem193	call-next-method	9
Advanced Programming Guide xii, xiii	call-specific-method	9
agenda12, 76 , 193, 194	ClassAbstractP	102 , 194
ANSI	class-abstractp	102
ANSI_COMPILER189	ClassReactiveP	102 , 191
any-instancep	class-reactivep	102
ArgCountCheck19	ClassSlots	102 , 194
ArgRangeCheck19	class-slots	102
ArgTypeCheck	ClassSubclasses	103 , 194
ARTxi	class-subclasses	103
Artificial Intelligence Sectionxi	ClassSuperclasses	103 , 194
Assert 54 , 63, 193	class-superclasses	103
AssertString 55 , 63, 144, 145	clear	39, 41 , 194
assert-string 55	ClearCLIPS	194
AssignFactSlotDefaults 56 , 191	ClearFocusStack	
AUXILIARY_MESSAGE_HANDLERS 10	clear-focus-stack	77
Basic Programming Guide xii, xiii, 1, 17	CLIPS	xi
BASIC_IO12	CLIPS_FALSE	189
batch*	CLIPS_TRUE	189
BatchStar 47, 190	CLIPSDeleteInstance	194
BinaryLoadInstances112	CLIPSFalseSymbol	189
BinarySaveInstances113	CLIPSFunctionCall	
bload11, 41 , 139	CLIPSGetSlot	194
BLOAD_AND_BSAVE 12	CLIPSMakeInstance	194
BLOAD_INSTANCES10	clipsmem.h	
BLOAD_ONLY 11, 12	CLIPSPutSlot	
bload-instances 10, 112	CLIPSSendMessage	194
BLOCK_MEMORY 13, 164	CLIPSTestSlot	194

CLIPSTrueSymbol189	DefineFunction2	. 17 , 191
CLIPSUnmakeInstance194	DEFINSTANCES_CONSTRUCT	9
close	DefinstancesModule	129
CloseCRSVTrace 194	definstances-module	129
CloseDribble	DEFMODULE_CONSTRUCT	11
CLP_EDIT190	DEFRULE_CONSTRUCT	8
CLP_HELP189	DefruleHasBreakpoint	69
CLP_TEXTPRO189	DefruleModule	
CommandLoop 140	defrule-module	69
Common Lisp Object Systemxii	DEFTEMPLATE_CONSTRUCT	9
compiler directives7	DeftemplateModule	51
CONFLICT_RESOLUTION_STRATEGIE	deftemplate-module	
S8	delayed-do-for-all-instances	
conserve-mem164, 166	delete\$	
CONSTRUCT_COMPILER 11, 140	DeleteActivation	77
constructs-to-c	DeleteDefclass	194
COOLxii	DeleteDeffacts	194
create\$ 12	DeleteDeffunction	194
CreateFact54, 56, 61, 193	DeleteDefgeneric	194
CreateMultifield33	DeleteDefinstances	
CreateRawInstance113	DeleteDefmessageHandler	194
CRSVTraceActive194	DeleteDefmethod	
DeactivateRouter161	DeleteDefrule	194
DEBUGGING_FUNCTIONS12	DeleteDeftemplate	194
DecrementFactCount58, 63	DeleteInstance	
DecrementInstanceCount113	DeleteRouter	161
DefclassModule	dependencies	8
defclass-module103	dependents	
DEFFACTS_CONSTRUCT8	DescribeClass	104
DeffactsModule	describe-class	104
deffacts-module	DirectGetSlot	114 , 194
DEFFUNCTION_CONSTRUCT9	DirectPutSlot	114 , 194
DeffunctionModule90	do-for-all-instances	10
deffunction-module90	do-for-instance	10
deffunctions	DOPToDouble	22
calling from C 42	DOPToFloat	22
DEFGENERIC_CONSTRUCT9	DOPToInteger	22
DefgenericModule	DOPToLong	
defgeneric-module	DOPToPointer	
DEFGLOBAL_CONSTRUCT9	DOPToString	22
DefglobalModule	DOToDouble	
defglobal-module84	DOToFloat	22
DefineFunction15 , 26, 28, 29, 30, 32, 191	DOToInteger	22

DOToLong 22	FindDefclass	104
DOToPointer22	FindDeffacts	66
DOToString	FindDeffunction	91
DribbleActive	FindDefgeneric	94
DribbleOff	FindDefglobal	84
dribble-off	FindDefinstances	129
DribbleOn 49 , 194	FindDefmessageHandler	124
dribble-on	FindDefmodule1	32 , 191
DYNAMIC_SALIENCE8	FindDefrule	70 , 144
dynamic-get 114	FindDeftemplate	51
dynamic-put 115	FindInstance1	. 15 , 193
EMACS_EDITOR 7, 11 , 190	find-instance	10
embedded application39	first\$	12
eval12, 48 , 141, 190	float	20
EX_MATH 7, 11	Focus	77 , 191
ExitCLIPS 189	format 12, 1	54, 155
ExitRouter157 , 189	FORTRAN	143
explode\$	FunctionCall	42 , 189
EXT_IO12	functions	
external address	argument access	19, 147
FactExistp 64 , 190	calling from C	42
fact-existp	external15	5, 19, 21
FactIndex 59 , 194	library	
fact-index 59	exit	157
facts12, 59 , 144, 193, 194	free	163
FactSlot 65	getc	
FactSlotNames190	malloc 163, 1	65, 166
fact-slot-names	printf	158
FALSE 189	sprintf	55
FalseSymbol189	string conversion	
fetch 11	Convert_to_C_String	169
files	MakeStringDsc147, 1	69, 176
header	user-defined	15
clips.h 15, 22, 39, 157, 159, 164	genalloc	163
memalloc.h 164	GENERIC	7
router.h 157, 159	generic functions	
setup.h 6, 7, 11, 140, 164	calling from C	42
source	genfree	163
main.c15, 37, 39, 136, 138, 140,	GetActivationName	77
151, 152	GetActivationPPForm	78
memory.c163	GetActivationSalience	78
sysdep.c 7	GetAgendaChanged	78
find-all-instances 10	GetAutoFloatDividend	42

get-auto-float-dividend42	GetDefmessageHandlerName12	25
GetcCLIPS	GetDefmessageHandlerPPForm12	26
GetClassMessageHandlers	GetDefmessageHandlerType12	26
GetClassSlots	GetDefmessageHandlerWatch126, 19)2
GetClassSubclasses	GetDefmethodDescription9	7
GetClassSuperclasses	GetDefmethodList	
GetConserveMemory164	get-defmethod-list9	8(
GetcRouter 158 , 159, 189	GetDefmethodPPForm9	8(
GetCurrentModule 132 , 191	GetDefmethodWatch 99, 19) 2
get-current-module	GetDefmoduleList132, 19) 2
GetDefclassList 104 , 191	get-defmodule-list13	33
get-defclass-list104	GetDefmoduleName133, 19) 2
GetDefclassName105	GetDefmodulePPForm133, 19) 2
GetDefclassPPForm105	GetDefruleList) 2
GetDefclassWatchInstances105, 191	get-defrule-list	70
GetDefclassWatchSlots 106 , 191	GetDefruleName	70
GetDeffactsList	GetDefrulePPForm7	70
get-deffacts-list	GetDefruleWatchActivations 71, 19) 2
GetDeffactsName 67	GetDefruleWatchFirings) 2
GetDeffactsPPForm67	GetDeftemplateList 51, 19) 2
GetDeffunctionList	get-deftemplate-list5	51
get-deffunction-list91	GetDeftemplateName5	52
GetDeffunctionName	GetDeftemplatePPForm5	
GetDeffunctionPPForm 92	GetDeftemplateWatch52, 19	
GetDeffunctionWatch 92, 191	GetDOBegin2	24
GetDefgenericList	GetDOEnd	24
get-defgeneric-list	GetDOLength2	24
GetDefgenericName	GetDynamicConstraintChecking19) 4
GetDefgenericPPForm95	GetDynamicConstraintChecking 42, 19) 2
GetDefgenericWatch	get-dynamic-constraint-checking4	13
GetDefglobalList 84 , 191	GetDynamicDeftemplateChecking 19) 4
get-defglobal-list85	GetFactDuplication5	59
GetDefglobalName85	get-fact-duplication5	59
GetDefglobalPPForm 85 , 193	GetFactIndex19) 4
GetDefglobalValue85	GetFactList) ()
GetDefglobalValueForm 86	get-fact-list6	55
GetDefglobalWatch	GetFactListChanged6	50
GetDefinstancesList130, 191	GetFactPPForm6	50
get-definstances-list130	GetFactSlot) 2
GetDefinstancesName130	GetFocus) 2
GetDefinstancesPPForm130	get-focus	19
GetDefmessageHandlerList125, 191, 194	GetFocusStack)2
get-defmessage-handler-list125	get-focus-stack	19

GetGlobalsChanged86	GetStrategy	80
GetIncrementalReset71	get-strategy	8, 80
get-incremental-reset	GetType	21
GetInstanceClass115	GetValue	24, 31
GetInstanceName116	GetWatchItem	49
GetInstancePPForm116	HELP_DEFAULT	11
GetInstancesChanged116	HELP_FUNCTIONS	11 , 189
GetMethodRestrictions 99, 192	I/O router	. 153 , 179
get-method-restrictions	priority	156
GetMFType24 , 61	IMPERATIVE_MESSAGE_HAND	
GetMFValue		10
GetNextActivation79	IMPERATIVE_METHODS	
GetNextDefclass106	implode\$	12
GetNextDeffacts	INCREMENTAL_RESET	
GetNextDeffunction	IncrementFactCount 5	55, 61, 63
GetNextDefgeneric96	IncrementInstanceCount	
GetNextDefglobal87	Inference Corporation	xi
GetNextDefinstances131	InitCImage	
GetNextDefmessageHandler127	InitializeCLIPS	
GetNextDefmethod99	InitializeEnvironment39, 43, 140,	144, 189
GetNextDefmodule 133 , 192	insert\$	
GetNextDefrule72	installation of CLIPS	3
GetNextDeftemplate 52	instance address	29
GetNextFact61	Instance manipulation from C	112
GetNextInstance117	INSTANCE_PATTERN_MATCHI	NG 10
GetNextInstanceInClass117	INSTANCE_SET_QUERIES	10
GetNextInstanceInClassAndSubclasses	Instances	. 120 , 194
190	integer	20
GetpDOBegin	integration	1
GetpDOEnd	Interfaces Guide	xiii
GetpDOLength 24	IsClassAbstract	
GetpType 21	IsDefclassDeletable	106
GetpValue24, 31	IsDeffactsDeletable	68
GetResetGlobals	IsDeffunctionDeletable	92
get-reset-globals87	IsDefgenericDeletable	96
GetSalienceEvaluation80	IsDefglobalDeletable	88 , 192
get-salience-evaluation	IsDefinstancesDeletable	131
GetSequenceOperatorRecognition 43, 192	IsDefmessageHandlerDeletable	127
get-sequence-operator-recognition 43	IsDefmethodDeletable	
GetSlotFacets194	IsDefruleDeletable	72
GetSlotSources	IsDeftemplateDeletable	53
GetStaticConstraintChecking 43, 192	LISP	
get-static-constraint-checking	ListAgenda	194

wprompt	155
wtrace	155
wwarning	155
LOGICAL_DEPENDENCIES	8
lowcase	12
main13	5, 136, 140
MakeInstance	121 , 194
make-instance	121
Matches	73 , 194
memalloc.c	189
memalloc.h	189
member\$	12
memory management	163
•	
mem-used	165
Message-passing from C	122
next-handlerp	10
next-methodp	9
_	
open	12, 154
OpenCRSVTrace	194
-	
override-next-handler	10
override-next-method	9
parameter	21
parsefun.h	190
PopFocus	80 , 192
pop-focus	81
portability	
1 ,	
e	
preview-send	128
	wprompt. wtrace wwarning LOGICAL_DEPENDENCIES lowcase main 13 MakeInstance make-instance Matches memalloc.c memalloc.h member\$ memory management memory.c MemoryRequests MemOryUsed MemRequests mem-requests MemUsed mem-used Message-passing from C MULTIFIELD_FUNCTIONS NASA next-handlerp next-methodp nth\$ OBJECT_SYSTEM open OpenCRSVTrace OpenDribble override-next-method parameter parsefun.c parsefun.c parsefun.h PopFocus pop-focus pop-focus portability ppdeffacts ppdefrule PreviewMessage PreviewSend preview-send

PrintCLIPS 189	RunCLIPS	195
printout	run-time module	139
print-region11	Save	45 , 46, 195
PrintRouter144, 156, 158 , 189	SaveConstructs	195
proflfun.c 190	SaveFacts	63 , 192
proflfun.h 190	save-facts	63
progn\$12	SaveInstances	121 , 193
PutFactSlot 56, 62 , 192	save-instances	121
read	Send	122 , 194
readline	SetActivationSalience	82
Reference Manualxiii, xv	SetAgendaChanged	83
Refresh	SetAutoFloatDividend	
RefreshAgenda 81 , 193	set-auto-float-dividend	46
refresh-agenda	SetBreak	73 , 193
RefreshDefrule194	set-break	74
ReleaseMem165 , 194	SetConserveMemory	166
release-mem165	SetCurrentModule	134 , 192
ReleaseMemory 194	set-current-module	134
RemoveBreak	SetDefclassWatch	107
remove-break	SetDefclassWatchInstances	192
RemoveBreakpoint195	SetDefclassWatchSlots	192
RemoveClearFunction44	SetDeffunctionWatch	93 , 192
RemovePeriodicFunction	SetDefgenericWatch	97 , 192
RemoveResetFunction45	SetDefglobalValue	88
RemoveRunFunction	SetDefglobalWatch	89 , 192
Reorder Agenda	SetDefmessageHandlerWatch	128 , 192
replace\$12	SetDefmethodWatch	100 , 192
RerouteStdin140	SetDefruleWatchActivations	74 , 192
reset	SetDefruleWatchFirings	74 , 192
ResetCLIPS	SetDeftemplateWatch	53
rest\$	SetDOBegin	33
RestoreInstances 121 , 192	SetDOEnd	33
restore-instances121, 124	SetDynamicConstraintChecking4	6 , 192, 195
RestoreInstancesFromString124, 190	set-dynamic-constraint-checking	g 46, 140
Retract 63, 144, 145, 195	SetDynamicDeftemplateChecking	ng195
RetractFact 195	SetFactDuplication	64
RtnArgCount	set-fact-duplication	64
RtnDouble	SetFactListChanged	64
RtnLexeme	SetGlobalsChanged	89
RtnLong	SetIncrementalReset	
RtnUnknown21, 24	set-incremental-reset	8, 74
Run 82 , 144, 195	SetInstancesChanged	123
RUN_TIME7 , 12, 140	SetMFType	33

SetMFValue	33 Smalltalk	xii
SetMultifieldErrorValue	Software Technology Branch	xi
SetOutOfMemoryFunction10	66 sortfun.c	190
SetpDOBegin	33 sortfun.h	190
SetpDOEnd	33 str-cat	12
SetpType	31 str-compare	12
SetpValue		
SetResetGlobals	89 STRING_FUNCTIONS	12
set-reset-globals	str-length	12
SetSalienceEvaluation	83 SubclassP	111 , 193
set-salience-evaluation	83 subseq\$	12
SetSequenceOperatorRecognition 47, 19	subsetp	12
set-sequence-operator-recognition	sub-string	12
SetStaticConstraintChecking 47, 19	92 SuperclassP	112 , 193
set-static-constraint-checking	47 symbol	20, 26
SetStrategy	FalseSymbol	28
set-strategy	83 TrueSymbol	28
SetType31 , 3		
setup flags	.7 TEXTPRO_FUNCTIONS	11 , 189
SetValue31, 3	33 toss	11
SetWatchItem19	95 TRUE	189
SHORT_LINK_NAMES	13 TrueSymbol	189
ShowBreaks	94 Undefclass	112 , 194
show-breaks	75 Undeffacts	69 , 194
ShowDefglobals 89 , 19	Undeffunction	93 , 194
show-defglobals	90 Undefgeneric	97 , 194
SlotAllowedValues107, 19	92 Undefglobal	90 , 193
slot-allowed-values10	08 Undefinstances	132 , 194
SlotCardinality 108 , 19	UndefmessageHandler12	28 , 194, 195
slot-cardinality10	08 undefmessage-handler	129
SlotDirectAccessP108, 19	Undefmethod	101 , 194
SlotExistP 109 , 19	93 Undefrule	'5 , 144, 194
SlotFacets 109 , 19	94 Undeftemplate	54 , 194
slot-facets10	09 UngetcCLIPS	189
SlotInitableP 109 , 19	93 UngetcRouter	159 , 189
SlotPublicP 110 , 19	UnmakeInstance	123 , 194
SlotRange110, 19	93 Unwatch 5	50 , 193, 195
slot-range	10 upcase	12
SlotSources 110 , 19	94 User's Guide	xiii, xv
slot-sources	10 UserFunctions15 , 20, 39, 135, 1	40, 146,
SlotTypes	93 147, 150, 151, 176	
slot-types 1	11 ValidInstanceAddress	123
SlotWritableP111, 19	93 ValueToDouble	24, 31

ValueToInteger 24, 31	WCLIPS 189
ValueToLong24, 31	WildDeleteHandler19
ValueToString 24, 31	WINDOW_INTERFACE13
Watch 50 , 144, 193, 195	WPROMPT 189