

Sale Discount Approval — User Guide

Overview

Sale Discount Approval lets you apply a single discount to an entire sale order or customer invoice — as a **Percent** or a fixed **Amount** — and spread it evenly across every line. Large discounts can optionally be routed to a **Sales Manager** for approval before the order is confirmed.

Prerequisites

The discount fields are only visible when the standard Odoo **Discounts** feature is enabled:

Settings → Sales → Pricing → Discounts (Discount per line, `sale.group_discount_per_so_line`).

If this group is off, the discount inputs described below stay hidden.

Configuration

1. Go to **Settings → Sales**.
2. In the **Pricing** block enable **Sale Discount Approval**.
3. Set **Discount Approval Limit (%)** — the average line-discount threshold above which an order needs manager approval (for example 15).
4. Save.

Internally this maps to the company fields `so_double_validation` (`one_step` / `two_step`) and `so_double_validation_limit`.

Applying an order-level discount

On a quotation (`Sales → Orders → Quotations`):

1. Pick a **Discount Type** — `Percent` or `Amount`.
2. Enter a **Discount Rate**.
 - **Percent** — every line's `discount` is set to that percentage directly.
 - **Amount** — the amount is converted to a uniform percentage $\text{rate} \div (\sum \text{qty} \times \text{unit price}) \times 100$ and applied to every line.
3. The fan-out runs automatically on change; you can also click the **(update)** link (draft/sent only) to re-run it.

Worked example (Amount). An order of two lines — $10 \times \text{€}300$ (=€3,000) and 20



× €100 (=€2,000), total **€5,000** — with an **Amount** discount of **€500** yields a uniform **10%** on both lines. The **per-line** percentage is rounded to 2 decimals, so an individual line's discounted subtotal can be off by a few cents from a perfectly even split — treat each line as approximately its share, not exact to the cent.

The **Discount** field on the order footer shows the informational total. For an **Amount**-type discount with at least one discountable line, it always equals the **Discount Rate** you entered exactly (e.g. entering **€700** always shows **Discount: €700.00**, even though the per-line percentage that achieves it is rounded). For a **Percent**-type discount it is computed as $\Sigma(\text{qty} \times \text{unit price} \times \text{line discount} \div 100)$, which is already exact since the percentage is applied to lines unconverted. If the order has no discountable lines (or they total zero), the Discount field shows **0.00** regardless of the entered rate, since nothing was actually discounted yet. The line subtotals already reflect the discount, so this field is for reference only.

Surcharges

A **negative** Discount Rate is allowed and behaves as a price increase (surcharge), fanned out the same way. No validation blocks negative values.

Pricelist interaction

Applying the order-level discount **overwrites** any discount the pricelist had computed on each line. There is no merge — the manual input always wins once applied.

The approval gate

When **two-step** approval is active, confirming an order compares the **unweighted average of all order-line discounts** (including 0% and negative lines) against the limit:

- **average ≤ limit** — the order confirms normally.
- **average > limit** — the order moves to **Waiting Approval** and confirmation is halted.

From a Waiting Approval order, a **Sales Manager** (`sales_team.group_sale_manager`) sees two buttons:

- **Approve** — confirms the order through the standard flow.
- **Reject** — sends the order back to **Draft** for revision.

Both actions are enforced on the server, not just hidden in the UI: calling either one as a user outside `sales_team.group_sale_manager` (e.g. over RPC) is rejected with an access error, and each only acts on orders actually in **Waiting Approval** — calling **Approve** on an order that never reached that state (still **Draft**) leaves it untouched rather than confirming it.

Approve works by internally re-running the same confirmation the **Confirm** button uses, with permission to skip the average-discount check — but only under two conditions checked together: the caller must be a Sales Manager (or a privileged system call such as a cron job), and the order must already be in **Waiting Approval**. Neither condition alone is enough:



- A non-manager can never skip the check, no matter how confirmation is triggered.
- A Sales Manager confirming a **Draft** or **Sent** order directly — one that never actually went through **Waiting Approval** — still has the average-discount check applied like anyone else. The only way to reach **Sale** without the check is to have first been parked in **Waiting Approval** and then explicitly approved, so the approval always leaves a visible trace in the order's history rather than being silently skipped.
- Confirming as an elevated system user — as the customer portal does when a customer accepts a quotation — is **not** on its own enough to bypass the check; the same average-discount comparison still applies unless the order is genuinely already waiting on an approval.

Re-confirming an order that is already **Sale** never re-triggers the gate: whatever its current line discounts are, clicking **Confirm** again leaves a confirmed order exactly as it is rather than sending it back to **Waiting Approval**.

Edge case — average dilution. Because 0% and negative lines are included unweighted, a single steeply-discounted line can be diluted below the limit. Example: one line at **25%** and one surcharge line at **-20%** average to **2.5%**, so the order confirms without approval. This is the confirmed business rule, not a defect.

Invoices

- Invoice lines accept the same **Discount Type / Discount Rate** inputs (in Other Info, before the notes), fanned out over `invoice_line_ids`.
- When an order is invoiced, its discount type, rate and amount are copied onto the invoice so it starts pre-populated.
- A zero-total guard prevents any division-by-zero on an empty invoice.
- The invoice's **Discount** total follows the same rule as the order footer: exact to the entered **Discount Rate** for Amount-type discounts, computed from line percentages for Percent-type, and **0.00** when there are no discountable lines.

Documents & analysis

- A **Discount** row is injected into printed quotations, printed invoices and the online portal totals.
- The invoice analysis report (`account.invoice.report`) exposes a **Discount %** column for pivot and graph views.
- Sales Analysis (`sale.report`) exposes the same **Discount %** measure for quotations and orders — open **Sales → Reporting → Sales**, switch to pivot or graph, and add **Discount %** to see it alongside the standard measures.

Field reference

Model	Field	Meaning
sale.order / account.move	discount_type	percent or amount
sale.order / account.move	discount_rate	value entered by the user
sale.order / account.move	amount_discount	computed informational total — exact to <code>discount_rate</code> for Amount-type, computed from lines for Percent-type
sale.order	margin_test	mirrors <code>margin</code> when Sale Margin is installed, else 0
sale.order.line	total_discount	discounted unit value for Amount discounts
res.company	so_double_validation	one_step / two_step
res.company	so_double_validation_limit	approval threshold in %

Known limitations

- For Amount-type discounts, individual **line** discount percentages are rounded to 2 decimals, so a single line's discounted subtotal can be off by a few cents from a perfectly even split. The order/invoice **Discount** footer total itself is exact to the entered amount — only the per-line breakdown is approximate.
- The approval average is **unweighted** and includes 0% and negative lines.
- `margin_test` is populated only when the **Sale Margin** app is installed.