60017 System Performance Engineering Imperial College London

Contents

1	Intr	roduction	2
	1.1	Logistics	2
		1.1.1 Extra Resources	2
	1.2	What is System Performance Engineering	2
	1.3	Performance Engineering Process	3
		1.3.1 Metrics	3
		1.3.2 Quality of Service (QoS) Objectives	4
		1.3.3 Service Level Agreements	4
	1.4	Performance Evaluation Techniques	4
		1.4.1 Measuring	4
	1.5	Optimisation Loop	5
2	Pro	ofiling	7
		2.0.1 Call Stack Tracing	
	2.1	Sampling	
		2.1.1 Time-Base Intervals	
		2.1.2 Event-Base Intervals	
		2.1.3 Indirect Tracing	9
	2.2	Recording Events	.0
		2.2.1 Manual Instrumentation	0
		2.2.2 Automatic Instrumentation	0
		2.2.3 Binary Instrumentation	0
		2.2.4 Kernel Counters/ Software Performance Counters	.1
		2.2.5 Emulation	.1
		2.2.6 Hardware Counters	.1
	2.3	Perf	1
	2.4	Microarchitectural bottleneck analysis	1
	2.5	Vtune	.2
3	\mathbf{Cre}	$_{ m edit}$.3

Chapter 1

Introduction

1.1 Logistics



Dr Holger Pirk



Dr Luis Vilanova

First Half

- Hardware efficiency in complex systems
- Scaling up
- "getting the most bang for buck"

Second Half

• Scale out Processing

1.1.1 Extra Resources

UNFINISHED!!!

1.2 What is System Performance Engineering


System Definition 1.2.1

A collection of components interacting to achieve a greater goal.

- Usually applicable to many domains (e.g a database, operating system, webserver). The goal is domain-agnostic
- Designed to be flexible at runtime (deal with other interacting systems, real conditions) (e.g OS with user input, database with varying query volume and type)
- Operating conditions are unknown at development time (Database does not know schema prior, OS does not know number of users prior, Tensorflow does not know matrix dimensionality prior)

Large & complex systems are typically developed over years by multiple teams.

The challenge with system performance engineering is to make systems maintainable, widely applicable and fast.



System Performance Engineering

Definition 1.2.2

Performance engineering encompasses the techniques applied during a systems development life cycle to ensure the non-functional requirements for performance will be met.

• Functional requirements (correctness, features) are assumed to be met.

•

High Performance Computing

Definition 1.2.3

High performance programming uses highly distributed & parallel computer systems (e.g supercomputers, clusters) to solve advanced problems.

- Focuses on solving a single computationally difficult problem.
- Workloads are well defined and known at development time.
- Sometimes supported by custom hardware (e.g FPGAs, ASICs, custom CPU extensions)

1.3 Performance Engineering Process

1.3.1 Metrics

A target metric is used to quantitatively measure any improvement in performance (e.g for use in a SLA). The metric needs to be wel defined:

- When measuring starts (e.g when to measure latency from)
- Where measuring is done (is server response time measured on server, on a client, under what conditions?)

Imperials	Example Question 1.3.1
Provide some example of	metrics regarding a database.
Latency	Measuring time to query, planning time, the whole systems response time over a network.
${ m Throughput}$	Measure the maximum request/second possible (often used to compare webservers)
Memory Usage scalability	measurable, but must be careful (e.g os interaction) Can define a metric regarding how quickly some metric (e.g throughput) increases with scale (e.g instances of a distributed system)

It is also important to define when a requirement is satisfied.

- Setting an optimisation budget (e.g in developer hours)
- Setting a target or threshold (e.g x% over baseline implementation)
- Combination of both

1.3.2 Quality of Service (QoS) Objectives

Quality of Service Objectives

Definition 1.3.1

A set of statistical properties of a metric that must hold for a system.

- Can include preconditions (e.g to define the environment/setup)
- Can be in conflict with functional requirements (e.g framerate vs realism in graphics)

Game On

Example Question 1.3.2

Give an example of a basic QoS Objective for a game's framerate.

The game's framerate will be on average (over ... preconditions ...) 60fps if run on a GPU rated at 50GFlops or higher.

1.3.3 Service Level Agreements

Service Level Agreements (SLAs)

Definition 1.3.2

Legal contracts specifying QoS objectives and penalties for violation.

- Non-functional requirements (not about system correctness)
- Can be legally enforced

Amazon Extra Fun! 1.3.1

Amazon Web Services (AWS) provides a set of *service level agreements* relating to performance and availability. Violations are resolved by providing customers with service credits. Amazon SLAs

When defining requirements for an SLA:

Specific State exact acceptance criteria (numerical terms).Measurable Ensure the metrics used can actually be measured.

AcceptableRequirements should be rigorous such that meeting them is a meaningful success.RealisableCounter to Acceptable - need to be lenient enough to allow implementation.

Thorough All necessary aspects of the system are specified.

1.4 Performance Evaluation Techniques

1.4.1 Measuring

- Performed on the actual system (can be prototype or production/final).
- Can be difficult and costly (need to mitigate any impact of the measuring system on the system itself).

Benchmarking

• As it is on the actual system, it can (if done properly) yield accurate results.

The two main types of measurement are:

Monitoring

Definition 1.4.1

perfor-

Definition 1.4.2

Measuring in production to get real usage performance metrics.

- Observe the system in its production environment
- Collect usage statistics and analyse data (e.g user's preferred query types/structure, schema designs for databases)
- Can monitor for and report SLA violations.

Measuring system performance in a controlled setting (e.g lab).

- The system to set into a predefined (or steady/hot) state
- Perform some workload while measuring performance metrics.

Benchmarking requires representative workloads in order to get metrics likely to be representative of a production environment.

Batch Workload Definition 1.4.3

Program has access to entire batch at start of the benchmark.

- Useful when a throughput metric is being measured
- Simple to generate, and can even be recorded from a production environment.

Interactive Workload Definition 1.4.4

A program generates requests to pass to the system being benchmarked.


- Useful when a latency metric is being measured.
- Workload generator needs to fast enough to saturate system being benchmarked.
- Often more representative of a production environment (e.g an operating system receives a workload over time)

Hybrid Definition 1.4.5

A common setup combining batch and interactive workload strategies (e.g sample random queries from a predefined work set).

In order to get useful results from which

1.5 Optimisation Loop



Performance Parameters

Definition 1.5.1

System and workload characteristics that affect performance.

System Parameters Do not change as the system runs (instruction costs, caches)

Workload Parameters Change as he system runs (available memory, users)

Numeric Parameters Quantitative (e.g CPU frequency, available memory, number of user)
Nominal Parameters Qualitative parameters (Runs on battery, has a GPU, runs in a VM)

The term resource Parameters/Resources refers to the parameters of the underlying platform (e.g CPU, memory).

Utilisation Definition 1.5.2

The proportion of a resource used by a to perform a service by a system.

- A service has limited resources available (e.g CPU time, memory capacity, network bandwidth etc)
- Total available resources/resource budget available to a service is a parameter

Bottleneck Definition 1.5.3

The resource with the highest utilisation.

- The limiting factor in performance of a system
- given some resource x is the bottleneck, the system is x-bound (e.g CPU-bound).
- Not always a resource, and performance may be bottlenecked by some other factor (e.g latency-bound → the system is dominated by waiting for some operation)

It is typically infeasible to identify all bottlenecks for an entire complex software system.

To limit optimisation complexity efforts should be restricted to optimising code paths that have particularly large effect on performance.

Critical Path Definition 1.5.4

The sequence of activities which contribute the larges overall duration.

Hot Path Definition 1.5.5

A code path where most of the execution time is spent (e.g very commonly executed subroutine)

In order to optimise we require:

- Ability to quickly compare alternative designs
- Ability to select a near optimal value for platform parameters

While workload parameters are not typically controllable at this stage, some system parameters are.

Parameter Tuning Definition 1.5.6

Finding the vector within the parameter space that minimises resource usage, or maximises performance.

- Exploring the parameter space is expensive (even with non-linear optimisation)
- Analytical models can be used to accelerate search.
- Tuning needs to consider tradeoffs (e.g much of a cheap resource versus little of an expensive one)

Analytical Performance Model

Definition 1.5.7

A model describing the relationship between system parameters and performance metrics.

- Having an accurate analytical model for the system is analogous to *understanding* the performance of the system.
- Models can be stateless (e.g an equation) or stateful (e.g using markov chains).
- Need to model dynamic systems with (ideally small) static models.
- Very fast (faster than search parameter space)
- Allow for what-if analysis of system and workload parameters.

Simulation Definition 1.5.8

A single observed run of a stateful model

- Can see all interactions within the system in perfect detail
- Extremely expensive to run (limiting number of simulations and the speed of the optimisation workflow)
- Much more rarely used than other techniques described

Chapter 2

Profiling

Event Definition 2.0.1

A change in the state of the system.

- Usually some granularity limit is used (e.g clock tick)
- Optionally has a payload (properties describing the event e.g cache line evicted \rightarrow the addresses & data evicted)
- Has an accuracy degree to which the event represents reality (many events are numeric & come with measurement related error)

Simple/Atomic Event Executed instruction, clock tick, function called Complex Event Cache line evicted, ROB flush due to misspeculation

Event sources have two components:

Generator Observes changes to system state (online \rightarrow part of the runtime system) **Consumer** Processes events and converts into meaningful insights (offline or online)

The overhead associated with collecting events can be very high.

Pertubation Definition 2.0.2

The effect of analysis on the performance of a system.

- If it is constant/deterministic we can subtract it from measurement to get an accurate result.
- Non-deterministic pertubation negatively affects accuracy as it cannot separate analysis overhead from measured performance

Stacking up! Example Question 2.0.1

Instrumentation is added to a program to inspect its stack at regular intervals, and record the stack trace. Assuming it is implemented to ensure the time spent traversing the trace is deterministic and can be removed from any results, why may this instrumentation still result in non-deterministic pertubation?

Data Cache Side Effects

The instrumentation may bring deep parts of the stack (shallow is hot and likely cached) into cache, evicting other lines. Hence the tracing pollutes the cache and results in more misses & hence more memory related stalls for the program.

We could also more weakly argue about instruction cache limitations, or potential for associativity conflicts occurring may have been avoided by design in the original program, but due to placement of instrumentation's static data & text have their positions moved.

Fidelity Definition 2.0.3

The level of granularity with which events are recorded.

- Perfect fidelity means every event is recorded.
- Lower fidelity generally means less overhead.

Trace Definition 2.0.4


A complete log of the system's state (and hence changes in state/events) for some time period.

- Events usually totally ordered (exceptions being with parallelism i.e multicore systems)
- Accuracy is inherited from events (e.g accuracy of clock, hardware counters etc)
- Analysing traces is time consuming (solution: Profiling)

Events may be aggregated to reduce the logging overhead.

2.0.1 Call Stack Tracing

A common trace is to capture and inspect the stack of a thread.



- Stack frame layout must conform to a convention that stores frame pointers and return addresses on the stack.
- Debug symbols included in the binary (e.g part of the ELF spec) can be used to convert return addresses scraped from the stack into symbols from the source code (function names).
- The stack may not easily represent the call structure of a program (inlining, tail call elimination, constant evaluation and propagation)

2.1 Sampling

Rather than recording all events, we can reduce overhead by sampling some events.

 $\begin{array}{ll} \text{Performance} & \text{Fidelity traded against pertubation for reduced overhead in recording events.} \\ \text{Less Pertubation} & \text{Fewer interactions with program} \rightarrow \text{less effect on performance} \rightarrow \text{less pertubation.} \end{array}$

Imperfect May skip sampling some events (e.g very small functions), but more expensive functions are more likely to be sampled, and we generally care about these more.

2.1.1 Time-Base Intervals

We can make use of hardware supported timer interrupts to set timers before using an interrupt to trap and allow the sampler to take control.

- Can use CPU reference cycles as a proxy metric to time
- Hardware clocks are often poorly defined & vary (i.e variable clock frequencies in modern CPUs, synchronisation of clocks between CPUs)
- Easily available & easy to interpret (ticks \propto time)

2.1.2 Event-Base Intervals

A generalisation of time-based intervals (as a clock tick \rightarrow time is an event)

- Can define in terms of occurrences of an event (e.g function call)
- Depending on design, can be accurate / low noise
- Can be tricky to interpret as a link to some measure proportional to time is needed (typically we care about execution time)

Quantisation Errors Definition 2.1.1

The resolution of an interval is limited (e.g by clock), but time is continuous. Mapping events to a discrete measure of time can introduce errors & bias (costs may be attributed to the wrong time & hence wrong state).

2.1.3 Indirect Tracing

Indirect Tracing Definition 2.1.2

We can sample from parts of a program, and infer traces from the structure of the program.


For example control flow instructions dominate non-control flow instructions, we could sample from control flow instructions, and then infer event between (non-control flow instructions), effectively indirectly tracing them.

- Can be used to reduce overhead from tracing
- fidelity and accuracy good (depending on the events traced and the indirection used)

Profile Definition 2.1.3

A (usually graphical) representation of information relating to the characteristics of a system in terms of resources (quantified) used in certain states.

- An aggregate over a specific metric (e.g a global aggregate if total cache misses, or per event such as cycles per instruction, or cache misses per function)
- Information is lost in aggregation
- Aggregation has lower overhead than recording all events, so can reduce pertubation



2.2 Recording Events

Instrumentation	Definition 2.2.1
Adding event logging code to a program.	
Easily Applicable No need to extra hardware or OS support. Flexible Can implement any kind of logging required.	
High Overhead Perturbation As part of the program can effect performance	

2.2.1 Manual Instrumentation

Logging using a library (e.g printf logging)

Fine control Programmer can easily specify exactly where to log what.
Supportless No need for compiler or hardware support.

High Overhead

Disable Need to disable for release builds (recompile without any logging)

2.2.2 Automatic Instrumentation

Compiler supported injection of event recording code into a program.

- Can be done at source level, or within some intermediate form (e.g injecting into some bytecode)
- Can potentially reduce overhead compared with manual instrumentation (compiler instruments at a lower level representation)

2.2.3 Binary Instrumentation

Instrumenting an already compiled binary.

Static Adding instrumentation directly, overhead can be assessed from the binary.

Dynamic Adding instrumentation at runtime (works well with JiT)

2.2.4 Kernel Counters/ Software Performance Counters

The kernel already has the tools required to collect many kinds of events. These tend to be higher-level OS interactions, rather than microarchitectural events. For example:

- Network packets sent
- Virtual memory events (e.g page faults)
- Context Switches
- Threads spawned

2.2.5 Emulation

2.2.6 Hardware Counters

Special registers configured to count low-level events as well as intervals (e.g cycles)

- Fixed number can be active at runtime
- ullet Often buggy / unmaintained / inaccurate (and poorly documented) \to only the most popular counters are trustworthy

2.3 Perf

UNFINISHED!!!

RTFM Extra Fun! 2.3.1

Intel 64 and IA-32 Architectures Optimization Reference Manual.

- Microarchitectural features documented.
- Written as an optimisation guide.
- Code example can be found in its github repo


2.4 Microarchitectural bottleneck analysis

Advanced Computer Architecture

Extra Fun! 2.4.1

A basic understanding of computer architecture is reuired (pipelining, in order, caches, out of order, speculation).

The 60001 - Advanced Computer Architecture module by Prof Paul Kelly covers this in great depth.



2.5 Vtune

UNFINISHED!!!

Chapter 3

Credit

Content

Based on the System Performance Engineering course taught by Dr Holger Pirk and Dr Luis Vilanova.

These notes were written by Oliver Killane.