MISS KUDI PRODUCTIONS · QUALITY ASSURANCE & UAT MANUAL

User Testing & Verification Guide

EDITION
v1.1 · NOV 2026

LOCAL BASE URL	FACILITY PLANTS	RBAC ACCESS TIERS	VIEWPORT TARGETS
http://localhost:3000	Yaba · VI · Ikeja (3)	Superadmin · Admin · Staff	1440×900 & 390×844

1. Environment Setup & Pre-Test Checklist

PRE-FLIGHT

Local or Staging Startup

1. Run `npm install` then `npm run dev` in the project root.
2. Open `http://localhost:3000` in Chrome, Safari, or Firefox.
3. **Hybrid Persistence:** Runs automatically in local mode; if `DATABASE_URL` is set, run `npm run db:init` and check `/api/health`.

Recommended Browser Setup

1. **Primary Window:** Desktop at `1440×900` for full console testing.
2. **Incognito Window:** Verify unauthenticated redirects & session boundaries.
3. **Mobile Emulation:** DevTools Device Toolbar at `390×844` (Suite 08).

2. Provisioned Test Accounts & Promo Codes

CREDENTIALS

ACCESS TIER	WORK EMAIL	PASSWORD	DEFAULT ROUTE	SCOPE & PLANT ASSIGNMENT
SUPERADMIN	demolablaze@gmail.com	$Omerta93	/superadmin	Global HQ across Yaba, VI & Ikeja; team, facility & audit control.
ADMIN	kudi@kproductions.com	misskudi	/dashboard	Yaba Flagship Plant Console; orders, roster & stock management.
FLOOR STAFF	tailor.uat@misskudi.com (Suite 04)	Atelier2026	/dashboard	Role-scoped Floor Station (My Work Queue, shift clock & batch logs).

B2B Quote Studio Promo Codes (Suite 02): `FIRSTBULK5` (5% off · min 50 pcs) · `LAGOSVIP10` (10% off · min 100 pcs) · `SCALE1000` (12% off · min 1,000 pcs).

3. Route & Role-Based Access Control (RBAC) Matrix

SECURITY BOUNDARIES

ROUTE PATH	LOGGED OUT	FLOOR STAFF	PLANT ADMIN	SUPERADMIN
/, /services, /process, /about	ALLOWED	ALLOWED	ALLOWED	ALLOWED
/size-charts, /quote	ALLOWED	ALLOWED	ALLOWED	ALLOWED
/login, /reset-password	SIGN-IN / OTP	Active + Change PW	Active + Change PW	Active + Change PW
/dashboard	Redirects → /login	Floor Station Only	Plant Admin Console	Plant Admin Console
/workspace, /tracker	Redirects → /login	Floor Updates	Full 5-Tab OS	Full 5-Tab OS
/superadmin	Redirects → /login	Blocked → /dashboard	Blocked → /dashboard	**Executive HQ**

4. Public Experience, Quote Studio & Authentication Suites

UAT-01 TO UAT-03

UAT-01 Public Editorial Atelier & Size Grading Matrix

`/` · `/services` · `/process` · `/about` · `/size-charts`

Verify public B2B brand storytelling, interactive 3D hero stage controls, legal pages, and size ratio persistence.

1. Open `/` and cycle through all stages of the **Fullscreen 3D Production Journey Hero** using the bottom dock buttons and next/previous controls.
2. Navigate across **Capabilities** (`/services`), **Process** (`/process`), and **Atelier** (`/about`) via the top header; verify zero broken images or layout shifts, plus footer legal routes (`/privacy-policy`, `/terms-and-conditions`, `/refund-policy`).
3. Open `/size-charts`, customize the **XS–XXL Size & Grading Matrix** quantities, and click the CTA to carry your saved size ratio into `/quote`.

Expected: Smooth 3D stage transitions; saved XS–XXL size breakdown banner appears automatically on `/quote`. **[ ] PASS [ ] FAIL**

UAT-02 B2B Quote Studio, Promo Codes & Printable Job Ticket

`/quote`

Validate live pro-forma NGN pricing, fabric yardage calculation, promo code thresholds, and Job Ticket generation.

1. On `/quote`, enter Company (e.g., *Lagos Resort Collective*), work email, phone, select **Dresses and womenswear**, and set quantity to **250** pieces. Confirm live unit cost, total NGN quote, and fabric meters update immediately.
2. Test promo validation: enter `SCALE1000` at 250 units (verify minimum-unit threshold prevents discount), then enter `LAGOSVIP10` and confirm the **10% VIP discount** applies cleanly.
3. Open the **XS–XXL size editor**, modify a size count (e.g., `M = 90`), and verify total unit quantity recalculates automatically.
4. Submit the brief. Click to open the generated **Factory Job Ticket** (`MKP-YYYYMMDD-NNN`) and inspect the print preview sheet.

Expected: Unique `MKP-...` Job Code logged at Stage 01; Job Ticket modal renders A4/80mm spec sheet cleanly. **[ ] PASS [ ] FAIL**

UAT-03 Streamlined Sign-In, 6-Digit OTP Reset & Session Security

`/login` · `/reset-password`

Verify the decluttered single-column Sign-In card, blur/input validation, 30-day persistence, OTP recovery, and route guards.

1. In an Incognito window, visit `/workspace` directly. Confirm immediate redirect to `/login?redirect=/workspace&reason=auth_required` with a clean status notice.
2. Verify `/login` renders a **clean, centered single-column Sign-In card** (zero right-hand CAD weave canvas or RBAC policy sidebar clutter).
3. Type an invalid email (`bad-email`) and tab out (**blur**) → inline error appears. Begin typing a correction → error clears immediately mid-keystroke. Test the **Show / Hide** password button.
4. Click **Forgot password?**, enter `kudi@kproductions.com`, and click **Send verification code**. Click **Fill code** in the Verification Preview box, enter a new password (8+ chars, letter + number, e.g., `MissKudi2026`), and submit.
5. Once signed in to `/dashboard`, visit `/login?mode=change-password`, switch between **Sign in** and **Change password**, rotate password back to `misskudi`, and click **Sign Out**.

Expected: Signed `HttpOnly` cookie issued (30d checked vs. 8h unchecked); OTP reset signs user in; Sign Out clears session. **[ ] PASS [ ] FAIL**

5. Role-Scoped Factory Console Test Suites

UAT-04 TO UAT-06

UAT-04 Superadmin Executive HQ, Facilities & Staff Provisioning

/superadmin

Test multi-plant governance across Yaba, Victoria Island & Ikeja, and provision a Floor Staff account for Suite 06.

1. Sign in at `/login` with `demolablaze@gmail.com` / `$0merta93`. Confirm automatic routing to `/superadmin`.
2. Review **Executive Summary** KPIs (consolidated GMV, OpEx, active orders, and 3-plant capacity cards). Toggle the collapsible left sidebar.
3. Open **Facilities**: edit machine count or fabric stock on a facility (e.g., Victoria Island Atelier) and save changes.
4. Open **Team & Access**: create a new account with email `tailor.uat@misskudi.com`, password `Atelier2026`, tier **Artisan / Floor Staff** (`staff`), and role **Master Tailor / Sewing Lead**. Test tier filter and search input.
5. Open **Audit Log** and search `tailor.uat` or your facility update to verify immutable event tracking.

Expected: All 4 HQ views update live; new Staff account persists with hashed credentials and logs in Audit Log. **[ ] PASS [ ] FAIL**

UAT-05 Plant Admin Console & Privilege Escalation Guard

/dashboard (Admin)

Verify Plant Admin operations across orders, branch switching, team roster, and fabric stock, plus Superadmin boundary enforcement.

1. Sign out, then sign in as Plant Admin (`kudi@kproductions.com` / `misskudi`). Attempt to visit `/superadmin` manually and confirm redirect back to `/dashboard?notice=superadmin_only`.
2. Switch active plant branches (**Yaba Flagship**, **Victoria Island**, **Ikeja**) and review **Overview** stock and order cards.
3. In **Production Orders**, create a manual floor order (200 pcs), confirm your Suite 02 quote inquiry appears, and open its Job Ticket.
4. In **Materials & Stock**, add a Fabric Roll SKU with `stockLevel = 120` below `reorderThreshold = 300` and toggle the **Low Stock** filter.

Expected: Admin blocked from `/superadmin`; orders, roster, and low-stock alerts update accurately per branch. **[ ] PASS [ ] FAIL**

UAT-06 Artisan / Floor Staff Workstation Experience

/dashboard (Staff)

Confirm Floor Staff receive a focused station tailored to their craft without administrative roster or branch mutation menus.

1. Sign out, then sign in with the Floor Staff account created in Suite 04 (`tailor.uat@misskudi.com` / `Atelier2026`).
2. Verify the sidebar adapts to **Station Overview**, **My Work Queue**, **All Plant Orders**, and **Materials Lookup** (no Team Roster management).
3. Toggle shift clock status between **CLOCKED_IN**, **BREAK**, and **OFF_SHIFT**, and log completed sewn/QC batch units on an active production run.

Expected: Role-scoped station renders cleanly; shift status and unit progress persist across page reloads. **[ ] PASS [ ] FAIL**

6. Pipeline OS, Mobile Ergonomics & Security Rate Limits

UAT-07 TO UAT-08

UAT-07 5-Stage Factory Workspace, Auto-PO, Finance & Order Tracker

/workspace · /tracker

Test end-to-end order stage progression (01 → 05), supplier Auto-PO generation, CRM tiers, OpEx P&L, and CSV/Z-Report exports.

1. Sign in as Admin or Superadmin and open `/workspace`. In **01. Production Floor & QC**, assign a Pattern Designer, Master Tailor, and QC Inspector to an active order.
2. Open **03. Fabric Runway & Auto-PO**: generate a Supplier Purchase Order for a low-runway SKU, then mark the PO as **Received** and verify stock replenishes.
3. Open **04. B2B Brand CRM & Tiers** to add a client, then open **05. Factory OpEx, P&L & Audit** to log an expense, inspect the **Z-Report** modal, and download **CSV Export**.
4. Open `/tracker`, filter by stage, advance an order from `01 Brief Received` through `05 Finished & Dispatched`, log +10 sewn units, and open the **AQL 2.5 QC Passport / Job Ticket**.

Expected: Stage transitions update sewn/QC counts and audit logs; Auto-PO increments stock; Z-Report & CSV export cleanly. **[ ] PASS [ ] FAIL**

UAT-08 Mobile Viewport (390×844), Accessibility & Rate Protection

390×844 · Keyboard · API

Validate mobile ergonomics, native dialog drawer dismissal, keyboard-only focus navigation, and brute-force protection.

1. Switch DevTools to `390×844` mobile viewport. Tap **Menu** in the header, verify the modal drawer opens, and tap outside or press `Esc` to confirm light-dismiss closes it.
2. Visit `/login` on mobile: confirm Email, Password, Remember checkbox, and **Sign in** button sit above the virtual keyboard zone with `16px` inputs (zero iOS zoom) and stacked cards on `/dashboard`.
3. Navigate `/login` and `/quote` via `Tab` / `Shift+Tab` / `Enter`; verify olive focus rings and `Skip to main content`. Optional: submit 5 wrong passwords on a test email to confirm the 15-minute lockout banner.

Expected: Zero horizontal overflow at `390px`; full keyboard operability; rate-limit & brute-force lockout enforced. **[ ] PASS [ ] FAIL**

7. UAT Defect Log & Release Sign-Off

APPROVAL LEDGER

DEFECT ID	SUITE / ROUTE	SEVERITY	OBSERVED BEHAVIOR & STEPS TO REPRODUCE	STATUS / OWNER

QA / TESTER NAME & SIGNATURE _____

PRODUCT / OPERATIONS LEAD APPROVAL _____

DATE · ENVIRONMENT · COMMIT SHA _____