Apps TELNET FTP SSH Web Server

Basic Network Applications

Jose L. Muñoz, Oscar Esparza, Juanjo Alins, Jorge Mata Telematics Engineering Universitat Politècnica de Catalunya (UPC)

Outline

Basic Net

Apps TELNET

ETD

SSH Web Server

Web Server Super Daemo

Basic Net Apps

Outline

Apps TELNET

SSH

Web Server Super Daemon

> 1 Basic Net Apps TELNET FTP SSH Web Server

Basic I Apps TELNET

SSH Web Server Super Daemo

What is TELNET?



- TELNET or TELecommunication NETwork is a standard Internet protocol for emulating a terminal in a remote host using a TCP/IP network.
- The TELNET service follows the client/server model.
- In Linux (and most Unix-like systems) the client is called telnet and the server is a daemon called telnetd.
- TELNET is a well-known service over TCP and its default port is 23.

TEL NET

Practical Telnet

Practical example:

```
$ telnet
telnet>open 192.168.0.1
```

or use parameters in the command-line:

```
$ telnet 192.168.0.1 23
```

- Once the connection is established, TELNET provides a bidirectional interactive text-oriented communication.
- The commands you type locally, are executed remotely in the host at the other end of the TCP/IP network.
- If at any moment you need to return to the telnet sub-shell, you can to type "CRL+ALTGR+]".
- · Because of security issues, the use of the telnet service has been reduced in favor of SSH (secure shell).

Outline

TELNET FTP SSH Web Server


1 Basic Net Apps
TELNET
FTP

SSH Web Server Super Daemo

Basic Ne Apps TELNET

SSH Web Server Super Daemo

What is FTP? I



- File Transfer Protocol (FTP) is a standard Internet protocol for transmitting files between computers (hosts) on the Internet.
- FTP uses TCP/IP and it is based on a client-server model.
- FTP utilizes separate control and data connections between the client and server.

What is FTP? II

- The default server port for control data is 21 and the default server port for data exchanging is 20.
- · The control connection remains open for the duration of the session and it is used for session administration (i.e., commands, identification, passwords) exchanged between the client and server.
- E.g. "RETR filename" would transfer the specified file from the server to the client.
- Due to this two-port structure, FTP is considered an out-of-band, as opposed to an in-band protocol such as TFI NFT
- The server responds on the control connection with three digit status codes in ASCII with an optional text message.
- E.g. "200 OK" means that the last command was successful.

Apps
TELNET
FTP
SSH
Web Server

Active and passive modes

- FTP can be run in active or passive mode, which determine how the data connection is established:
 - In active mode, the client sends the server the IP address and port number on which the client will listen, and the server initiates the TCP connection. In situations where the client is behind a firewall and unable to accept incoming TCP connections, passive mode may be used.
 - In passive mode, the client sends a PASV command to the server and receives an IP address and port number in return. The client uses these to open the data connection to the server.

Practical FTP I

- The ftp client supports active and passive mode, ASCII and binary transmissions and only stream mode.
- To connect to a ftpd server, we can use one of the following options:

```
ftp 192.168.0.1
ftp user@192.168.0.1
```

- To establish an FTP session you must know the ftp username and password.
- When you enter your own loginname and password, it returns the prompt "ftp>". This is a sub-shell in which you can type several subcommands.
- As summary of these subcommands is shown in following Table.

TELNET FTP SSH

SSH Web Server Super Daemo

Practical FTP II

open	opens an FTP session.
close	closes and FTP session.
quit	exits ftp.
rmdir	removes a directory in the server.
mkdir	creates a directory in the server.
delete	removes files in the server.
get	downloads a file from the server to the client.
mget	downloads multiple files from the server.
put	uploads a file from the client to the server.
mput	uploads multiple files from the client to the server.
type ascii	selects ascii mode.
type binary	selects binary mode.
!	executes a command in the local shell.
cd	remotely change directory (in the server).
lcd	locally change directory (in the client).
ls	lists files in the remote directory.
!ls	lists files in the local directory.
pwd	print remote working directory.
!pwd	print local working directory.
verbose	show debug info.
status	show the configuration parameters.
help	help.
-	

Apps
TELNET
FTP
SSH
Web Server
Super Daemo

Practical FTP III

- To use the ftp client in passive mode (default is active mode) you can type either ftp -p or pftp.
- Finally, it is worth to mention that you can also use FTP through a Browser (and also with a several available graphical applications).
- Browsers such as Firefox allow typing the following in the URL bar:

```
ftp://ftp.upc.edu
ftp://ftpusername@ftp.upc.edu
ftp://ftpusername:password@ftp.upc.edu
```

Outline

TELNET

SSH

1 Basic Net Apps

TELNET

FTP

SSH

Web Server


Basic Ne Apps TELNET

SSH

Web Server Super Daemor

Features of SSH

 The SSH protocol is used to obtain an encrypted end-to-end TCP connection between a client (ssh) and a server (sshd) over a TCP/IP network.



- The sshd daemon listens to port 22 TCP by default.
- This encrypted connection can be used to build serveral services

Basic Ne Apps TELNET

SSH

Web Server Super Daemor

Remote Terminal

- The ssh client can be used to connect to a sshd server to obtain a remote terminal.
- Same idea as TELNET, but secure.

```
user1$ ssh 192.168.0.1
```

 If you want to use a different user for login on the remote host, simply use remoteusername@hostname:

```
user1$ ssh user2@192.168.0.1
```

Basic Net Apps TELNET

SSH

Web Server Super Daemon

Secure Copy (SCP) I

- scp is a client program that uses the SSH protocol to send and receive files over an encrypted SSH connection.
- You can transfer files from the client to the server and vice versa.
- Client to server:

```
$ scp file.txt username@remotehost:
```

```
$ scp file.txt username@remotehost:anothername.txt
```

 If you want to copy a file to a directory relative to the home directory you can type:

```
$ scp file.txt username@remotehost:mydirectory/anothername.txt
```

Basic Net Apps TELNET

SSH

Web Server Super Daemo

Secure Copy (SCP) II

 You can also use absolute paths typing "/" after the colon.

```
$ scp file.txt username@remotehost:/tmp
```

 To recursively copy a directory to the server use the "-r" option.

```
$ scp -r Documents username@remotehost:
```

 To copy from the server to the client just reverse the from and to:

```
$ scp username@remotehost:file.txt .
```

Basic Ne Apps TELNET

SSH

Web Server

Secure File Transfer Protocol (SFTP) I

- SFTP is a secure implementation of the traditional FTP protocol using a SSH session.
- Let us take a look at how to use the sftp command:

```
$ sftp user@hostname
```

For example:

```
user@192.168.0.1:~$ sftp 192.168.0.2
Connecting to 192.168.0.2...
user@192.168.0.2's password:
sftp> cd django
sftp> 1s -1
drwxr-xr-x 2 user user 4096 Apr 30 17:33 website
sftp> cd website
sftp> ls
__init__.py __init__.pyc manage.py settings.py settings.pyc
urls.py urls.pyc view.py view.pyc
sftp> get manage.py
Fetching /home/user/django/website/manage.py 100% 542 0.5KB/s 00:01
sftp>
```

Basic No Apps TELNET

SSH

Web Server Super Daemor

Secure File Transfer Protocol (SFTP) II

- Some of the commands available under sftp are:
 - cd. Changes the current directory on the remote machine.
 - lcd. Changes the current directory on localhost.
 - 1s. Lists the remote directory contents.
 - lls. Lists the local directory contents.
 - put. Send/upload files to the remote machine from the current working directory of the localhost. Supports wildcards for choosing files based on patterns (like *).
 - get. Receive/download files from the remote machine to the current working directory of the localhost.
 Supports wildcards for choosing files based on patterns (like *).

Start/Stop sshd

- The configuration of the sshd server is /etc/ssh/sshd config.
- If you change the configuration of the daemon you have to stop and start it to apply the changes.
- Under Debian Linux use the script under the directory /etc/init.d:

```
# /etc/init.d/ssh stop
```

To start the daemon type:

```
# /etc/init.d/ssh start
```

Outline

Basic Net Apps TELNET

Web Server Super Daemon

> 1 Basic Net Apps TELNET FTP SSH Web Server

Basic No Apps TELNET FTP

Web Server Super Daemo

WEB Servers

- HTTP servers (or WEB servers) listen by default to TCP port 80.
- The "Apache WEB server" is widely spread.
- Current version is apache2.
- Debian-based distros store the Apache 2.0 configuration files in the directory /etc/apache2.
- The file ports.conf contains the Listen directives telling apache2 what IP address and port to listen to.
- In the configuration files of the WEB server, we can also find a parameter called "Document Root", which tells us where we can find the WEB resources.
- Typically, the Document root for apache2 is /var/www.
- In this directory we can find a file called index.html that is an HTML file that contains the initial WEB page of the server.

Basic Net
Apps
TELNET
FTP
SSH
Web Server

WEB Browsers (clients)

- To access to the resources of a WEB server you have to use a WEB browser.
- The WEB browser is the client application of this service.
- We will use firefox (graphical browser) and lynx (textual browser).
- With firefox you have to type in the URL bar the address of the server.
- For example: http://10.1.1.1.
- Using lynx you can type in a terminal the following command to access to a WEB server:

```
$ lynx http://10.1.1.1
```

Basic Net
Apps
TELNET
FTP
SSH
Web Server

Start/Stop apache2

- If you change the configuration of the daemon you have to stop and start it to apply the changes.
- As most of the network daemons, apache2 can be started and stopped under Debian Linux using a script under the directory /etc/init.d.
- In particular, to stop apache2 type:

```
# /etc/init.d/apache2 stop
```

To start the daemon type:

```
# /etc/init.d/apache2 start
```

Outline


Apps
TELNET
FTP
SSH
Web Server
Super Daemon

1 Basic Net Apps
TELNET
FTP
SSH
Web Server
Super Daemon

Apps
TELNET
FTP
SSH
Web Server
Super Daemon

What is inetd

- The inetd server is sometimes referred to as the Internet "super-server" or "super-daemon" because inetd can manage connections for several services.
- When a connection is received by inetd, it determines which program the connection is destined for.
- Spawns the particular process and delegates the socket to it.



Apps
TELNET
FTP
SSH
Web Server
Super Daemon

An inetd Service I

- The main configuration file is /etc/inetd.conf.
- Let's configure the service "my-echo" on port 12345.
- Let's add the following line in /etc/inetd.conf:

```
my-echo stream tcp nowait root /root/my-echo.sh
```

You can restart the inetd super-daemon with:

```
# /etc/init.d/openbsd-inetd reload
```

 Restart inetd and observe the log file where inetd writes its messages (in a Debian system is /var/log/daemon.log).

Apps
TELNET
FTP
SSH
Web Server
Super Daemon

An inetd Service II

 Taking a look at the log file you will observe it is complaining about the port name:

```
# tail -f /var/log/daemon.log
inetd[1173]: my-echo/tcp: unknown service
```

- Let's add the port number for our service "my-echo" in the file /etc/services.
- The file /etc/services is the system file to map a port number/protocol to a service name.
- In this example, we will add the following line to /etc/services:

```
my-echo 12345/tcp # By telematics
```

Restart inetd and try to connect to the service.

Apps
TELNET
FTP
SSH
Web Server

Super Daemon

An inetd Service III

Let's observe the log file:

```
# tail -f /var/log/daemon.log
execv /root/my-echo.sh: No such file or directory
```

Create the file my-echo.sh with the following content:

```
cat
```

- The command cat without parameters reads writes to STDOUT what it reads from STDIN.
- Try to connect to the service and observe the log file:

```
# tail -f /var/log/daemon.log
inetd[1204]: execv /root/my-echo.sh: Permission denied
```

Apps
TELNET
FTP
SSH
Web Server
Super Daemon

An inetd Service IV

Give permissions to the script:

```
# chmod u+x /root/my-echo.sh
```

Try to connect to the service and observe the log file:

```
# tail -f /var/log/daemon.log
inetd[1207]: execv /root/my-echo.sh: Exec format error
```

 We need a script "formally correct", to do so, you must include the initial line with the corresponding interpreter (/bin/bash in our example):

```
#!/bin/bash
cat
```

Apps
TELNET
FTP
SSH
Web Server
Super Daemon

Stand-alone vs. inetd Services

Stand-alone:

 When a daemon is started stand-alone it must open its service port for listening and manage incoming service requests.

• inetd:

- When a service is managed with inetd, the server program can just use STDIN and STDOUT, which are inherited from inetd.
- In this case, as mentioned, the server program does not need any specific code to manage the network.
- Check our echo service: open two clients with netcat and check the open files of inetd and of the processes executed by inetd.