
Command Reference: PrintTextFile()

Print a text file

The PrintTextFile() command prints a text file to a physical or virtual (e.g., PDF file) printer. This command is used in testing to verify print features but also can be used in production to automate printing. Printing is highly dependent on the features available from a printer. The command attempts to list printer options to configure command parameters. However, some options are listed based on what a printer can do, but this may require physically changing/selecting paper trays, using manual feed, etc. The command will be enhanced in the future to specify features including tray selection but currently it is intended for use with common printer settings. If advanced settings are needed beyond the properties available in the command, use ShowDialog=True (displaying the dialog will pause command execution).

The following dialog is used to edit the command and illustrates the syntax for the command (in this case printing to a Microsoft XPS file).



PrintTextFile() Command Editor


The command syntax is as follows:

PrintTextFile(Parameter=Value,...)

Command Parameters

Parameter	Description	Default
InputFile	The name of the text file to print.	None – must be
		specified.
PrinterName	The name of the printer to use (e.g.,	The default printer
	\\MyComputer\MyPrinter or Adobe PDF)	will be used.
PaperSize	The paper size to print. Because there are a number of	The default for the
	standards for paper, the size is specified as standard-	printer will be used.
	sizename (e.g., na-letter for North American Lettter).	
	For information on paper sizes, see:	
	http://en.wikipedia.org/wiki/Paper_size.	
PaperSource	The tray for the paper – currently not enabled. Use	The PaperSize is
	ShowDialog=True to select.	used.
Orientation	The paper orientation.	The default for the
		printer and paper size
		will be used.
MarginLeft	The left margin for the orientation, inches.	See above.
MarginRight	The right margin for the orientation, inches.	See above.
MarginTop	The top margin for the orientation, inches.	See above.
MarginBottom	The bottom margin for the orientation, inches.	See above.
LinesPerPage	The number of lines per page to print. The font size is	An even number is
	chosen accordingly.	chosen with font size
		between 7 and 12
		points.
Header	String included in the top left of every page.	No header is shown.
Footer	String included in the bottom left of every page.	No footer is shown.
ShowLineCount	Indicate whether the line count should be shown to the left	False
	of each line.	
ShowPageCount	Indicate whether the page count should be shown in the	True
	center of the footer.	_
DoubleSided	Indicate whether printing should be double-sided, currently	False
	not enabled. Use ShowDialog=True to select.	
OutputFile	Specify an output file, in cases where the printer name	Content is sent to
	corresponds to a file formatter (such as Adobe PDF).	printer device, not a
-1 -1 -		file.
ShowDialog	Indicate whether to show the printer dialog, which allows	False
	review and editing of printer parameters. This is useful for	
	testing and for selecting advanced printer features not	
T CATAL TO 3	handled in batch mode by this command.	T
IfNotFound	Indicate action if the file is not found, one of:	Ignore
	• Ignore – ignore the missing file (do not warn).	
	• Warn – generate a warning (use this if the file truly is	
	expected and a missing file is a cause for concern).	
	• Fail – generate a failure (use this if the file truly is	
	expected and a missing file is a cause for concern).	


This command can be used to test print features. For example, use a printer that outputs to a PDF, XPS, or other format file rather than a physical printer. If ShowDialog=True and printing to a file is indicated by specifying the OutputFile parameter (such as with Adobe PDF), the *General* tab on the print dialog will be similar to the following:



PrintTextFile_DialogGeneral

Print Job Dialog General Properties


Note that **Print to File** is checked; however, the name of the file may not be displayed. Instead, the output file is specified by pressing **Print**, which displays the following dialog, with the initial choice matching the value of the OutputFile parameter:



Print To File Dialog

PrintTextFile_PrintToFile

If running a command to write a PDF file, the following may be displayed:



Adobe PDF Error

PrintTextFile_DistillerFontError

Unfortunately, there does not seem to be any way to change the printer setting from the print dialog and consequently PDF cannot be used. An alternate approach such as iText may be implemented for PDF.

If a Microsoft XPS file is printed, the following software may need to be installed, in particular for Windows XP: http://www.microsoft.com/download/en/details.aspx?displaylang=en&id=11816