



ORACLE SCM TRACK

Security Locator Implementation Guide



Prepared by: Ahmed Mohamed Sameh

Date: AUG 20, 2025

AHMED MOHAMED SAMEH

ORACLE SCM TRACK

Security Locator

. Introduction

The Security Locator is one of the most critical keys in Oracle Fusion Security. It plays a fundamental role in controlling access and ensuring that users only interact with the data and functions that are directly related to their responsibilities.

One of the main benefits of Security Locator is that it eliminates the need to always create multiple In-Organization responsibilities. Instead, organizations can define one organization that serves multiple users, while ensuring that each user is restricted to viewing only the locator(s) assigned to them. This provides a much more efficient and secure approach to managing access.



By using Security Locator in this way, enterprises achieve:

- **Flexibility:** Simplified security design without unnecessary duplication.
- **Data Security:** Users cannot view or access locators outside of their granted scope.
- **Efficiency:** Reduced complexity in security setup and maintenance.

This document highlights the importance of Security Locator, how it streamlines access control, and its role in building a secure and well-structured enterprise environment

Step 1: Copy an Existing Role from Security Console

1. Navigate **Tools** to **Security Console** in Oracle Fusion.
2. From the **Roles** tab, **search** for the required base role (the role you want to use as a template).
3. Select the role, then click **Copy Role**.
4. Provide a new **Role Name** and **Code** for the copied role.
5. Do **Next** → **Next** → **Next** → **Finish** without adding or modifying any privileges or data security policies.
 - This ensures you now have a clean **Base Role** identical to the original, ready for customization with Security Locator



SAVOLA | الأغذية Foods Dev

1 Basic Information 2 Function Security Policies 3 Data Security Policies 4 Role Hierarchy 5 Segregation of Duties 6 Users 7 Summary

New Role SFC-SAR Custom: Basic Information

Back Next Cancel

1 Role Name SFC-SAR Custom

2 Role Code SFC-SAR_CUSTOM

Role Category SCM - Job Roles

Predefined Role ☐

Description AS

Step 2: Navigate to Manage Inventory Value Set

1. From the home page, go to **Setup and Maintenance**.
2. In **Offering**, select **Manufacturing and Supply Chain Materials Management (SCM)**.
3. Under the **Manufacturing** area, navigate to **Inventory Management**.
4. Open the task **Manage Inventory Value Sets**.

SAVOLA | Foods Dev

1 Setup: Manufacturing and Supply Chain Materials Management

Actions

Functional Areas Change Feature Opt In

* Legal Structures Shared

* Financial Reporting Structures Shared

* Organization Structures Shared

* Customers Shared

* Suppliers Shared

* Facilities Shared

* Users and Security Shared

* Items Shared

Carriers and Transit Times

* Catalogs Shared

2 Inventory Management

Receiving Shared

* Shipping

Search Tasks


Inventory Management

View Format Freeze Detach Wrap Show All Tasks

Task	Scope	Actions
3 Manage Inventory Value Sets		
Manage Inventory Descriptive Flexfields		
Manage Inventory Account Alias Key Flexfield		
Manage Inventory Locator Key Flexfield		
Inventory Transaction Sources and Types		
Manage Inventory Transaction Sources and Types		
Material Statuses		
Manage Material Statuses		
Manage Subinventories and Locators		
Units of Measure Usages		
Columns Hidden 3		

Step 3: Create a New Value in Locator Segment 1 Value Set

1. Inside **Inventory Management**, open **Manage Inventory Value Sets**.
2. From the list, select the **Value Set** named **Segment 1**.
3. Navigate to the **Values** section.
4. Click + **(Add)** to create a new value.
5. Enter the **Value Name** → for example: **"SAR"**.
6. Save your changes.



Manage Inventory Value Sets

Search

Value Set Code
Validation Type
Value Data Type
Module: Inventory Management (1)
Description

Search (2) Reset

Search Results

Actions View Format + Freeze Detach Wrap Manage Values (4)

Value Set Code	Protected	Description	Module	Validation Type	Value Data Type
Agro Contract	—		Inventory Management	Independent	Character
Contract number	—		Inventory Management	Independent	Character
Daka-Yasmi	—		Inventory Management	Independent	Character
EGP_E_Invoice	—		Inventory Management	Independent	Character
Locator Segment 1 Value Set	—	Security Enabled Locator Segment 1 Value Set	Inventory Management	Independent	Charac



Manage Values

Value Set Code: Locator Segment 1 Value Set
Description: Security Enabled Locator Segment 1 Value Set

Search

Search Results

Actions View Format + (1) Freeze Detach Wrap

* Value: SAR (2) Description

Value Set Values

Value	Description	Unit	Category	Context Value
SAR				

Columns Hidden 1

Step 4: Assign Security Locator in Subinventory

- From the **Setup and Maintenance** work area, navigate to:
 - Manufacturing and Supply Chain Materials Management (SCM) → Inventory Management.**
- Open **Manage Subinventories and Locators.**
- Search for the **Subinventory** you want to configure.
- Select the subinventory, then click on **Manage Locators.**
- In the **Locator Setup**, click + **(Add)** to create a new locator.
- For the locator definition, in the **Segment (e.g., Segment 1)** field, select the **Value Set** you created earlier (e.g., " **SAR** ").
- Save your changes

Setup: Manufacturing and Supply Chain Materials Management

Functional Areas

- Legal Structures
- Financial Reporting Structures
- Organization Structures
- Customers
- Suppliers
- Facilities
- Users and Security
- Items
- Carriers and Transit Times
- Catalogs
- Inventory Management**

Inventory Management

Task

- Manage Subinventories and Locators**
- Units of Measure Usages
- Manage Units of Measure Usages
- Inventory ABC Analysis
- Manage ABC Classes
- Manage ABC Classification Sets
- Manage ABC Assignment Groups
- Interorganization Parameters
- Manage Interorganization Parameters
- Interorganization Parameters

Manage Subinventories

Inventory Organization: PASTA_PLANT

Search

Search Results

Actions View Manage Item Subinventories **Manage Locators**

Subinventory	Description	Active	Material Status	Locator Control	Subinventory Type	Additional Information	To Date
DEPOT 4	DEPOT 4	✓	Active	Previously defined	Storage		
Agro	Agro	✓	Active	Previously defined	Storage		
DECN	Decantation	✓	Active	Previously defined	Storage		
DECN-EXP	Decantation Expense Subinventory for Decn_items	✓	Active - No Sales Issue and Pick	None	Storage		
DEPOT 1	DEPOT 1	✓	Active	Previously defined	Storage		
DEPOT 2	DEPOT 2	✓	Active	Previously defined	Storage		
DEPOT 3	DEPOT 3	✓	Active	Previously defined	Storage		
FG	Finished Goods	✓	Active	Previously defined	Storage		

Manage Locators ?

Search

Search Results

Actions View **+**  

Create Locator

Subinventory FG

Locator Structure Four-Segment Locator Structure Instance

Aisle **SAR** 

Row 1

Rack 1

Bin 1

Description

To Date dd-mmm-yyyy 

Type 

Picking Order

* Material Status Active 

Context 

Save and Create Another **Save and Close** Cancel

2 SELECT THE VALUE THAT WE CREATED BEFORE

3

SAVOLLA | الأغذية
SAVOLLA Foods Dev

Manage Locators ?

Search

Search Results

Actions View   

Locator				Description	Active	Type	Material Status	Subinventory	Additional Information
Aisle	Row	Rack	Bin						
SAR	1	1	1		✓		Active	FG	
FG	2	2	2		✓		Active	FG	
SONA	5	5	5		✓		Active	FG	

AR.1.1.1: Locator Details

In This sub. inventory there is 3 locators and only one will appear to the user

Description

Locator Structure Four-Segment Locator Structure Instance

Subinventory **FG**

Picking Order

Material Status Active

Type

To Date

Step 5: Define Condition and Policy for Locator Value Set

1. Navigate again to **Manage Inventory Value Sets**.
2. Open the **Locator Segment 1 Value Set**.
3. Click **Edit** to modify the value set.
4. Go to the **Security** tab.
5. Create a new **Condition**:
 - Define the condition that filters access (e.g., users with the value " SAR ").
6. Create a new **Policy**:
 - In the policy setup, **call the custom role** you created/copied earlier.
 - Link the **Condition** you just created to this policy.
7. Save the changes.

👉 At this point, the **Policy** ensures that only users with the assigned custom role can access the locator that matches the condition (e.g., " SAR ")

Manage Inventory Value Sets ①

Save Save and Close Cancel

Search

** Value Set Code

** Validation Type

** Value Data Type

** Module ⓘ

** Description

** At least one is required

Search Reset ⓘ

Search Results

Actions View Format + - Freeze Detach Wrap Manage Values

Value Set Code	Protected	Description	Module	Validation Type	Value Data Type
Agro Contract	—		Inventory Management	Independent	Character
Contract number	—		Inventory Management	Independent	Character
Daka-Yasmi	—		Inventory Management	Independent	Character
EGP_E_Invoice	—		Inventory Management	Independent	Character
Locator Segment 1 Value Set	—	Security Enabled Locator Segment 1 Value Set	Inventory Management	Independent	Character

Edit Value Set: Locator Segment 1 Value Set ⓘ

Manage Values Save Save and Close

Value Set Code Locator Segment 1 Value Set
Description Security Enabled Locator Segment 1 Value Set
* Module Inventory Management
Validation Type Independent
Value Data Type Character

☒ Security enabled

* Data Security Resource Name Locator_Segment_1_Resource

Edit Data Security

Definition

Value Subtype Text

* Maximum Length 10

Minimum Value

Maximum Value

☐ Uppercase only

Edit Data Security: Locator_Segment_1_Resource

Save Submit Cancel

Condition Policy				
Actions View Format + ✎ ✕ Freeze Detach Wrap				
Name	Display Name	Description	Sql Predicate	Filter
SFC FG-Mud Access Condition	SFC FG-Mud Access Condition		FILTER	
SFC FG-SILO Access Condition	SFC FG-SILO Access Condition		FILTER	
SFC EXT-WHS Access Condition	SFC EXT-WHS Access Condition		FILTER	
SFC FG-MOLASES Access Condition	SFC FG-MOLASES Access Condition		FILTER	
SFC FG-Dammam Access Condition	SFC FG-Dammam Access Condition		FILTER	
SFC RM-CHM-UTL Access Condition	SFC RM-CHM-UTL Access Condition		FILTER	
SFC RM-PKG-FPD Access Condition	SFC RM-PKG-FPD Access Condition		FILTER	
SFC WIP-UTL Access Condition	SFC WIP-UTL Access Condition		FILTER	
SFC FG-FPD Access Condition	SFC FG-FPD Access Condition		FILTER	
SFC LSC-RYD Access Condition	SFC LSC-RYD Access Condition		FILTER	

dition Policy

itions View Format + ✎ ✕ Freeze ✎ Detach Wrap

Name	Display Name
SFC_FGMM_SUBINVENTORY_LO...	SFC_FGMM_SUBINVENTORY...
SFC_PKG_M Access Condition	SFC_PKG_M Access Condition
SFC WIPPK_M Access Condition	SFC WIPPK_M Access Condition
SFC FGD_M Access Condition	SFC FGD_M Access Condition
SUPER USER Access Condition	SUPER USER Access Condition
SFC 3PL-JED Access Condition	SFC 3PL-JED Access Condition
SFC FG-Riyadh Access Condition	SFC FG-Riyadh Access Condition
SAR CONDITION	SAR CONDITION
SFC FG-EXPORT Access Condition	SFC FG-EXPORT Access Condition
SONA CONDETION	SONA CONDETION

* Name SAR CONDITION

* Display Name SAR CONDITION

Description

Condition Type ☒ Filter ☐ SQL predicate

Match ☒ All ☐ Any

Conditions

Actions View Format + ✎ ✕ Freeze ✎ Detach Wrap

* Column Name	Tree Operators	* Operator	* Value
VALUE		Equal to	SAR

Save Cancel

Edit Data Security: Locator_Segment_1_Resource

Save Submit Cancel

Condition Policy

Actions View Format + - Freeze Detach Wrap

Name	Display Name	Description	Sql Predicate	Filter
SFC_FGMM_SUBINVENTORY_LO...	SFC_FGMM_SUBINVENTORY_LOCATOR_S...		FILTER	
SFC_PKG_M Access Condition	SFC_PKG_M Access Condition		FILTER	
SFC WIPPK_M Access Condition	SFC WIPPK_M Access Condition		FILTER	
SFC FGD_M Access Condition	SFC FGD_M Access Condition		FILTER	
SUPER USER Access Condition	SUPER USER Access Condition		FILTER	
SFC 3PL-JED Access Condition	SFC 3PL-JED Access Condition		FILTER	
SFC FG-Riyadh Access Condition	SFC FG-Riyadh Access Condition		FILTER	
SAR CONDITION	SAR CONDITION		FILTER	
SFC FG-EXPORT Access Condition	SFC FG-EXPORT Access Condition	Condition to L...	FILTER	
SONA CONDETION	SONA CONDETION	SONA CON...	FILTER	

t Data Security: Locator_Segment_1_Resource

Save Submit Cancel

idition Policy

ctions View Format + - Freeze

Policy	Role
SFC WIP-UTL Access Condition	SFC_WIP-UTL_SUBINVENTORY...
SFC FG-MOLASES Access Condi...	SFC_FG-MOLASES_SUBINVENT...
SFC FGMM	SFC_FGMM_SUBINVENTORY_L...
SAR POLICY	SFC-SAR
SONA POLICY	SFC-SAR
SFC RM-CHM-R&D Access Condit...	SFC_RM-CHM-RD_SUBINVENTO...
SFC RM-PKG-RTL Access Condition	SFC_RM-PKG-RTL_SUBINVENT...
SFC WIP-FPD Access Condition	SFC_WIP-FPD_SUBINVENTORY...
SFC WIP-RTL Access Condition	SFC_WIP-RTL_SUBINVENTORY...
SFC FG-Mud Access Condition	SFC_FG-MUD_SUBINVENTORY...

Create Policy

General Information Role Rule

Select and Add: Roles

Search

Role Name SFC-SAR Application fscm Search

Name

Description

SFC-SAR

AS

Apply OK Cancel

Save and Close Cancel

t Data Security: Locator_Segment_1_Resource

Save Submit Cancel

idition Policy

ctions View Format + - Freeze

Policy	Role
SFC WIP-UTL Access Condition	SFC_WIP-UTL_SUBINVENTORY...
SFC FG-MOLASES Access Condi...	SFC_FG-MOLASES_SUBINVENT...
SFC FGMM	SFC_FGMM_SUBINVENTORY_L...
SAR POLICY	SFC-SAR
SFC RM-CHM-R&D Access Condit...	SFC_RM-CHM-RD_SUBINVENTO...
SFC RM-PKG-RTL Access Condition	SFC_RM-PKG-RTL_SUBINVENT...
SFC WIP-FPD Access Condition	SFC_WIP-FPD_SUBINVENTORY...
SFC WIP-RTL Access Condition	SFC_WIP-RTL_SUBINVENTORY...
SFC FG-Mud Access Condition	SFC_FG-MUD_SUBINVENTORY...
SFC RM-PKG-FPD Access Condition	SFC_RM-PKG-FPD_SUBINVENT...

Create Policy

General Information Role Rule

Row Set Multiple Values

Condition

Description

Pick a Set of Database Row

SAR

Select a Set of Database Rows for the Policy by clicking on the row below.

Display Name

Description



SAR CONDITION

OK Cancel

Save and Close Cancel

Step 6: Assign Role to User and Test Access

1. Navigate to **Security Console**.
2. Search for the user you want to grant access.
3. Assign the custom role (e.g., **SFC-SAR**) to user name **SAMEH.HATEM**.
4. Save the changes and have the user log in again to refresh their roles.
5. To validate the setup, go to **Inventory Management** → **Create Miscellaneous Transaction**.
6. In the transaction screen, check the **Locator field**:
 - The user should only see the locator(s) allowed by the policy (e.g., the one with value " SAR ").
 - Other locators should be hidden from this user



Company Single Sign-On

or

User ID

SAMEH.HATEM

Password

••••••••

[Forgot Password](#)

Sign In

SAVOLLA

الأغذية
Foods

Dev

Search

SA

Good evening, SAMEH HATEM

[Conflict of Interest](#) [Succession Planning](#) [My Client Groups](#) [Order Management](#) [Supply Chain Execution](#) [Product Manager](#) >

QUICK ACTIONS

Production Calendar

Manufacturing Work Center Resource Calendar

Show More

APPS


Quality Management

Inventory Management (Classic)

Supply Orchestration


+

Things to Finish



Important Note

When navigating through Subinventories, the user will only be able to view the locators within the Subinventory explicitly granted through the **Security Locator** policy. Any other Subinventories or locators will remain hidden, ensuring that access is strictly limited to the defined scope



Use Case

Although the **FG Subinventory** contains three locators, only one locator (**SAR**) has been assigned to the user through the Security Locator setup. Consequently, when the user accesses the FG Subinventory, they will only be able to view and transact against the **SAR locator**, while the other locators remain hidden

Thank You