

TYPICAL ELEMENTS AND CLASSES

Copyright © 2017 Liferay, Inc.
All Rights Reserved.
No material may be reproduced electronically or in print, distributed, copied, sold, resold, or otherwise exploited for any commercial purpose without express written consent of Liferay, Inc.

PORYGON LAYOUT TEMPLATE SOURCE

Let's take a look at the Porygon Layout source code.

```
<div class="porygon-50-50-width-limited" id="main-content" role="main">
  <div class="portlet-layout row">
    <div class="col-md-2 portlet-column portlet-column-first" id="column-1">
      $processor.processColumn("column-1", "portlet-column-content
      portlet-column-content-first")
    </div>
    <div class="col-md-4 portlet-column" id="column-2">
      $processor.processColumn("column-2", "portlet-column-content")
    </div>
    <div class="col-md-4 portlet-column" id="column-3">
      $processor.processColumn("column-3", "portlet-column-content")
    </div>
    <div class="col-md-2 portlet-column portlet-column-last" id="column-4">
      $processor.processColumn("column-4", "portlet-column-content
      portlet-column-content-last")
    </div>
 </div>
</div>
```

COLUMN ELEMENTS AND CLASSES

Let's take a closer look at the first column of the previous example and the various elements it consists of.

```
<div class="col-md-2 portlet-column portlet-column-first" id="column-1">
    $processor.processColumn("column-1", "portlet-column-content
    portlet-column-content-first")
</div>
```

- You'll notice three things that we'll work through:
 - 1. The id
 - 2. The classes
 - the \$processor.processColumn



COLUMN CONTAINER

- ▶ The id: column-1
 - Unique identifier for the column that matches ID passed to \$processor.processColumn.
- ➤ Classes: col-md-2
 - This class comes from Bootstrap's grid system and determines two things: the percentage-based width of the element, and the media query breakpoint for when this element expands to 100% width.
 - ▶ 12 is the maximum amount, so col-md-2 indicates 2/12 width, or 16.66%.
- Classes portlet-column portlet-column-first
 - All column containers should have the portlet-column class.
 - ▶ For rows with more than one column, the first column will have portlet-column-first and the last will have portlet-column-last.
 - For rows with only one column, the column will have the portlet-column-only class.



INSIDE \$PROCESSOR.PROCESSCOLUMN

- \$processor.processColumn is necessary to render our layouts.
- The \$processor.processColumn function takes the CSS column ID and the list of CSS classes as its two arguments.
 - \$processor.processColumn: column-1
 - Unique identifier; should match ID of the parent div
 - \$processor.processColumn: portlet-column-content
 portlet-column-content-first
 - Additional classes added to the content element; classes match the parent div's classes with -content appended



MODIFYING TEMPLATE BREAKPOINTS

When looking at the example template, you'll notice this Bootstrap grid class used on every column.

```
col-md-{size}
```

- The different sizes available are xs, sm, md, and 1g.
 - The medium size is used by default, but the others can be used in layout templates as well.
 - For example, setting the column classes to col-lg-{size} means the columns would expand to 100% width at a larger screen width than col-md-{size}.
 - > These classes can also be mixed to achieve more advanced layouts.

BREAKPOINT EXAMPLE

- In this example row, on medium-sized view ports (such as a tablet), column-1 will be 33.33% width.
- > column-2 will be 66.66% width.
- On small-sized view ports, both column-1 and column-2 will be 50% width.



