

MATLAB®


The Language of Technical Computing

Computation

Visualization

Programming

MATLAB Function Reference
Volume 2: F - O
Version 6



How to Contact The MathWorks:



www.mathworks.com
comp.soft-sys.matlab

Web
Newsgroup



support@mathworks.com
suggest@mathworks.com
bugs@mathworks.com
doc@mathworks.com
servi ce@mathworks.com
[info@mathworks.com](mailto:i nfo@mathworks.com)

Technical support
Product enhancement suggestions
Bug reports
Documentation error reports
Order status, license renewals, passcodes
Sales, pricing, and general information



508-647-7000

Phone



508-647-7001

Fax



The MathWorks, Inc.
3 Apple Hill Drive
Natick, MA 01760-2098

Mail

For contact information about worldwide offices, see the MathWorks Web site.

MATLAB Function Reference Volume 2: F - O

© COPYRIGHT 1984 - 2001 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by or for the federal government of the United States. By accepting delivery of the Program, the government hereby agrees that this software qualifies as "commercial" computer software within the meaning of FAR Part 12.212, DFARS Part 227.7202-1, DFARS Part 227.7202-3, DFARS Part 252.227-7013, and DFARS Part 252.227-7014. The terms and conditions of The MathWorks, Inc. Software License Agreement shall pertain to the government's use and disclosure of the Program and Documentation, and shall supersede any conflicting contractual terms or conditions. If this license fails to meet the government's minimum needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to MathWorks.

MATLAB, Simulink, Stateflow, Handle Graphics, and Real-Time Workshop are registered trademarks, and Target Language Compiler is a trademark of The MathWorks, Inc.

Other product or brand names are trademarks or registered trademarks of their respective holders.

Printing History:	December 1996	First printing	(for MATLAB 5)
	June 1997	Revised for 5.1	(online version)
	October 1997	Revised for 5.2	(online version)
	January 1999	Revised for Release 11	(online version)
	June 1999	Printed for Release 11	
	March 2000	Beta	(online only)
	June 2001	Revised for 6.1	(online version)

Functions By Category

1

Development Environment	1-3
Starting and Quitting	1-3
Command Window	1-3
Getting Help	1-4
Workspace, File, and Search Path	1-4
Programming Tools	1-5
System	1-6
Performance Improvement Tools and Techniques	1-6
Mathematics	1-7
Arrays and Matrices	1-8
Linear Algebra	1-10
Elementary Math	1-12
Data Analysis and Fourier Transforms	1-14
Polynomials	1-15
Interpolation and Computational Geometry	1-16
Coordinate System Conversion	1-17
Nonlinear Numerical Methods	1-17
Specialized Math	1-18
Sparse Matrices	1-19
Math Constants	1-21
Programming and Data Types	1-22
Data Types	1-22
Arrays	1-26
Operators and Operations	1-27
Programming in MATLAB	1-30
File I/O	1-34
Filename Construction	1-34
Opening, Loading, Saving Files	1-34
Low-Level File I/O	1-35
Text Files	1-35
Spreadsheets	1-35

Scientific Data	1-36
Audio and Audio/Video	1-36
Images	1-37
Graphics	1-38
Basic Plots and Graphs	1-38
Annotating Plots	1-38
Specialized Plotting	1-39
Bit-Mapped Images	1-41
Printing	1-41
Handle Graphics	1-41
3-D Visualization	1-43
Surface and Mesh Plots	1-43
View Control	1-44
Lighting	1-45
Transparency	1-46
Volume Visualization	1-46
Creating Graphical User Interfaces	1-47
Predefined Dialog Boxes	1-47
Deploying User Interfaces	1-48
Developing User Interfaces	1-48
User Interface Objects	1-48
Finding and Identifying Objects	1-48
GUI Utility Functions	1-48
Controlling Program Execution	1-49

Alphabetical List of Functions

2 |

Functions By Category

The MATLAB Function Reference contains descriptions of all MATLAB commands and functions.

If you know the name of a function, use the “Alphabetical List of Functions” to find the reference page.

If you do not know the name of a function, select a category from the following table to see a list of related functions. You can also browse these tables to see what functionality MATLAB provides.

Category	Description
Development Environment	Startup, Command Window, help, editing and debugging, other general functions
Mathematics	Arrays and matrices, linear algebra, data analysis, other areas of mathematics
Programming and Data Types	Function/expression evaluation, program control, function handles, object oriented programming, error handling, operators, data types
File I/O	General and low-level file I/O, plus specific file formats, like audio, spreadsheet, HDF, images
Graphics	Line plots, annotating graphs, specialized plots, images, printing, Handle Graphics
3-D Visualization	Surface and mesh plots, view control, lighting and transparency, volume visualization.
Creating Graphical User Interface	GUIDE, programming graphical user interfaces.
External Interfaces	Java, ActiveX, Serial Port functions.

See Simulink, Stateflow, Real-Time Workshop, and the individual toolboxes for lists of their functions

Development Environment

General functions for working in MATLAB, including functions for startup, Command Window, help, and editing and debugging.

Category	Description
“Starting and Quitting”	Startup and shutdown options
“Command Window”	Controlling Command Window
“Getting Help”	Methods for finding information
“Workspace, File, and Search Path”	File, search path, variable management
“Programming Tools”	Editing and debugging, source control, profiling
“System”	Identifying current computer, license, or product version
“Performance Improvement Tools and Techniques”	Improving and assessing performance, e.g., memory use

Starting and Quitting

<code>exit</code>	Terminate MATLAB (same as <code>quit</code>)
<code>finish</code>	MATLAB termination M-file
<code>matlab</code>	Start MATLAB (UNIX systems only)
<code>matlabrc</code>	MATLAB startup M-file for single user systems or administrators
<code>quit</code>	Terminate MATLAB
<code>startup</code>	MATLAB startup M-file for user-defined options

Command Window

<code>clc</code>	Clear Command Window
<code>diary</code>	Save session to file
<code>dos</code>	Execute DOS command and return result
<code>format</code>	Control display format for output
<code>home</code>	Move cursor to upper left corner of Command Window
<code>more</code>	Control paged output for Command Window

<code>notebook</code>	Open M-book in Microsoft Word (Windows only)
<code>uni x</code>	Execute UNIX command and return result

Getting Help

<code>doc</code>	Display online documentation in MATLAB Help browser
<code>docopt</code>	Location of help file directory for UNIX platforms
<code>hel p</code>	Display help for MATLAB functions in Command Window
<code>hel pbrowser</code>	Display Help browser for access to extensive online help
<code>hel pw n</code>	Display M-file help, with access to M-file help for all functions
<code>i nfo</code>	Display information about The MathWorks or products
<code>l ookfor</code>	Search for specified keyword in all help entries
<code>support</code>	Open MathWorks Technical Support Web page
<code>web</code>	Point Help browser or Web browser to file or Web site
<code>whatsnew</code>	Display information about MATLAB and toolbox releases

Workspace, File, and Search Path

- “Workspace”
- “File”
- “Search Path”

Workspace

<code>assi gni n</code>	Assign value to workspace variable
<code>cl ear</code>	Remove items from workspace, freeing up system memory
<code>eval i n</code>	Execute string containing MATLAB expression in a workspace
<code>exi st</code>	Check if variable or file exists
<code>openvar</code>	Open workspace variable in Array Editor for graphical editing
<code>pack</code>	Consolidate workspace memory
<code>whi ch</code>	Locate functions and files
<code>who, whos</code>	List variables in the workspace
<code>workspace</code>	Display Workspace browser, a tool for managing the workspace

File

<code>cd</code>	Change working directory
<code>copyfile</code>	Copy file
<code>del ete</code>	Delete files or graphics objects
<code>di r</code>	Display directory listing
<code>exi st</code>	Check if a variable or file exists
<code>fil ebrowser</code>	Display Current Directory browser, a tool for viewing files
<code>l ookfor</code>	Search for specified keyword in all help entries

<code>ls</code>	List directory on UNIX
<code>matlabroot</code>	Return root directory of MATLAB installation
<code>mkdir</code>	Make new directory
<code>pwd</code>	Display current directory
<code>rehash</code>	Refresh function and file system caches
<code>type</code>	List file
<code>what</code>	List MATLAB specific files in current directory
<code>which</code>	Locate functions and files

See also “File I/O” functions.

Search Path

<code>addpath</code>	Add directories to MATLAB search path
<code>genpath</code>	Generate path string
<code>partialpath</code>	Partial pathname
<code>path</code>	View or change the MATLAB directory search path
<code>pathtool</code>	Open Set Path dialog box to view and change MATLAB path
<code>rmpath</code>	Remove directories from MATLAB search path

Programming Tools

- “Editing and Debugging”
- “Source Control”
- “Profiling”

Editing and Debugging

<code>dbclear</code>	Clear breakpoints
<code>dbcont</code>	Resume execution
<code>dbdown</code>	Change local workspace context
<code>dbquit</code>	Quit debug mode
<code>dbstack</code>	Display function call stack
<code>dbstatus</code>	List all breakpoints
<code>dbstep</code>	Execute one or more lines from current breakpoint
<code>dbstop</code>	Set breakpoints in M-file function
<code>dbtype</code>	List M-file with line numbers
<code>dbup</code>	Change local workspace context
<code>edit</code>	Edit or create M-file
<code>keyboard</code>	Invoke the keyboard in an M-file

Source Control

checkin	Check file into source control system
checkout	Check file out of source control system
cmopts	Get name of source control system
customverctrl	Allow custom source control system
undochekout	Undo previous checkout from source control system

Profiling

profile	Optimize performance of M-file code
profreport	Generate profile report

System

computer	Identify information about computer on which MATLAB is running
javachk	Generate error message based on Java feature support
license	Show license number for MATLAB
usej ava	Determine if a Java feature is supported in MATLAB
ver	Display version information for MathWorks products
versi on	Get MATLAB version number

Performance Improvement Tools and Techniques

memory	Help for memory limitations
pack	Consolidate workspace memory
profile	Optimize performance of M-file code
profreport	Generate profile report
rehash	Refresh function and file system caches
sparse	Create sparse matrix
zeros	Create array of all zeros

Mathematics

Functions for working with arrays and matrices, linear algebra, data analysis, and other areas of mathematics.

Category	Description
“Arrays and Matrices”	Basic array operators and operations, creation of elementary and specialized arrays and matrices
“Linear Algebra”	Matrix analysis, linear equations, eigenvalues, singular values, logarithms, exponentials, factorization
“Elementary Math”	Trigonometry, exponentials and logarithms, complex values, rounding, remainders, discrete math
“Data Analysis and Fourier Transforms”	Descriptive statistics, finite differences, correlation, filtering and convolution, fourier transforms
“Polynomials”	Multiplication, division, evaluation, roots, derivatives, integration, eigenvalue problem, curve fitting, partial fraction expansion
“Interpolation and Computational Geometry”	Interpolation, Delaunay triangulation and tessellation, convex hulls, Voronoi diagrams, domain generation
“Coordinate System Conversion”	Conversions between Cartesian and polar or spherical coordinates
“Nonlinear Numerical Methods”	Differential equations, optimization, integration
“Specialized Math”	Airy, Bessel, Jacobi, Legendre, beta, elliptic, error, exponential integral, gamma functions

Category	Description
“Sparse Matrices”	Elementary sparse matrices, operations, reordering algorithms, linear algebra, iterative methods, tree operations
“Math Constants”	Pi, imaginary unit, infinity, Not-a-Number, largest and smallest positive floating point numbers, floating point relative accuracy

Arrays and Matrices

- “Basic Information”
- “Operators”
- “Operations and Manipulation”
- “Elementary Matrices and Arrays”
- “Specialized Matrices”

Basic Information

<code>di sp</code>	Display array
<code>di spl ay</code>	Display array
<code>i sempty</code>	True for empty matrix
<code>i sequal</code>	True if arrays are identical
<code>i sl ogi cal</code>	True for logical array
<code>i snumeri c</code>	True for numeric arrays
<code>i ssparse</code>	True for sparse matrix
<code>l ength</code>	Length of vector
<code>ndi ms</code>	Number of dimensions
<code>numel</code>	Number of elements
<code>si ze</code>	Size of matrix

Operators

<code>+</code>	Addition
<code>+</code>	Unary plus
<code>-</code>	Subtraction
<code>-</code>	Unary minus
<code>*</code>	Matrix multiplication
<code>^</code>	Matrix power
<code>\</code>	Backslash or left matrix divide

/	Slash or right matrix divide
'	Transpose
.'	Nonconjugated transpose
.*	Array multiplication (element-wise)
.^	Array power (element-wise)
.\	Left array divide (element-wise)
./	Right array divide (element-wise)

Operations and Manipulation

:	(colon)	Index into array, rearrange array
blkdiag	Block diagonal concatenation	
cat	Concatenate arrays	
cross	Vector cross product	
cumprod	Cumulative product	
cumsum	Cumulative sum	
diag	Diagonal matrices and diagonals of matrix	
dot	Vector dot product	
end	Last index	
find	Find indices of nonzero elements	
fliplr	Flip matrices left-right	
fliptud	Flip matrices up-down	
fliptdim	Flip matrix along specified dimension	
horzcat	Horizontal concatenation	
ind2sub	Multiple subscripts from linear index	
ipermute	Inverse permute dimensions of multidimensional array	
kron	Kronecker tensor product	
max	Maximum elements of array	
min	Minimum elements of array	
permute	Rearrange dimensions of multidimensional array	
prod	Product of array elements	
repmat	Replicate and tile array	
reshape	Reshape array	
rot90	Rotate matrix 90 degrees	
sort	Sort elements in ascending order	
sortrows	Sort rows in ascending order	
sum	Sum of array elements	
sqrtm	Matrix square root	
sub2ind	Linear index from multiple subscripts	
tril	Lower triangular part of matrix	
triu	Upper triangular part of matrix	
vertcat	Vertical concatenation	

See also “Linear Algebra” for other matrix operations.
See also “Elementary Math” for other array operations.

Elementary Matrices and Arrays

:	(colon)	Regularly spaced vector
bl kdi ag	Construct block diagonal matrix from input arguments	
di ag	Diagonal matrices and diagonals of matrix	
eye	Identity matrix	
freqspace	Frequency spacing for frequency response	
l i nspace	Generate linearly spaced vectors	
l ogspace	Generate logarithmically spaced vectors	
meshgrid	Generate X and Y matrices for three-dimensional plots	
ndgrid	Arrays for multidimensional functions and interpolation	
ones	Create array of all ones	
rand	Uniformly distributed random numbers and arrays	
randn	Normally distributed random numbers and arrays	
repmat	Replicate and tile array	
zeros	Create array of all zeros	

Specialized Matrices

compan	Companion matrix
gal l ery	Test matrices
hadamard	Hadamard matrix
hankel	Hankel matrix
hil b	Hilbert matrix
invhilb	Inverse of Hilbert matrix
magic	Magic square
pascal	Pascal matrix
rosser	Classic symmetric eigenvalue test problem
toepl i tz	Toeplitz matrix
vander	Vandermonde matrix
wil k i nson	Wilkinson’s eigenvalue test matrix

Linear Algebra

- “Matrix Analysis”
- “Linear Equations”
- “Eigenvalues and Singular Values”
- “Matrix Logarithms and Exponentials”
- “Factorization”

Matrix Analysis

<code>cond</code>	Condition number with respect to inversion
<code>condeig</code>	Condition number with respect to eigenvalues
<code>det</code>	Determinant
<code>norm</code>	Matrix or vector norm
<code>normest</code>	Estimate matrix 2-norm
<code>nul1</code>	Null space
<code>orth</code>	Orthogonalization
<code>rank</code>	Matrix rank
<code>rcond</code>	Matrix reciprocal condition number estimate
<code>rref</code>	Reduced row echelon form
<code>subspace</code>	Angle between two subspaces
<code>trace</code>	Sum of diagonal elements

Linear Equations

<code>\ and /</code>	Linear equation solution
<code>chol</code>	Cholesky factorization
<code>cholinc</code>	Incomplete Cholesky factorization
<code>cond</code>	Condition number with respect to inversion
<code>condest</code>	1-norm condition number estimate
<code>funm</code>	Evaluate general matrix function
<code>inv</code>	Matrix inverse
<code>lscov</code>	Least squares solution in presence of known covariance
<code>lsqnonneg</code>	Nonnegative least squares
<code>lu</code>	LU matrix factorization
<code>lunc</code>	Incomplete LU factorization
<code>pinv</code>	Moore-Penrose pseudoinverse of matrix
<code>qr</code>	Orthogonal-triangular decomposition
<code>rcond</code>	Matrix reciprocal condition number estimate

Eigenvalues and Singular Values

<code>balance</code>	Improve accuracy of computed eigenvalues
<code>cdf2rdf</code>	Convert complex diagonal form to real block diagonal form
<code>condeig</code>	Condition number with respect to eigenvalues
<code>eig</code>	Eigenvalues and eigenvectors
<code>eigs</code>	Eigenvalues and eigenvectors of sparse matrix
<code>gsvd</code>	Generalized singular value decomposition
<code>hess</code>	Hessenberg form of matrix
<code>poly</code>	Polynomial with specified roots
<code>polyeig</code>	Polynomial eigenvalue problem
<code>qz</code>	QZ factorization for generalized eigenvalues
<code>rsf2csf</code>	Convert real Schur form to complex Schur form

schur	Schur decomposition
svd	Singular value decomposition
svds	Singular values and vectors of sparse matrix

Matrix Logarithms and Exponentials

expm	Matrix exponential
logm	Matrix logarithm
sqrtm	Matrix square root

Factorization

balance	Diagonal scaling to improve eigenvalue accuracy
cdf2rdf	Complex diagonal form to real block diagonal form
chol	Cholesky factorization
cholinc	Incomplete Cholesky factorization
cholupdate	Rank 1 update to Cholesky factorization
lu	LU matrix factorization
luninc	Incomplete LU factorization
planerot	Givens plane rotation
qr	Orthogonal-triangular decomposition
qrdelete	Delete column from QR factorization
qrinsert	Insert column in QR factorization
qrupdate	Rank 1 update to QR factorization
qz	QZ factorization for generalized eigenvalues
rsf2csf	Real block diagonal form to complex diagonal form

Elementary Math

- “Trigonometric”
- “Exponential”
- “Complex”
- “Rounding and Remainder”
- “Discrete Math (e.g., Prime Factors)”

Trigonometric

acos, acosh	Inverse cosine and inverse hyperbolic cosine
acot, acoth	Inverse cotangent and inverse hyperbolic cotangent
acsc,acsch	Inverse cosecant and inverse hyperbolic cosecant
asec, asech	Inverse secant and inverse hyperbolic secant
asin, asinh	Inverse sine and inverse hyperbolic sine

<code>atan</code> , <code>atanh</code>	Inverse tangent and inverse hyperbolic tangent
<code>atan2</code>	Four-quadrant inverse tangent
<code>cos</code> , <code>cosh</code>	Cosine and hyperbolic cosine
<code>cot</code> , <code>coth</code>	Cotangent and hyperbolic cotangent
<code>csc</code> , <code>csch</code>	Cosecant and hyperbolic cosecant
<code>sec</code> , <code>sech</code>	Secant and hyperbolic secant
<code>sin</code> , <code>sinh</code>	Sine and hyperbolic sine
<code>tan</code> , <code>tanh</code>	Tangent and hyperbolic tangent

Exponential

<code>exp</code>	Exponential
<code>log</code>	Natural logarithm
<code>log2</code>	Base 2 logarithm and dissect floating-point numbers into exponent and mantissa
<code>log10</code>	Common (base 10) logarithm
<code>nextpow2</code>	Next higher power of 2
<code>pow2</code>	Base 2 power and scale floating-point number
<code>sqrt</code>	Square root

Complex

<code>abs</code>	Absolute value
<code>angle</code>	Phase angle
<code>complex</code>	Construct complex data from real and imaginary parts
<code>conj</code>	Complex conjugate
<code>cplxpair</code>	Sort numbers into complex conjugate pairs
<code>i</code>	Imaginary unit
<code>imag</code>	Complex imaginary part
<code>isreal</code>	True for real array
<code>j</code>	Imaginary unit
<code>real</code>	Complex real part
<code>unwrap</code>	Unwrap phase angle

Rounding and Remainder

<code>fix</code>	Round towards zero
<code>floor</code>	Round towards minus infinity
<code>ceil</code>	Round towards plus infinity
<code>round</code>	Round towards nearest integer
<code>mod</code>	Modulus (signed remainder after division)
<code>rem</code>	Remainder after division
<code>sign</code>	Signum

Discrete Math (e.g., Prime Factors)

factor	Prime factors
factorial	Factorial function
gcd	Greatest common divisor
isprime	True for prime numbers
lcm	Least common multiple
nchoosek	All combinations of N elements taken K at a time
perms	All possible permutations
primes	Generate list of prime numbers
rat, rats	Rational fraction approximation

Data Analysis and Fourier Transforms

- “Basic Operations”
- “Finite Differences”
- “Correlation”
- “Filtering and Convolution”
- “Fourier Transforms”

Basic Operations

cumprod	Cumulative product
cumsum	Cumulative sum
cumtrapz	Cumulative trapezoidal numerical integration
max	Maximum elements of array
mean	Average or mean value of arrays
median	Median value of arrays
min	Minimum elements of array
prod	Product of array elements
sort	Sort elements in ascending order
sortrows	Sort rows in ascending order
std	Standard deviation
sum	Sum of array elements
trapz	Trapezoidal numerical integration
var	Variance

Finite Differences

del2	Discrete Laplacian
diff	Differences and approximate derivatives
gradient	Numerical gradient

Correlation

<code>corrcoef</code>	Correlation coefficients
<code>cov</code>	Covariance matrix
<code>subspace</code>	Angle between two subspaces

Filtering and Convolution

<code>conv</code>	Convolution and polynomial multiplication
<code>conv2</code>	Two-dimensional convolution
<code>convn</code>	N-dimensional convolution
<code>deconv</code>	Deconvolution and polynomial division
<code>detrend</code>	Linear trend removal
<code>filter</code>	Filter data with infinite impulse response (IIR) or finite impulse response (FIR) filter
<code>filter2</code>	Two-dimensional digital filtering

Fourier Transforms

<code>abs</code>	Absolute value and complex magnitude
<code>angle</code>	Phase angle
<code>fft</code>	One-dimensional fast Fourier transform
<code>fft2</code>	Two-dimensional fast Fourier transform
<code>fftn</code>	N-dimensional discrete Fourier Transform
<code>fftshift</code>	Shift DC component of fast Fourier transform to center of spectrum
<code>ifft</code>	Inverse one-dimensional fast Fourier transform
<code>ifft2</code>	Inverse two-dimensional fast Fourier transform
<code>ifftn</code>	Inverse multidimensional fast Fourier transform
<code>ifftshift</code>	Inverse fast Fourier transform shift
<code>nextpow2</code>	Next power of two
<code>unwrap</code>	Correct phase angles

Polynomials

<code>conv</code>	Convolution and polynomial multiplication
<code>deconv</code>	Deconvolution and polynomial division
<code>poly</code>	Polynomial with specified roots
<code>pol yder</code>	Polynomial derivative
<code>pol yeig</code>	Polynomial eigenvalue problem
<code>pol yfit</code>	Polynomial curve fitting
<code>pol yint</code>	Analytic polynomial integration
<code>pol yval</code>	Polynomial evaluation
<code>pol yvalm</code>	Matrix polynomial evaluation
<code>residue</code>	Convert between partial fraction expansion and polynomial coefficients
<code>roots</code>	Polynomial roots

Interpolation and Computational Geometry

- “Interpolation”
- “Delaunay Triangulation and Tessellation”
- “Convex Hull”
- “Voronoi Diagrams”
- “Domain Generation”

Interpolation

<code>dsearch</code>	Search for nearest point
<code>dsearchn</code>	Multidimensional closest point search
<code>griddata</code>	Data gridding
<code>griddata3</code>	Data gridding and hypersurface fitting for three-dimensional data
<code>griddataan</code>	Data gridding and hypersurface fitting (dimension ≥ 2)
<code>interp1</code>	One-dimensional data interpolation (table lookup)
<code>interp2</code>	Two-dimensional data interpolation (table lookup)
<code>interp3</code>	Three-dimensional data interpolation (table lookup)
<code>interpft</code>	One-dimensional interpolation using fast Fourier transform method
<code>interpn</code>	Multidimensional data interpolation (table lookup)
<code>meshgrid</code>	Generate X and Y matrices for three-dimensional plots
<code>mkpp</code>	Make piecewise polynomial
<code>ndgrid</code>	Generate arrays for multidimensional functions and interpolation
<code>pchip</code>	Piecewise Cubic Hermite Interpolating Polynomial (PCHIP)
<code>ppval</code>	Piecewise polynomial evaluation
<code>spline</code>	Cubic spline data interpolation
<code>tsearchn</code>	Multidimensional closest simplex search
<code>unmkpp</code>	Piecewise polynomial details

Delaunay Triangulation and Tessellation

<code>delaunay</code>	Delaunay triangulation
<code>delaunay3</code>	Three-dimensional Delaunay tessellation
<code>delaunayn</code>	Multidimensional Delaunay tessellation
<code>dsearch</code>	Search for nearest point
<code>dsearchn</code>	Multidimensional closest point search
<code>tetramesh</code>	Tetrahedron mesh plot
<code>trimesh</code>	Triangular mesh plot
<code>tripplot</code>	Two-dimensional triangular plot
<code>trisurf</code>	Triangular surface plot
<code>tsearch</code>	Search for enclosing Delaunay triangle
<code>tsearchn</code>	Multidimensional closest simplex search

Convex Hull

<code>convhull</code>	Convex hull
<code>convhulln</code>	Multidimensional convex hull
<code>patch</code>	Create patch graphics object
<code>plot</code>	Linear two-dimensional plot
<code>trisurf</code>	Triangular surface plot

Voronoi Diagrams

<code>dsearch</code>	Search for nearest point
<code>patch</code>	Create patch graphics object
<code>plot</code>	Linear two-dimensional plot
<code>voronoi</code>	Voronoi diagram
<code>voronoin</code>	Multidimensional Voronoi diagrams

Domain Generation

<code>meshgrid</code>	Generate X and Y matrices for three-dimensional plots
<code>ndgrid</code>	Generate arrays for multidimensional functions and interpolation

Coordinate System Conversion

Cartesian

<code>cart2sph</code>	Transform Cartesian to spherical coordinates
<code>cart2pol</code>	Transform Cartesian to polar coordinates
<code>pol2cart</code>	Transform polar to Cartesian coordinates
<code>sph2cart</code>	Transform spherical to Cartesian coordinates

Nonlinear Numerical Methods

- “Ordinary Differential Equations (IVP)”
- “Boundary Value Problems”
- “Partial Differential Equations”
- “Optimization”
- “Numerical Integration (Quadrature)”

Ordinary Differential Equations (IVP)

<code>deval</code>	Evaluate solution of differential equation problem
<code>ode113</code>	Solve non-stiff differential equations, variable order method
<code>ode15s</code>	Solve stiff ODEs and DAEs Index 1, variable order method

ode23	Solve non-stiff differential equations, low order method
ode23s	Solve stiff differential equations, low order method
ode23t	Solve moderately stiff ODEs and DAEs Index 1, trapezoidal rule
ode23tb	Solve stiff differential equations, low order method
ode45	Solve non-stiff differential equations, medium order method
odeget	Get ODE options parameters
odeset	Create/alter ODE options structure

Boundary Value Problems

bvp4c	Solve two-point boundary value problems for ODEs by collocation
bvpset	Create/alter BVP options structure
bvpget	Get BVP options parameters
deval	Evaluate solution of differential equation problem

Partial Differential Equations

pdepe	Solve initial-boundary value problems for parabolic-elliptic PDEs
pdeval	Evaluates by interpolation solution computed by pdepe

Optimization

fminbnd	Scalar bounded nonlinear function minimization
fminsearch	Multidimensional unconstrained nonlinear minimization, by Nelder-Mead direct search method
fzero	Scalar nonlinear zero finding
lsqnonneg	Linear least squares with nonnegativity constraints
optimset	Create or alter optimization options structure
optimget	Get optimization parameters from options structure

Numerical Integration (Quadrature)

quad	Numerically evaluate integral, adaptive Simpson quadrature (low order)
quadl	Numerically evaluate integral, adaptive Lobatto quadrature (high order)
dbl quad	Numerically evaluate double integral

Specialized Math

airy	Airy functions
besselh	Bessel functions of third kind (Hankel functions)
besseli	Modified Bessel function of first kind
besselj	Bessel function of first kind
besselk	Modified Bessel function of second kind
besselj	Bessel function of second kind
beta	Beta function

<code>betai nc</code>	Incomplete beta function
<code>beta1 n</code>	Logarithm of beta function
<code>ellipj</code>	Jacobi elliptic functions
<code>ellipke</code>	Complete elliptic integrals of first and second kind
<code>erf</code>	Error function
<code>erfc</code>	Complementary error function
<code>erfcinv</code>	Inverse complementary error function
<code>erfcx</code>	Scaled complementary error function
<code>erfinv</code>	Inverse error function
<code>expint</code>	Exponential integral
<code>gamma</code>	Gamma function
<code>gammainc</code>	Incomplete gamma function
<code>gammaln</code>	Logarithm of gamma function
<code>legendre</code>	Associated Legendre functions

Sparse Matrices

- “Elementary Sparse Matrices”
- “Full to Sparse Conversion”
- “Working with Sparse Matrices”
- “Reordering Algorithms”
- “Linear Algebra”
- “Linear Equations (Iterative Methods)”
- “Tree Operations”

Elementary Sparse Matrices

<code>spdiags</code>	Sparse matrix formed from diagonals
<code>speye</code>	Sparse identity matrix
<code>sprand</code>	Sparse uniformly distributed random matrix
<code>sprandn</code>	Sparse normally distributed random matrix
<code>sprandsym</code>	Sparse random symmetric matrix

Full to Sparse Conversion

<code>find</code>	Find indices of nonzero elements
<code>full</code>	Convert sparse matrix to full matrix
<code>sparse</code>	Create sparse matrix
<code>spconvert</code>	Import from sparse matrix external format

Working with Sparse Matrices

issparse	True for sparse matrix
nnz	Number of nonzero matrix elements
nonzeros	Nonzero matrix elements
nzmax	Amount of storage allocated for nonzero matrix elements
spalloc	Allocate space for sparse matrix
spfun	Apply function to nonzero matrix elements
spones	Replace nonzero sparse matrix elements with ones
spparms	Set parameters for sparse matrix routines
spy	Visualize sparsity pattern

Reordering Algorithms

colamd	Column approximate minimum degree permutation
colmmd	Column minimum degree permutation
colperm	Column permutation
dmp perm	Dulmage-Mendelsohn permutation
randperm	Random permutation
symamd	Symmetric approximate minimum degree permutation
symmmd	Symmetric minimum degree permutation
symrcm	Symmetric reverse Cuthill-McKee permutation

Linear Algebra

cholinc	Incomplete Cholesky factorization
conde st	1-norm condition number estimate
eigs	Eigenvalues and eigenvectors of sparse matrix
lui nc	Incomplete LU factorization
normest	Estimate matrix 2-norm
sprank	Structural rank
svds	Singular values and vectors of sparse matrix

Linear Equations (Iterative Methods)

bicg	BiConjugate Gradients method
bicgstab	BiConjugate Gradients Stabilized method
cgs	Conjugate Gradients Squared method
gmres	Generalized Minimum Residual method
lsqr	LSQR implementation of Conjugate Gradients on Normal Equations
minres	Minimum Residual method
pcg	Preconditioned Conjugate Gradients method
qmr	Quasi-Minimal Residual method
spaugment	Form least squares augmented system
symmlq	Symmetric LQ method

Tree Operations

<code>etree</code>	Elimination tree
<code>etreeplot</code>	Plot elimination tree
<code>gplot</code>	Plot graph, as in “graph theory”
<code>symbfact</code>	Symbolic factorization analysis
<code>treelayout</code>	Lay out tree or forest
<code>treeplot</code>	Plot picture of tree

Math Constants

<code>eps</code>	Floating-point relative accuracy
<code>i</code>	Imaginary unit
<code>Inf</code>	Infinity, ∞
<code>j</code>	Imaginary unit
<code>NaN</code>	Not-a-Number
<code>pi</code>	Ratio of a circle’s circumference to its diameter, π
<code>realmax</code>	Largest positive floating-point number
<code>realmin</code>	Smallest positive floating-point number

Programming and Data Types

Functions to store and operate on data at either the MATLAB command line or in programs and scripts. Functions to write, manage, and execute MATLAB programs.

Category	Description
“Data Types”	Numeric, character, structures, cell arrays, and data type conversion
“Arrays”	Basic array operations and manipulation
“Operators and Operations”	Special characters and arithmetic, bit-wise, relational, logical, set, date and time operations
“Programming in MATLAB”	M-files, function/expression evaluation, program control, function handles, object oriented programming, error handling

Data Types

- “Numeric”
- “Characters and Strings”
- “Structures”
- “Cell Arrays”
- “Data Type Conversion”

Numeric

[]	Array constructor
cat	Concatenate arrays
class	Return object's class name (e.g., numeric)
find	Find indices and values of nonzero array elements
ipermute	Inverse permute dimensions of multidimensional array
isa	Detect object of given class (e.g., numeric)
isequal	Determine if arrays are numerically equal
isnumeric	Determine if item is numeric array
isreal	Determine if all array elements are real numbers

permute	Rearrange dimensions of multidimensional array
reshape	Reshape array
squeeze	Remove singleton dimensions from array
zeros	Create array of all zeros

Characters and Strings

Description of Strings in MATLAB

strings	Describes MATLAB string handling
----------------	----------------------------------

Creating and Manipulating Strings

blanks	Create string of blanks
char	Create character array (string)
cellstr	Create cell array of strings from character array
datestr	Convert to date string format
deblank	Strip trailing blanks from the end of string
lower	Convert string to lower case
printf	Write formatted data to string
sscanf	Read string under format control
strcat	String concatenation
strjust	Justify character array
strread	Read formatted data from string
strrep	String search and replace
strvcat	Vertical concatenation of strings
upper	Convert string to upper case

Comparing and Searching Strings

class	Return object's class name (e.g., char)
findstr	Find string within another, longer string
isa	Detect object of given class (e.g., char)
iscellstr	Determine if item is cell array of strings
ischar	Determine if item is character array
isletter	Detect array elements that are letters of the alphabet
isspace	Detect elements that are ASCII white spaces
strcmp	Compare strings
strcmpi	Compare strings, ignoring case
strfind	Find one string within another
strmatch	Find possible matches for string
strncmp	Compare first n characters of strings
strncmpi	Compare first n characters of strings, ignoring case
 strtok	First token in string

Evaluating String Expressions

<code>eval</code>	Execute string containing MATLAB expression
<code>eval c</code>	Evaluate MATLAB expression with capture
<code>eval i n</code>	Execute string containing MATLAB expression in workspace

Structures

<code>cell2struct</code>	Cell array to structure array conversion
<code>class</code>	Return object's class name (e.g., struct)
<code>deal</code>	Deal inputs to outputs
<code>fieldnames</code>	Field names of structure
<code>getfield</code>	Get field of structure array
<code>isa</code>	Detect object of given class (e.g., struct)
<code>isequal</code>	Determine if arrays are numerically equal
<code>isfield</code>	Determine if item is structure array field
<code>isstruct</code>	Determine if item is structure array
<code>rmfield</code>	Remove structure fields
<code>setfield</code>	Set field of structure array
<code>struct</code>	Create structure array
<code>struct2cell</code>	Structure to cell array conversion

Cell Arrays

<code>{ }</code>	Construct cell array
<code>cell</code>	Construct cell array
<code>cellfun</code>	Apply function to each element in cell array
<code>cellstr</code>	Create cell array of strings from character array
<code>cell2struct</code>	Cell array to structure array conversion
<code>celldisp</code>	Display cell array contents
<code>cellplot</code>	Graphically display structure of cell arrays
<code>class</code>	Return object's class name (e.g., cell)
<code>deal</code>	Deal inputs to outputs
<code>isa</code>	Detect object of given class (e.g., cell)
<code>iscell</code>	Determine if item is cell array
<code>iscellstr</code>	Determine if item is cell array of strings
<code>isequal</code>	Determine if arrays are numerically equal
<code>num2cell</code>	Convert numeric array into cell array
<code>struct2cell</code>	Structure to cell array conversion

Data Type Conversion

Numeric

<code>double</code>	Convert to double-precision
---------------------	-----------------------------

<code>int8</code>	Convert to signed 8-bit integer
<code>int16</code>	Convert to signed 16-bit integer
<code>int32</code>	Convert to signed 32-bit integer
<code>singl e</code>	Convert to single-precision
<code>uint8</code>	Convert to unsigned 8-bit integer
<code>uint16</code>	Convert to unsigned 16-bit integer
<code>uint32</code>	Convert to unsigned 32-bit integer

String to Numeric

<code>base2dec</code>	Convert base N number string to decimal number
<code>bin2dec</code>	Convert binary number string to decimal number
<code>hex2dec</code>	Convert hexadecimal number string to decimal number
<code>hex2num</code>	Convert hexadecimal number string to double number
<code>str2double</code>	Convert string to double-precision number
<code>str2num</code>	Convert string to number

Numeric to String

<code>char</code>	Convert to character array (string)
<code>dec2base</code>	Convert decimal to base N number in string
<code>dec2bin</code>	Convert decimal to binary number in string
<code>dec2hex</code>	Convert decimal to hexadecimal number in string
<code>int2str</code>	Convert integer to string
<code>mat2str</code>	Convert a matrix to string
<code>num2str</code>	Convert number to string

Other Conversions

<code>cell2struct</code>	Convert cell array to structure array
<code>datestr</code>	Convert serial date number to string
<code>func2str</code>	Convert function handle to function name string
<code>logical</code>	Convert numeric to logical array
<code>num2cell</code>	Convert a numeric array to cell array
<code>str2func</code>	Convert function name string to function handle
<code>struct2cell</code>	Convert structure to cell array

Determine Data Type

<code>is*</code>	Detect state
<code>isa</code>	Detect object of given MATLAB class or Java class
<code>iscell</code>	Determine if item is cell array
<code>iscellstr</code>	Determine if item is cell array of strings
<code>ischar</code>	Determine if item is character array
<code>isfield</code>	Determine if item is character array

i sj ava	Determine if item is Java object
i sl ogi cal	Determine if item is logical array
i snumeri c	Determine if item is numeric array
i sobj ect	Determine if item is MATLAB OOPs object
i sstruct	Determine if item is MATLAB structure array

Arrays

- “Array Operations”
- “Basic Array Information”
- “Array Manipulation”
- “Elementary Arrays”

Array Operations

[]	Array constructor
,	Array row element separator
:	Array column element separator
:	Specify range of array elements
end	Indicate last index of array
+	Addition or unary plus
-	Subtraction or unary minus
. *	Array multiplication
. /	Array right division
. \	Array left division
. ^	Array power
. '	Array (nonconjugated) transpose

Basic Array Information

di sp	Display text or array
di spl ay	Overloaded method to display text or array
i sempty	Determine if array is empty
i sequal	Determine if arrays are numerically equal
i snumeri c	Determine if item is numeric array
i sl ogi cal	Determine if item is logical array
l ength	Length of vector
ndi ms	Number of array dimensions
numel	Number of elements in matrix or cell array
si ze	Array dimensions

Array Manipulation

:	Specify range of array elements
blkdiag	Construct block diagonal matrix from input arguments
cat	Concatenate arrays
find	Find indices and values of nonzero elements
fliplr	Flip matrices left-right
fliptud	Flip matrices up-down
fliplr m	Flip array along specified dimension
horzcat	Horizontal concatenation
ind2sub	Subscripts from linear index
ipermute	Inverse permute dimensions of multidimensional array
permute	Rearrange dimensions of multidimensional array
repmat	Replicate and tile array
reshape	Reshape array
rot90	Rotate matrix 90 degrees
shiftdim	Shift dimensions
sort	Sort elements in ascending order
sortrows	Sort rows in ascending order
squeeze	Remove singleton dimensions
sub2ind	Single index from subscripts
vertcat	Horizontal concatenation

Elementary Arrays

:	Regularly spaced vector
blkdiag	Construct block diagonal matrix from input arguments
eye	Identity matrix
linspace	Generate linearly spaced vectors
logspace	Generate logarithmically spaced vectors
meshgrid	Generate X and Y matrices for three-dimensional plots
ndgrid	Generate arrays for multidimensional functions and interpolation
ones	Create array of all ones
rand	Uniformly distributed random numbers and arrays
randn	Normally distributed random numbers and arrays
zeros	Create array of all zeros

Operators and Operations

- “Special Characters”
- “Arithmetic Operations”
- “Bit-wise Operations”
- “Relational Operations”

- “Logical Operations”
- “Set Operations”
- “Date and Time Operations”

Special Characters

:	Specify range of array elements
()	Pass function arguments, or prioritize operations
[]	Construct array
{ }	Construct cell array
.	Decimal point, or structure field separator
...	Continue statement to next line
,	Array row element separator
;	Array column element separator
%	Insert comment line into code
!	Command to operating system
=	Assignment

Arithmetic Operations

+	Plus
-	Minus
.	Decimal point
=	Assignment
*	Matrix multiplication
/	Matrix right division
\	Matrix left division
^	Matrix power
'	Matrix transpose
.*	Array multiplication (element-wise)
./	Array right division (element-wise)
.\	Array left division (element-wise)
.^	Array power (element-wise)
.'	Array transpose

Bit-wise Operations

bitand	Bit-wise AND
bictcmp	Bit-wise complement
bitor	Bit-wise OR
bitmmax	Maximum floating-point integer
bitsset	Set bit at specified position
bitshift	Bit-wise shift
bitget	Get bit at specified position

bitxor Bit-wise XOR

Relational Operations

<	Less than
<=	Less than or equal to
>	Greater than
>=	Greater than or equal to
==	Equal to
~=	Not equal to

Logical Operations

&	Logical AND
	Logical OR
~	Logical NOT
all	Test to determine if all elements are nonzero
any	Test for any nonzero elements
find	Find indices and values of nonzero elements
is*	Detect state
isa	Detect object of given class
iskeyword	Determine if string is MATLAB keyword
isvarname	Determine if string is valid variable name
logical	Convert numeric values to logical
xor	Logical EXCLUSIVE OR

Set Operations

intersect	Set intersection of two vectors
ismember	Detect members of set
setdiff	Return set difference of two vectors
setxor	Set exclusive or of two vectors
union	Set union of two vectors
unique	Unique elements of vector

Date and Time Operations

calendar	Calendar for specified month
clock	Current time as date vector
cputime	Elapsed CPU time
date	Current date string
datenum	Serial date number
datestr	Convert serial date number to string
datevec	Date components
eomday	End of month

<code>etime</code>	Elapsed time
<code>now</code>	Current date and time
<code>tic, toc</code>	Stopwatch timer
<code>weekday</code>	Day of the week

Programming in MATLAB

- “M-File Functions and Scripts”
- “Evaluation of Expressions and Functions”
- “Variables and Functions in Memory”
- “Control Flow”
- “Function Handles”
- “Object-Oriented Programming”
- “Error Handling”
- “MEX Programming”

M-File Functions and Scripts

<code>()</code>	Pass function arguments
<code>%</code>	Insert comment line into code
<code>...</code>	Continue statement to next line
<code>depfun</code>	List dependent functions of M-file or P-file
<code>depdir</code>	List dependent directories of M-file or P-file
<code>function</code>	Function M-files
<code>input</code>	Request user input
<code>inputname</code>	Input argument name
<code>mfilename</code>	Name of currently running M-file
<code>nargin</code>	Number of function input arguments
<code>nargout</code>	Number of function output arguments
<code>nargchk</code>	Check number of input arguments
<code>nargoutchk</code>	Validate number of output arguments
<code>pcode</code>	Create prepared pseudocode file (P-file)
<code>script</code>	Describes script M-file
<code>varargin</code>	Accept variable number of arguments
<code>varargout</code>	Return variable number of arguments

Evaluation of Expressions and Functions

<code>builtin</code>	Execute builtin function from overloaded method
<code>cellfun</code>	Apply function to each element in cell array
<code>eval</code>	Interpret strings containing MATLAB expressions

<code>eval c</code>	Evaluate MATLAB expression with capture
<code>eval i n</code>	Evaluate expression in workspace
<code>feval</code>	Evaluate function
<code>i skeyword</code>	Determine if item is MATLAB keyword
<code>i svarname</code>	Determine if item is valid variable name
<code>pause</code>	Halt execution temporarily
<code>run</code>	Run script that is not on current path
<code>scri pt</code>	Describes script M-file
<code>symvar</code>	Determine symbolic variables in expression
<code>tic, toc</code>	Stopwatch timer

Variables and Functions in Memory

<code>assi gni n</code>	Assign value to workspace variable
<code>gl obal</code>	Define global variables
<code>i nmem</code>	Return names of functions in memory
<code>i sgl obal</code>	Determine if item is global variable
<code>mi sl ocked</code>	True if M-file cannot be cleared
<code>ml ock</code>	Prevent clearing M-file from memory
<code>munl ock</code>	Allow clearing M-file from memory
<code>pack</code>	Consolidate workspace memory
<code>persi stent</code>	Define persistent variable
<code>rehash</code>	Refresh function and file system caches

Control Flow

<code>break</code>	Terminate execution of <code>for</code> loop or <code>whi le</code> loop
<code>case</code>	Case switch
<code>cat ch</code>	Begin catch block
<code>cont i nue</code>	Pass control to next iteration of <code>for</code> or <code>whi le</code> loop
<code>el se</code>	Conditionally execute statements
<code>el sei f</code>	Conditionally execute statements
<code>end</code>	Terminate conditional statements, or indicate last index
<code>error</code>	Display error messages
<code>for</code>	Repeat statements specific number of times
<code>i f</code>	Conditionally execute statements
<code>otherwi se</code>	Default part of <code>swi tch</code> statement
<code>return</code>	Return to invoking function
<code>swi tch</code>	Switch among several cases based on expression
<code>try</code>	Begin <code>try</code> block
<code>whi le</code>	Repeat statements indefinite number of times

Function Handles

<code>cl ass</code>	Return object's class name (e.g. <code>function_handle</code>)
---------------------	---

f eval	Evaluate function
funct i on_handl e	Describes function handle data type
funct i ons	Return information about function handle
func2str	Constructs function name string from function handle
i sa	Detect object of given class (e.g. function_handle)
i sequal	Determine if function handles are equal
str2func	Constructs function handle from function name string

Object-Oriented Programming

MATLAB Classes and Objects

cl ass	Create object or return class of object
fi el dnames	List public fields belonging to object,
i nferior o	Establish inferior class relationship
i sa	Detect object of given class
i sobj ect	Determine if item is MATLAB OOPs object
l oadobj	User-defined extension of l oad function for user objects
methods	Display method names
methodsvi ew	Displays information on all methods implemented by class
saveobj	User-defined extension of save function for user objects
subsasgn	Overloaded method for A(I) =B, A{I }=B, and A. fi el d=B
subsi ndex	Overloaded method for X(A)
subsref	Overloaded method for A(I), A{I } and A. fi el d
subst ruct	Create structure argument for subsasgn or subsref
superi ort o	Establish superior class relationship

Java Classes and Objects

cell	Convert Java array object to cell array
cl ass	Return class name of Java object
cl ear	Clear Java packages import list
depfun	List Java classes used by M-file
exist	Detect if item is Java class
fi el dnames	List public fields belonging to object,
i mport	Add package or class to current Java import list
i nmem	List names of Java classes loaded into memory
i sa	Detect object of given class
i sj ava	Determine whether object is Java object
j avaArray	Constructs Java array
j avaMethod	Invokes Java method
j avaObj ect	Constructs Java object
methods	Display methods belonging to class

methodsview	Display information on all methods implemented by class
which	Display package and class name for method

Error Handling

catch	Begin catch block of try/catch statement
error	Display error message
ferror	Query MATLAB about errors in file input or output
lasterr	Return last error message generated by MATLAB
lastwarn	Return last warning message issued by MATLAB
try	Begin try block of try/catch statement
warning	Display warning message

MEX Programming

dbmex	Enable MEX-file debugging
inmem	Return names of currently loaded MEX-files
mex	Compile MEX-function from C or Fortran source code
mexext	Return MEX-filename extension

File I/O

Functions to read and write data to files of different format types.

Category	Description
“Filename Construction”	Get path, directory, filename information; construct filenames
“Opening, Loading, Saving Files”	Open files; transfer data between files and MATLAB workspace
“Low-Level File I/O”	Low-level operations that use a file identifier (e.g., fopen, fseek, fread)
“Text Files”	Delimited or formatted I/O to text files
“Spreadsheets”	Excel and Lotus 123 files
“Scientific Data”	CDF, FITS, HDF formats
“Audio and Audio/Video”	General audio functions; SparcStation, Wave, AVI files
“Images”	Graphics files

To see a listing of file formats that are readable from MATLAB, go to file formats.

Filename Construction

<code>fileparts</code>	Return parts of filename
<code>filesep</code>	Return directory separator for this platform
<code>fullfile</code>	Build full filename from parts
<code>tempdir</code>	Return name of system's temporary directory
<code>tempname</code>	Return unique string for use as temporary filename

Opening, Loading, Saving Files

<code>importdata</code>	Load data from various types of files
<code>load</code>	Load all or specific data from MAT or ASCII file

<code>open</code>	Open files of various types using appropriate editor or program
<code>save</code>	Save all or specific data to MAT or ASCII file

Low-Level File I/O

<code>fclose</code>	Close one or more open files
<code>feof</code>	Test for end-of-file
<code>ferror</code>	Query MATLAB about errors in file input or output
<code>fgetl</code>	Return next line of file as string without line terminator(s)
<code>fgets</code>	Return next line of file as string with line terminator(s)
<code>fopen</code>	Open file or obtain information about open files
<code>fprintf</code>	Write formatted data to file
<code>fread</code>	Read binary data from file
<code>frewind</code>	Rewind open file
<code>fscanf</code>	Read formatted data from file
<code>fseek</code>	Set file position indicator
<code>ftell</code>	Get file position indicator
<code>fwrite</code>	Write binary data to file

Text Files

<code>csvread</code>	Read numeric data from text file, using comma delimiter
<code>csvwrite</code>	Write numeric data to text file, using comma delimiter
<code>dlmread</code>	Read numeric data from text file, specifying your own delimiter
<code>dlmwrite</code>	Write numeric data to text file, specifying your own delimiter
<code>textread</code>	Read data from text file, specifying format for each value

Spreadsheets

Microsoft Excel Functions

<code>xlsinfo</code>	Determine if file contains Microsoft Excel (.xls) spreadsheet
<code>xlsread</code>	Read Microsoft Excel spreadsheet file (.xls)

Lotus123 Functions

<code>wk1read</code>	Read Lotus123 WK1 spreadsheet file into matrix
<code>wk1write</code>	Write matrix to Lotus123 WK1 spreadsheet file

Scientific Data

Common Data Format (CDF)

cdfinfo Return information about CDF file
cdfread Read CDF file

Flexible Image Transport System

fitsinfo Return information about FITS file
fitsread Read FITS file

Hierarchical Data Format (HDF)

hdf Interface to HDF files
hdfinfo Return information about HDF or HDF-EOS file
hdfread Read HDF file

Audio and Audio/Video

- “General”
- “SPARCstation-Specific Sound Functions”
- “Microsoft WAVE Sound Functions”
- “Audio Video Interleaved (AVI) Functions”
- “Microsoft Excel Functions”
- “Lotus123 Functions”

General

audioplayer Create audio player object
audiorecorder Perform real-time audio capture
beep Produce beep sound
lin2mu Convert linear audio signal to mu-law
mu2lin Convert mu-law audio signal to linear
sound Convert vector into sound
soundsc Scale data and play as sound

SPARCstation-Specific Sound Functions

auread Read NeXT/SUN (.au) sound file
auwrite Write NeXT/SUN (.au) sound file

Microsoft WAVE Sound Functions

wavplay	Play sound on PC-based audio output device
wavead	Read Microsoft WAVE (. wav) sound file
wavrecord	Record sound using PC-based audio input device
wavwrite	Write Microsoft WAVE (. wav) sound file

Audio Video Interleaved (AVI) Functions

addframe	Add frame to AVI file
avi file	Create new AVI file
avi info	Return information about AVI file
avi read	Read AVI file
close	Close AVI file
movie2avi	Create AVI movie from MATLAB movie

Images

imfinfo	Return information about graphics file
imread	Read image from graphics file
imwrite	Write image to graphics file

Graphics

2-D graphs, specialized plots (e.g., pie charts, histograms, and contour plots), function plotters, and Handle Graphics functions.

Category	Description
Basic Plots and Graphs	Linear line plots, log and semilog plots
Annotating Plots	Titles, axes labels, legends, mathematical symbols
Specialized Plotting	Bar graphs, histograms, pie charts, contour plots, function plotters
Bit-Mapped Images	Display image object, read and write graphics file, convert to movie frames
Printing	Printing and exporting figures to standard formats
Handle Graphics	Creating graphics objects, setting properties, finding handles

Basic Plots and Graphs

box	Axis box for 2-D and 3-D plots
errorbar	Plot graph with error bars
hold	Hold current graph
loglog	Plot using log-log scales
polar	Polar coordinate plot
plot	Plot vectors or matrices.
plot3	Plot lines and points in 3-D space
plotyy	Plot graphs with Y tick labels on the left and right
semilogx	Semi-log scale plot
semilogy	Semi-log scale plot
subplot	Create axes in tiled positions

Annotating Plots

label	Add contour labels to contour plot
datetick	Date formatted tick labels

<code>gtext</code>	Place text on 2-D graph using mouse
<code>legend</code>	Graph legend for lines and patches
<code>texlabel</code>	Produce the TeX format from character string
<code>title</code>	Titles for 2-D and 3-D plots
<code> xlabel</code>	X-axis labels for 2-D and 3-D plots
<code> ylabel</code>	Y-axis labels for 2-D and 3-D plots
<code> zlabel</code>	Z-axis labels for 3-D plots

Specialized Plotting

- “Area, Bar, and Pie Plots”
- “Contour Plots”
- “Direction and Velocity Plots”
- “Discrete Data Plots”
- “Function Plots”
- “Histograms”
- “Polygons and Surfaces”
- “Scatter Plots”

Area, Bar, and Pie Plots

<code>area</code>	Area plot
<code>bar</code>	Vertical bar chart
<code>barh</code>	Horizontal bar chart
<code>bar3</code>	Vertical 3-D bar chart
<code>bar3h</code>	Horizontal 3-D bar chart
<code>pareto</code>	Pareto char
<code>pie</code>	Pie plot
<code>pie3</code>	3-D pie plot

Contour Plots

<code>contour</code>	Contour (level curves) plot
<code>contourc</code>	Contour computation
<code>contourf</code>	Filled contour plot
<code>ezcontour</code>	Easy to use contour plotter
<code>ezcontourf</code>	Easy to use filled contour plotter

Direction and Velocity Plots

<code>comet</code>	Comet plot
<code>comet3</code>	3-D comet plot

compass	Compass plot
feather	Feather plot
qui ver	Quiver (or velocity) plot
qui ver3	3-D quiver (or velocity) plot

Discrete Data Plots

stem	Plot discrete sequence data
stem3	Plot discrete surface data
stairs	Stairstep graph

Function Plots

ezcontour	Easy to use contour plotter
ezcontourf	Easy to use filled contour plotter
ezmesh	Easy to use 3-D mesh plotter
ezmeshc	Easy to use combination mesh/contour plotter
ezplot	Easy to use function plotter
ezplot3	Easy to use 3-D parametric curve plotter
ezpolar	Easy to use polar coordinate plotter
ezsurf	Easy to use 3-D colored surface plotter
ezsurfc	Easy to use combination surface/contour plotter
fplot	Plot a function

Histograms

hist	Plot histograms
histc	Histogram count
rose	Plot rose or angle histogram

Polygons and Surfaces

convhull	Convex hull
cylinder	Generate cylinder
delaunay	Delaunay triangulation
dsearch	Search Delaunay triangulation for nearest point
ellipsoid	Generate ellipsoid
fill	Draw filled 2-D polygons
fill3	Draw filled 3-D polygons in 3-space
inpolygon	True for points inside a polygonal region
pcolor	Pseudocolor (checkerboard) plot
polarea	Area of polygon
ribbon	Ribbon plot
slice	Volumetric slice plot
sphere	Generate sphere

tsearch	Search for enclosing Delaunay triangle
voronoi	Voronoi diagram
waterfall	Waterfall plot

Scatter Plots

plotmatrix	Scatter plot matrix
scatter	Scatter plot
scatter3	3-D scatter plot

Bit-Mapped Images

frame2im	Convert movie frame to indexed image
image	Display image object
imagesc	Scale data and display image object
imfinfo	Information about graphics file
im2frame	Convert image to movie frame
imread	Read image from graphics file
imwrite	Write image to graphics file
ind2rgb	Convert indexed image to RGB image

Printing

orient	Hardcopy paper orientation
pagesetupdlg	Page position dialog box
print	Print graph or save graph to file
printdlg	Print dialog box
printopt	Configure local printer defaults
printpreview	Preview figure to be printed
saveas	Save figure to graphic file

Handle Graphics

- Finding and Identifying Graphics Objects
- Object Creation Functions
- Figure Windows
- Axes Operations

Finding and Identifying Graphics Objects

allchild	Find all children of specified objects
copyobj	Make copy of graphics object and its children

<code>delete</code>	Delete files or graphics objects
<code>findall</code>	Find all graphics objects (including hidden handles)
<code>findobj</code>	Find objects with specified property values
<code>gca</code>	Get current Axes handle
<code>gcbo</code>	Return object whose callback is currently executing
<code>gcbf</code>	Return handle of figure containing callback object
<code>gco</code>	Return handle of current object
<code>get</code>	Get object properties
<code>ishandle</code>	True if value is valid object handle
<code>rotate</code>	Rotate objects about specified origin and direction
<code>set</code>	Set object properties

Object Creation Functions

<code>axes</code>	Create axes object
<code>figure</code>	Create figure (graph) windows
<code>image</code>	Create image (2-D matrix)
<code>light</code>	Create light object (illuminates Patch and Surface)
<code>line</code>	Create line object (3-D polylines)
<code>patch</code>	Create patch object (polygons)
<code>rectangle</code>	Create rectangle object (2-D rectangle)
<code>surface</code>	Create surface (quadrilaterals)
<code>text</code>	Create text object (character strings)
<code>uicontextmenu</code>	Create context menu (popup associated with object)

Figure Windows

<code>capture</code>	Screen capture of the current figure
<code>clc</code>	Clear figure window
<code>clf</code>	Clear figure
<code>close</code>	Close specified window
<code>closereq</code>	Default close request function
<code>drawnow</code>	Complete any pending drawing
<code>gcf</code>	Get current figure handle
<code>newplot</code>	Graphics M-file preamble for <code>NextPlot</code> property
<code>refresh</code>	Refresh figure
<code>saveas</code>	Save figure or model to desired output format

Axes Operations

<code>axis</code>	Plot axis scaling and appearance
<code>cla</code>	Clear Axes
<code>gca</code>	Get current Axes handle
<code>grid</code>	Grid lines for 2-D and 3-D plots

3-D Visualization

Create and manipulate graphics that display 2-D matrix and 3-D volume data, controlling the view, lighting and transparency.

Category	Description
Surface and Mesh Plots	Plot matrices, visualize functions of two variables, specify colormap
View Control	Control the camera viewpoint, zooming, rotation, aspect ratio, set axis limits
Lighting	Add and control scene lighting
Transparency	Specify and control object transparency
Volume Visualization	Visualize gridded volume data

Surface and Mesh Plots

- Creating Surfaces and Meshes
- Domain Generation
- Color Operations
- Colormaps

Creating Surfaces and Meshes

hidden	Mesh hidden line removal mode
meshc	Combination mesh/contourplot
mesh	3-D mesh with reference plane
peaks	A sample function of two variables
surf	3-D shaded surface graph
surface	Create surface low-level objects
surfc	Combination surf/contourplot
surfl	3-D shaded surface with lighting
tetramesh	Tetrahedron mesh plot
tri mesh	Triangular mesh plot
triplot	2-D triangular plot
trisurf	Triangular surface plot

Domain Generation

<code>griddata</code>	Data gridding and surface fitting
<code>meshgrid</code>	Generation of X and Y arrays for 3-D plots

Color Operations

<code>brighten</code>	Brighten or darken color map
<code>caxis</code>	Pseudocolor axis scaling
<code>colorbar</code>	Display color bar (color scale)
<code>colordef</code>	Set up color defaults
<code>colormap</code>	Set the color look-up table (list of colormaps)
<code>graymon</code>	Graphics figure defaults set for grayscale monitor
<code>hsv2rgb</code>	Hue-saturation-value to red-green-blue conversion
<code>rgb2hsv</code>	RGB to HSVconversion
<code>rgbplot</code>	Plot color map
<code>shading</code>	Color shading mode
<code>spinmap</code>	Spin the colormap
<code>surfnorm</code>	3-D surface normals
<code>whitebg</code>	Change axes background color for plots

Colormaps

<code>autumn</code>	Shades of red and yellow color map
<code>bone</code>	Gray-scale with a tinge of blue color map
<code>contrast</code>	Gray color map to enhance image contrast
<code>cool</code>	Shades of cyan and magenta color map
<code>copper</code>	Linear copper-tone color map
<code>flag</code>	Alternating red, white, blue, and black color map
<code>gray</code>	Linear gray-scale color map
<code>hot</code>	Black-red-yellow-white color map
<code>hsv</code>	Hue-saturation-value (HSV) color map
<code>jet</code>	Variant of HSV
<code>lines</code>	Line color colormap
<code>prism</code>	Colormap of prism colors
<code>spring</code>	Shades of magenta and yellow color map
<code>summer</code>	Shades of green and yellow colormap
<code>winter</code>	Shades of blue and green color map

View Control

- Controlling the Camera Viewpoint
- Setting the Aspect Ratio and Axis Limits
- Object Manipulation

- Selecting Region of Interest

Controlling the Camera Viewpoint

<code>camdol1y</code>	Move camera position and target
<code>caml ookat</code>	View specific objects
<code>camorbi t</code>	Orbit about camera target
<code>campan</code>	Rotate camera target about camera position
<code>campos</code>	Set or get camera position
<code>camproj</code>	Set or get projection type
<code>camroll</code>	Rotate camera about viewing axis
<code>camtarget</code>	Set or get camera target
<code>camup</code>	Set or get camera up-vector
<code>camva</code>	Set or get camera view angle
<code>camzoom</code>	Zoom camera in or out
<code>view</code>	3-D graph viewpoint specification.
<code>viewmtx</code>	Generate view transformation matrices

Setting the Aspect Ratio and Axis Limits

<code>daspect</code>	Set or get data aspect ratio
<code>pbaspect</code>	Set or get plot box aspect ratio
<code>xlim</code>	Set or get the current x -axis limits
<code>ylim</code>	Set or get the current y -axis limits
<code>zlim</code>	Set or get the current z -axis limits

Object Manipulation

<code>reset</code>	Reset axis or figure
<code>rotate3d</code>	Interactively rotate the view of a 3-D plot
<code>selectmove</code>	Interactively select, move, or resize objects
<code>zoom</code>	Zoom in and out on a 2-D plot

Selecting Region of Interest

<code>dragrect</code>	Drag XOR rectangles with mouse
<code>rbbox</code>	Rubberband box

Lighting

<code>camlight</code>	Create or position Light
<code>light</code>	Light object creation function
<code>lightangle</code>	Position light in spherical coordinates
<code>lighting</code>	Lighting mode
<code>material</code>	Material reflectance mode

Transparency

al pha	Set or query transparency properties for objects in current axes
al phamap	Specify the figure alphamap
al im	Set or query the axes alpha limits

Volume Visualization

coneplot	Plot velocity vectors as cones in 3-D vector field
contourslice	Draw contours in volume slice plane
curl	Compute curl and angular velocity of vector field
divergence	Compute divergence of vector field
flow	Generate scalar volume data
interpolate	Interpolate streamline vertices from vector-field magnitudes
isocaps	Compute isosurface end-cap geometry
isocolors	Compute colors of isosurface vertices
isonormals	Compute normals of isosurface vertices
isosurface	Extract isosurface data from volume data
reducepatch	Reduce number of patch faces
reducevolume	Reduce number of elements in volume data set
shrinkfaces	Reduce size of patch faces
slice	Draw slice planes in volume
smooth3	Smooth 3-D data
stream2	Compute 2-D stream line data
stream3	Compute 3-D stream line data
streamline	Draw stream lines from 2- or 3-D vector data
streamparticles	Draws stream particles from vector volume data
streamribbons	Draws stream ribbons from vector volume data
streamslice	Draws well-spaced stream lines from vector volume data
streamtube	Draws stream tubes from vector volume data
surf2patch	Convert surface data to patch data
subvolume	Extract subset of volume data set
volumebounds	Return coordinate and color limits for volume (scalar and vector)

Creating Graphical User Interfaces

Predefined dialog boxes and functions to control GUI programs.

Category	Description
Predefined Dialog Boxes	Dialog boxes for error, user input, waiting, etc.
Deploying User Interfaces	Launching GUIs, creating the handles structure
Developing User Interfaces	Starting GUIDE, managing application data, getting user input
User Interface Objects	Creating GUI components
Finding and Identifying Objects	Finding object handles from callbacks
GUI Utility Functions	Moving objects, text wrapping
Controlling Program Execution	Wait and resume based on user input

Predefined Dialog Boxes

di al og	Create dialog box
errordl g	Create error dialog box
hel pdl g	Display help dialog box
i nputdl g	Create input dialog box
l i stdl g	Create list selection dialog box
msgbox	Create message dialog box
pagedl g	Display page layout dialog box
pri nt dl g	Display print dialog box
questdl g	Create question dialog box
ui getfile	Display dialog box to retrieve name of file for reading
ui putfile	Display dialog box to retrieve name of file for writing
ui setcol or	Set Col orSpec using dialog box
ui setfont	Set font using dialog box
wai tbar	Display wait bar
warndl g	Create warning dialog box

Deploying User Interfaces

<code>gui data</code>	Store or retrieve application data
<code>gui handles</code>	Create a structure of handles
<code>movegui</code>	Move GUI figure onscreen
<code>openfig</code>	Open or raise GUI figure

Developing User Interfaces

<code>gui de</code>	Open GUI Layout Editor
<code>i nspect</code>	Display Property Inspector

Working with Application Data

<code>getappdata</code>	Get value of application data
<code>i sappdata</code>	True if application data exists
<code>rmappdata</code>	Remove application data
<code>setappdata</code>	Specify application data

Interactive User Input

<code>gi nput</code>	Graphical input from a mouse or cursor
<code>wai tforbuttonpress</code>	Wait for key/buttonpress over figure

User Interface Objects

<code>menu</code>	Generate menu of choices for user input
<code>ui contextmenu</code>	Create context menu
<code>ui control</code>	Create user interface control
<code>ui menu</code>	Create user interface menu

Finding and Identifying Objects

<code>fi ndal l</code>	Find all graphics objects
<code>fi ndfigs</code>	Display off-screen visible figure windows
<code>gcbf</code>	Return handle of figure containing callback object
<code>gcbo</code>	Return handle of object whose callback is executing

GUI Utility Functions

<code>sel ectmoveresize</code>	Select, move, resize, or copy axes and uicontrol graphics objects
<code>textwrap</code>	Return wrapped string matrix for given uicontrol

Controlling Program Execution

<code>ui resume</code>	Resumes program execution halted with <code>ui wai t</code>
<code>ui wai t</code>	Halts program execution, restart with <code>ui resume</code>

1 Functions By Category

Alphabetical List of Functions

factor	2-11
factorial	2-12
fclose	2-13
fclose (serial)	2-14
feather	2-15
feof	2-17
ferror	2-18
feval	2-19
fft	2-21
fft2	2-25
fftn	2-26
fftshift	2-27
fgetl	2-28
fgetl (serial)	2-29
fgets	2-31
fgets (serial)	2-32
fieldnames	2-34
figflag	2-35
figure	2-36
Figure Properties	2-45
filebrowser	2-71
file formats	2-72
fileparts	2-78
filesep	2-79
fill	2-80
fill3	2-82
filter	2-85
filter2	2-87
find	2-88
findall	2-90
findfigs	2-91
findobj	2-92
findstr	2-94
finish	2-95
fitsinfo	2-96
fitsread	2-104
fix	2-106

flipdim	2-107
fliplr	2-108
flipud	2-109
floor	2-111
flops	2-112
flow	2-113
fmin	2-114
fminbnd	2-117
fmins	2-120
fminsearch	2-123
fopen	2-127
fopen (serial)	2-130
for	2-132
format	2-134
fplot	2-137
fprintf	2-141
fprintf (serial)	2-147
frame2im	2-150
frameedit	2-151
fread	2-154
fread (serial)	2-159
freeserial	2-163
freqspace	2-164
frewind	2-165
fscanf	2-166
fscanf (serial)	2-169
fseek	2-172
ftell	2-173
full	2-174
fullfile	2-175
func2str	2-176
function	2-177
function_handle (@)	2-179
functions	2-181
funm	2-182
fwrite	2-184
fwrite (serial)	2-185

fzero	2-189
gallery	2-193
gamma, gammairc, gammaln	2-213
gca	2-215
gcbf	2-216
gcbo	2-217
gcd	2-218
gcf	2-220
gco	2-221
genpath	2-222
get	2-224
get (activex)	2-226
get (serial)	2-228
getappdata	2-230
getenv	2-231
getfield	2-232
getframe	2-234
ginput	2-237
global	2-238
gmres	2-240
gplot	2-245
gradient	2-247
graymon	2-250
grid	2-251
griddata	2-252
griddata3	2-255
griddatan	2-256
gsvd	2-258
gtext	2-263
guidata	2-264
guide	2-266
guihandles	2-267
hadamard	2-268
hankel	2-269
hdf	2-270
hdfinfo	2-272
hdfread	2-279

help	2-288
helpbrowser	2-291
helpdesk	2-292
helpdlg	2-293
helpwin	2-295
hess	2-296
hex2dec	2-298
hex2num	2-299
hgload	2-300
hgsave	2-301
hidden	2-302
hilb	2-303
hist	2-304
histc	2-307
hold	2-308
home	2-309
horzcat	2-310
hsv2rgb	2-312
i	2-313
if	2-314
ifft	2-317
ifft2	2-318
ifftn	2-319
ifftshift	2-320
im2frame	2-321
imag	2-322
image	2-323
Image Properties	2-330
imagesc	2-339
imfinfo	2-342
import	2-345
importdata	2-347
imread	2-348
imwrite	2-354
ind2rgb	2-361
ind2sub	2-362
Inf	2-363

inferiorto	2-364
info	2-365
inline	2-366
inmem	2-369
inpolygon	2-370
input	2-371
inputdlg	2-372
inputname	2-374
inspect	2-375
instrcallback	2-376
instrfind	2-377
int2str	2-379
int8, int16, int32	2-380
interp1	2-381
interp2	2-386
interp3	2-389
interpft	2-391
interpn	2-392
interpstreamspeed	2-394
intersect	2-398
inv	2-399
invhilb	2-402
invoke (activex)	2-403
ipermute	2-404
is*	2-405
isa	2-407
isappdata	2-409
iscell	2-410
iscellstr	2-411
ischar	2-412
isempty	2-413
isequal	2-414
isfield	2-415
isfinite	2-416
isglobal	2-417
ishandle	2-418
ishold	2-419

isinf	2-420
isjava	2-421
iskeyword	2-422
isletter	2-424
islogical	2-425
ismember	2-426
isnan	2-427
isnumeric	2-428
isobject	2-429
isocaps	2-430
isocolors	2-432
isonormals	2-436
isosurface	2-438
ispc	2-441
isprime	2-442
isreal	2-443
isruntime	2-445
isspace	2-446
issparse	2-447
isstr	2-448
isstruct	2-449
isstudent	2-450
isunix	2-451
isValid	2-452
isvarname	2-453
j	2-454
javaArray	2-455
javachk	2-456
javaMethod	2-458
javaObject	2-460
keyboard	2-462
kron	2-463
lasterr	2-465
lastwarn	2-467
lcm	2-468
legend	2-469
legendre	2-473

length	2-475
length (serial)	2-476
license	2-477
light	2-478
Light Properties	2-482
lightangle	2-487
lighting	2-488
lin2mu	2-489
line	2-490
Line Properties	2-497
LineSpec	2-505
linspace	2-511
listdlg	2-512
load	2-514
load (activex)	2-516
load (serial)	2-517
loadobj	2-519
log	2-521
log2	2-522
log10	2-523
logical	2-524
loglog	2-525
logm	2-527
logspace	2-529
lookfor	2-530
lower	2-531
ls	2-532
lscov	2-533
lsqnonneg	2-534
lsqr	2-537
lu	2-540
luinc	2-544
magic	2-551
mat2str	2-554
material	2-555
matlab	2-557
matlabrc	2-566

matlabroot	2-567
max	2-568
mean	2-569
median	2-570
memory	2-571
menu	2-572
mesh, meshc, meshz	2-573
meshgrid	2-577
methods	2-579
methodsview	2-581
mex	2-583
mexext	2-585
filename	2-586
min	2-587
minres	2-588
mislocked	2-592
mkdir	2-593
mkpp	2-594
mlock	2-597
mod	2-598
more	2-599
move (activex)	2-600
movegui	2-601
movie	2-603
movie2avi	2-605
moviein	2-607
msgbox	2-608
mu2lin	2-609
munlock	2-610
NaN	2-611
nargchk	2-612
nargin, nargout	2-613
nargoutchk	2-615
nchoosek	2-616
ndgrid	2-617
ndims	2-619
newplot	2-620

nextpow2	2-622
nnls	2-623
nnz	2-625
noanimate	2-626
nonzeros	2-627
norm	2-628
normest	2-629
notebook	2-630
now	2-631
null	2-632
num2cell	2-633
num2str	2-634
numel	2-635
nzmax	2-637
ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb . . .	2-638
odefile	2-648
odeget	2-654
odeset	2-655
ones	2-661
open	2-662
openfig	2-665
opengl	2-666
openvar	2-667
optimget	2-668
optimset	2-669
orient	2-674
orth	2-676
otherwise	2-677

Purpose	Prime factors
Syntax	<code>f = factor(n)</code>
Description	<code>f = factor(n)</code> returns a row vector containing the prime factors of <code>n</code> .
Examples	<pre>f = factor(123) f = 3 41</pre>
See Also	<code>isprime</code> , <code>primes</code>

factorial

Purpose	Factorial function
Syntax	<code>factorial (n)</code>
Description	<code>factorial (n)</code> is the product of all the integers from 1 to n, i.e. <code>prod(1:n)</code> . Since double precision numbers only have about 15 digits, the answer is only accurate for $n \leq 21$. For larger n, the answer will have the right magnitude, and is accurate for the first 15 digits.
See Also	<code>prod</code>

Purpose	Close one or more open files
Syntax	<code>status = fclose(fid)</code> <code>status = fclose('all')</code>
Description	<code>status = fclose(fid)</code> closes the specified file, if it is open, returning 0 if successful and -1 if unsuccessful. Argument <code>fid</code> is a file identifier associated with an open file. (See <code>fopen</code> for a complete description of <code>fid</code>). <code>status = fclose('all')</code> closes all open files, (except standard input, output, and error), returning 0 if successful and -1 if unsuccessful.
See Also	<code>ferror</code> , <code>fopen</code> , <code>fprintf</code> , <code>fread</code> , <code>frewind</code> , <code>fscanf</code> , <code>fseek</code> , <code>ftell</code> , <code>fwrite</code>

fclose (serial)

Purpose	Disconnect a serial port object from the device
Syntax	<code>fclose(obj)</code>
Arguments	<code>obj</code> A serial port object or an array of serial port objects.
Description	<code>fclose(obj)</code> disconnects <code>obj</code> from the device.
Remarks	If <code>obj</code> was successfully disconnected, then the <code>Status</code> property is configured to <code>closed</code> and the <code>RecordStatus</code> property is configured to <code>off</code> . You can reconnect <code>obj</code> to the device using the <code>fopen</code> function. An error is returned if you issue <code>fclose</code> while data is being written asynchronously. In this case, you should abort the write operation with the <code>stopasync</code> function, or wait for the write operation to complete. If you use the <code>help</code> command to display help for <code>fclose</code> , then you need to supply the pathname shown below.
	<code>help serial/fclose</code>
Example	This example creates the serial port object <code>s</code> , connects <code>s</code> to the device, writes and reads text data, and then disconnects <code>s</code> from the device using <code>fclose</code> .
	<pre>s = serial('COM1'); fopen(s) fprintf(s, '*IDN?') idn = fscanf(s); fclose(s)</pre>
	At this point, the device is available to be connected to a serial port object. If you no longer need <code>s</code> , you should remove it from memory with the <code>delete</code> function, and remove it from the workspace with the <code>clear</code> command.
See Also	Functions <code>clear</code> , <code>delete</code> , <code>fopen</code> , <code>stopasync</code>
	Properties <code>RecordStatus</code> , <code>Status</code>

Purpose Plot velocity vectors

Syntax

```
feather(U, V)
feather(Z)
feather(..., LineSpec)
```

Description A feather plot displays vectors emanating from equally spaced points along a horizontal axis. You express the vector components relative to the origin of the respective vector.

`feather(U, V)` displays the vectors specified by `U` and `V`, where `U` contains the *x* components as relative coordinates, and `V` contains the *y* components as relative coordinates.


`feather(Z)` displays the vectors specified by the complex numbers in `Z`. This is equivalent to `feather(real(Z), imag(Z))`.

`feather(..., LineSpec)` draws a feather plot using the line type, marker symbol, and color specified by `LineSpec`.

Examples Create a feather plot showing the direction of theta.

```
theta = (-90: 10: 90) * pi / 180;
r = 2*ones(size(theta));
[u, v] = pol2cart(theta, r);
feather(u, v);
```

feather



See Also

[compass](#), [LineSpec](#), [rose](#)

Purpose	Test for end-of-file
Syntax	<code>eofstat = feof(fid)</code>
Description	<code>eofstat = feof(fid)</code> returns 1 if the end-of-file indicator for the file, <code>fid</code> , has been set, and 0 otherwise. (See <code>fopen</code> for a complete description of <code>fid</code> .) The end-of-file indicator is set when there is no more input from the file.
See Also	<code>fopen</code>

ferror

Purpose	Query MATLAB about errors in file input or output
Syntax	<pre>message = ferror(fid) message = ferror(fid, 'clear') [message, errnum] = ferror(...)</pre>
Description	<p><code>message = ferror(fid)</code> returns the error string, <code>message</code>. Argument <code>fid</code> is a file identifier associated with an open file (See <code>fopen</code> for a complete description of <code>fid</code>).</p> <p><code>message = ferror(fid, 'clear')</code> clears the error indicator for the specified file.</p> <p><code>[message, errnum] = ferror(...)</code> returns the error status number <code>errnum</code> of the most recent file I/O operation associated with the specified file.</p> <p>If the most recent I/O operation performed on the specified file was successful, the value of <code>message</code> is empty and <code>ferror</code> returns an <code>errnum</code> value of 0.</p> <p>A nonzero <code>errnum</code> indicates that an error occurred in the most recent file I/O operation. The value of <code>message</code> is a string that may contain information about the nature of the error. If the message is not helpful, consult the C run-time library manual for your host operating system for further details.</p>
See Also	<code>fclose</code> , <code>fopen</code> , <code>fprintf</code> , <code>fread</code> , <code>fscanf</code> , <code>fseek</code> , <code>ftell</code> , <code>fwrite</code>

Purpose	Function evaluation
Syntax	<code>[y1, y2, ...] = feval (fhandl e, x1, ..., xn)</code> <code>[y1, y2, ...] = feval (function, x1, ..., xn)</code>
Description	<code>[y1, y2, ...] = feval (fhandl e, x1, ..., xn)</code> evaluates the function handle, <code>fhandl e</code> , using arguments <code>x1</code> through <code>xn</code> . If the function handle is bound to more than one built-in or M-file, (that is, it represents a set of overloaded functions), then the data type of the arguments <code>x1</code> through <code>xn</code> , determines which function is dispatched to. <code>[y1, y2...] = feval (function, x1, ..., xn)</code> If <code>function</code> is a quoted string containing the name of a function (usually defined by an M-file), then <code>feval (function, x1, ..., xn)</code> evaluates that function at the given arguments. The <code>function</code> parameter must be a simple function name; it cannot contain path information.
<hr/>	
Note	The preferred means of evaluating a function by reference is to use a function handle. To support backward compatibility, <code>feval</code> also accepts a function name string as a first argument. However, function handles offer the additional performance, reliability, and source file control benefits listed in the section “Benefits of Using Function Handles”.
<hr/>	
Remarks	The following two statements are equivalent.
	<code>[V, D] = eig(A)</code> <code>[V, D] = feval (@eig, A)</code>
Examples	The following example passes a function handle, <code>fhandl e</code> , in a call to <code>fminbnd</code> . The <code>fhandl e</code> argument is a handle to the <code>humps</code> function. <code>fhandl e = @humps;</code> <code>x = fminbnd(fhandl e, 0.3, 1);</code> The <code>fminbnd</code> function uses <code>feval</code> to evaluate the function handle that was passed in. <code>function [xf, fval, exitflag, output] = ...</code>

feval

```
fminbnd(funfcn, ax, bx, options, varargin)
.
.
.
fx = feval(funfcn, x, varargin{:});
```

In the next example, `@deblank` returns a function handle to variable, `fhandl e`. Examining the handle using `functions(fhandl e)` reveals that it is bound to two M-files that implement the `deblank` function. The default, `strfun\deblank.m`, handles most argument types. However, the function is overloaded by a second M-file (in the `@cell` subdirectory) to handle cell array arguments as well.

```
fhandl e = @deblank;
ff = functions(fhandl e);
ff.default
ans =
    matlabroot\toolbox\matlab\strfun\deblank.m
ff.methods
ans =
    cell: 'matlabroot\toolbox\matlab\strfun\@cell\deblank.m'
```

When the function handle is evaluated on a cell array, `feval` determines from the argument type that the appropriate function to dispatch to is the one that resides in `strfun\@cell`.

```
feval(fhandl e, {'string', 'with', 'blanks'})
ans =
    'string'    'with'    'blanks'
```

See Also


`assignin`, `function_handle`, `functions`, `builtin`, `eval`, `evalin`

Purpose	One-dimensional fast Fourier transform
Syntax	$Y = \text{fft}(X)$ $Y = \text{fft}(X, n)$ $Y = \text{fft}(X, [], \text{dim})$ $Y = \text{fft}(X, n, \text{dim})$
Definition	The functions $X = \text{fft}(x)$ and $x = \text{ifft}(X)$ implement the transform and inverse transform pair given for vectors of length N by:
	$X(k) = \sum_{j=1}^N x(j)\omega_N^{(j-1)(k-1)}$ $x(j) = (1/N) \sum_{k=1}^N X(k)\omega_N^{-(j-1)(k-1)}$
	where
	$\omega_N = e^{(-2\pi i)/N}$ is an N th root of unity.
Description	<p>$Y = \text{fft}(X)$ returns the discrete Fourier transform (DFT) of vector X, computed with a fast Fourier transform (FFT) algorithm.</p> <p>If X is a matrix, fft returns the Fourier transform of each column of the matrix.</p> <p>If X is a multidimensional array, fft operates on the first nonsingleton dimension.</p> <p>$Y = \text{fft}(X, n)$ returns the n-point DFT. If the length of X is less than n, X is padded with trailing zeros to length n. If the length of X is greater than n, the sequence X is truncated. When X is a matrix, the length of the columns are adjusted in the same manner.</p> <p>$Y = \text{fft}(X, [], \text{dim})$ and $Y = \text{fft}(X, n, \text{dim})$ applies the FFT operation across the dimension dim.</p>

Examples

A common use of Fourier transforms is to find the frequency components of a signal buried in a noisy time domain signal. Consider data sampled at 1000 Hz. Form a signal containing 50 Hz and 120 Hz and corrupt it with some zero-mean random noise:

```
t = 0: 0.001: 0.6;
x = sin(2*pi *50*t) +sin(2*pi *120*t);
y = x + 2*randn(size(t));
plot(y(1:50))
title('Signal Corrupted with Zero-Mean Random Noise')
xlabel('time (seconds)')
```



It is difficult to identify the frequency components by looking at the original signal. Converting to the frequency domain, the discrete Fourier transform of the noisy signal y is found by taking the 512-point fast Fourier transform (FFT):


```
Y = fft(y, 512);
```

The power spectrum, a measurement of the power at various frequencies, is

```
Pyy = Y.* conj(Y) / 512;
```

Graph the first 257 points (the other 255 points are redundant) on a meaningful frequency axis.

```
f = 1000*(0: 256)/512;
plot(f, Pyy(1: 257))
title('Frequency content of y')
xlabel('frequency (Hz)')
```



This represents the frequency content of y in the range from DC up to and including the Nyquist frequency. (The signal produces the strong peaks.)

Algorithm

The FFT functions (`fft`, `fft2`, `fftn`, `ifft`, `ifft2`, `ifftn`) are based on a library called FFTW [3],[4]. To compute an N -point DFT when N is composite (that is, when $N = N_1 N_2$), the FFTW library decomposes the problem using the Cooley-Tukey algorithm [1], which first computes N_1 transforms of size N_2 , and then computes N_2 transforms of size N_1 . The decomposition is applied recursively to both the N_1 - and N_2 -point DFTs until the problem can be solved using one of several machine-generated fixed-size “codelets.” The codelets in turn use several algorithms in combination, including a variation of Cooley-Tukey [5], a prime factor algorithm [6], and a split-radix algorithm [2]. The particular factorization of N is chosen heuristically.

When N is a prime number, the FFTW library first decomposes an N -point problem into three $(N - 1)$ -point problems using Rader's algorithm [7]. It then uses the Cooley-Tukey decomposition described above to compute the $(N - 1)$ -point DFTs.

For most N , real-input DFTs require roughly half the computation time of complex-input DFTs. However, when N has large prime factors, there is little or no speed difference.

The execution time for `fft` depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.

See Also

`fft2`, `fftn`, `fftshift`, `ifft`

`dftmtx`, `filter`, and `freqz` in the Signal Processing Toolbox

References

- [1] Cooley, J. W. and J. W. Tukey, "An Algorithm for the Machine Computation of the Complex Fourier Series," *Mathematics of Computation*, Vol. 19, April 1965, pp. 297-301.
- [2] Duhamel, P. and M. Vetterli, "Fast Fourier Transforms: A Tutorial Review and a State of the Art," *Signal Processing*, Vol. 19, April 1990, pp. 259-299.
- [3] FFTW (<http://www.fftw.org>)
- [4] Frigo, M. and S. G. Johnson, "FFTW: An Adaptive Software Architecture for the FFT," *Proceedings of the International Conference on Acoustics, Speech, and Signal Processing*, Vol. 3, 1998, pp. 1381-1384.
- [5] Oppenheim, A. V. and R. W. Schafer, *Discrete-Time Signal Processing*, Prentice-Hall, 1989, p. 611.
- [6] Oppenheim, A. V. and R. W. Schafer, *Discrete-Time Signal Processing*, Prentice-Hall, 1989, p. 619.
- [7] Rader, C. M., "Discrete Fourier Transforms when the Number of Data Samples Is Prime," *Proceedings of the IEEE*, Vol. 56, June 1968, pp. 1107-1108.

Purpose	Two-dimensional fast Fourier transform
Syntax	$Y = \text{fft2}(X)$ $Y = \text{fft2}(X, m, n)$
Description	$Y = \text{fft2}(X)$ returns the two-dimensional discrete Fourier transform (DFT) of X , computed with a fast Fourier transform (FFT) algorithm. The result Y is the same size as X . $Y = \text{fft2}(X, m, n)$ truncates X , or pads X with zeros to create an m -by- n array before doing the transform. The result is m -by- n .
Algorithm	$\text{fft2}(X)$ can be simply computed as $\text{fft}(\text{fft}(X) \cdot ') \cdot '$ This computes the one-dimensional DFT of each column X , then of each row of the result. The execution time for fft depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.
See Also	fft , fftn , fftshift , ifft2

fftn

Purpose	Multidimensional fast Fourier transform
Syntax	$Y = \text{fftn}(X)$ $Y = \text{fftn}(X, \text{size})$
Description	$Y = \text{fftn}(X)$ returns the discrete Fourier transform (DFT) of X , computed with a multidimensional fast Fourier transform (FFT) algorithm. The result Y is the same size as X . $Y = \text{fftn}(X, \text{size})$ pads X with zeros, or truncates X , to create a multidimensional array of size size before performing the transform. The size of the result Y is size .
Algorithm	$\text{fftn}(X)$ is equivalent to <pre>Y = X; for p = 1: length(size(X)) Y = fft(Y, [], p); end</pre> This computes in-place the one-dimensional fast Fourier transform along each dimension of X . The execution time for fft depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.
See Also	fft , fft2 , fftn , ifftn

Purpose	Shift zero-frequency component of fast Fourier transform to center of spectrum
Syntax	$Y = \text{fftshift}(X)$ $Y = \text{fftshift}(X, dim)$
Description	$Y = \text{fftshift}(X)$ rearranges the outputs of <code>fft</code> , <code>fft2</code> , and <code>fftn</code> by moving the zero-frequency component to the center of the array. It is useful for visualizing a Fourier transform with the zero-frequency component in the middle of the spectrum. For vectors, <code>fftshift(X)</code> swaps the left and right halves of <code>X</code> . For matrices, <code>fftshift(X)</code> swaps quadrants one and three of <code>X</code> with quadrants two and four. For higher-dimensional arrays, <code>fftshift(X)</code> swaps “half-spaces” of <code>X</code> along each dimension. <code>Y = fftshift(X, dim)</code> applies the <code>fftshift</code> operation along the dimension <code>dim</code> .
Examples	For any matrix <code>X</code> $Y = \text{fft2}(X)$ has $Y(1, 1) = \text{sum}(\text{sum}(X))$; the zero-frequency component of the signal is in the upper-left corner of the two-dimensional FFT. For $Z = \text{fftshift}(Y)$ this zero-frequency component is near the center of the matrix.
See Also	<code>fft</code> , <code>fft2</code> , <code>fftn</code> , <code>ifftshift</code>

fgetl

Purpose	Read line from file, discard newline character
Syntax	<code>tline = fgetl(fid)</code>
Description	<code>tline = fgetl(fid)</code> returns the next line of the file associated with the file identifier <code>fid</code> . If <code>fgetl</code> encounters the end-of-file indicator, it returns <code>-1</code> . (See <code>fopen</code> for a complete description of <code>fid</code> .) <code>fgetl</code> is intended for use with text files only.
	The returned string <code>tline</code> does not include the line terminator(s) with the text line. To obtain the line terminators, use <code>fgets</code> .
Example	The example reads every line of the M-file <code>fgetl.m</code> .
	<pre>fid=fopen('fgetl.m'); while 1 tline = fgetl(fid); if ~ischar(tline), break, end disp(tline) end fclose(fid);</pre>
See Also	<code>fgets</code>

Purpose	Read one line of text from the device and discard the terminator								
Syntax	<code>tline = fgetl(obj)</code> <code>[tline, count] = fgetl(obj)</code> <code>[tline, count, msg] = fgetl(obj)</code>								
Arguments	<table><tr><td><code>obj</code></td><td>A serial port object.</td></tr><tr><td><code>tline</code></td><td>Text read from the instrument, excluding the terminator.</td></tr><tr><td><code>count</code></td><td>The number of values read, including the terminator.</td></tr><tr><td><code>msg</code></td><td>A message indicating if the read operation was unsuccessful.</td></tr></table>	<code>obj</code>	A serial port object.	<code>tline</code>	Text read from the instrument, excluding the terminator.	<code>count</code>	The number of values read, including the terminator.	<code>msg</code>	A message indicating if the read operation was unsuccessful.
<code>obj</code>	A serial port object.								
<code>tline</code>	Text read from the instrument, excluding the terminator.								
<code>count</code>	The number of values read, including the terminator.								
<code>msg</code>	A message indicating if the read operation was unsuccessful.								
Description	<p><code>tline = fgetl(obj)</code> reads one line of text from the device connected to <code>obj</code>, and returns the data to <code>tline</code>. The returned data does not include the terminator with the text line. To include the terminator, use <code>fgets</code>.</p> <p><code>[tline, count] = fgetl(obj)</code> returns the number of values read to <code>count</code>.</p> <p><code>[tline, count, msg] = fgetl(obj)</code> returns a warning message to <code>msg</code> if the read operation was unsuccessful.</p>								
Remarks	<p>Before you can read text from the device, it must be connected to <code>obj</code> with the <code>fopen</code> function. A connected serial port object has a <code>Status</code> property value of <code>open</code>. An error is returned if you attempt to perform a read operation while <code>obj</code> is not connected to the device.</p> <p>If <code>msg</code> is not included as an output argument and the read operation was not successful, then a warning message is returned to the command line.</p> <p>The <code>ValuesReceived</code> property value is increased by the number of values read – including the terminator – each time <code>fgetl</code> is issued.</p> <p>If you use the <code>help</code> command to display help for <code>fgetl</code>, then you need to supply the pathname shown below.</p> <pre>help serial/fgetl</pre>								
<p>Rules for Completing a Read Operation with <code>fgetl</code></p> <p>A read operation with <code>fgetl</code> blocks access to the MATLAB command line until:</p>									

fgetl (serial)

- The terminator specified by the Terminator property is reached.
- The time specified by the Timeout property passes.
- The input buffer is filled.

Example

Create the serial port object s, connect s to a Tektronix TDS 210 oscilloscope, and write the RS232? command with the fprintf function. RS232? instructs the scope to return serial port communications settings.

```
s = serial('COM1');
fopen(s)
fprintf(s, 'RS232?')
```

Since the default value for the ReadAsyncMode property is continuous, data is automatically returned to the input buffer.

```
s.BytesAvailable
ans =
17
```

Use fgetl to read the data returned from the previous write operation, and discard the terminator.

```
settings = fgetl(s)
settings =
9600; 0; 0; NONE; LF
length(settings)
ans =
16
```

Disconnect s from the scope, and remove s from memory and the workspace.

```
fclose(s)
delete(s)
clear s
```

See Also

Functions

fgets, fopen

Properties

BytesAvailable, InputBufferSize, ReadAsyncMode, Status, Terminator, Timeout, ValuesReceived

Purpose	Read line from file, keep newline character
Syntax	<code>tline = fgets(fid)</code> <code>tline = fgets(fid, nchar)</code>
Description	<code>tline = fgets(fid)</code> returns the next line of the file associated with file identifier <code>fid</code> . If <code>fgets</code> encounters the end-of-file indicator, it returns <code>-1</code> . (See <code>fopen</code> for a complete description of <code>fid</code> .) <code>fgets</code> is intended for use with text files only. The returned string <code>tline</code> includes the line terminators associated with the text line. To obtain the string without the line terminators, use <code>fgetl</code> . <code>tline = fgets(fid, nchar)</code> returns at most <code>nchar</code> characters of the next line. No additional characters are read after the line terminators or an end-of-file.
See Also	<code>fgetl</code>

fgets (serial)

Purpose	Read one line of text from the device and include the terminator								
Syntax	<pre>tline = fgets(obj) [tline, count] = fgets(obj) [tline, count, msg] = fgets(obj)</pre>								
Arguments	<table><tr><td>obj</td><td>A serial port object.</td></tr><tr><td>tline</td><td>Text read from the instrument, including the terminator.</td></tr><tr><td>count</td><td>The number of bytes read, including the terminator.</td></tr><tr><td>msg</td><td>A message indicating if the read operation was unsuccessful.</td></tr></table>	obj	A serial port object.	tline	Text read from the instrument, including the terminator.	count	The number of bytes read, including the terminator.	msg	A message indicating if the read operation was unsuccessful.
obj	A serial port object.								
tline	Text read from the instrument, including the terminator.								
count	The number of bytes read, including the terminator.								
msg	A message indicating if the read operation was unsuccessful.								
Description	<p><code>tline = fgets(obj)</code> reads one line of text from the device connected to <code>obj</code>, and returns the data to <code>tline</code>. The returned data includes the terminator with the text line. To exclude the terminator, use <code>fgetl</code>.</p> <p><code>[tline, count] = fgets(obj)</code> returns the number of values read to <code>count</code>.</p> <p><code>[tline, count, msg] = fgets(obj)</code> returns a warning message to <code>msg</code> if the read operation was unsuccessful.</p>								
Remarks	<p>Before you can read text from the device, it must be connected to <code>obj</code> with the <code>fopen</code> function. A connected serial port object has a <code>Status</code> property value of <code>open</code>. An error is returned if you attempt to perform a read operation while <code>obj</code> is not connected to the device.</p> <p>If <code>msg</code> is not included as an output argument and the read operation was not successful, then a warning message is returned to the command line.</p> <p>The <code>ValuesReceived</code> property value is increased by the number of values read – including the terminator – each time <code>fgets</code> is issued.</p> <p>If you use the <code>help</code> command to display help for <code>fgets</code>, then you need to supply the pathname shown below.</p> <pre>help serial /fgets</pre>								

Rules for Completing a Read Operation with fgets

A read operation with `fgets` blocks access to the MATLAB command line until:

- The terminator specified by the Terminator property is reached.
- The time specified by the Timeout property passes.
- The input buffer is filled.

Example

Create the serial port object `s`, connect `s` to a Tektronix TDS 210 oscilloscope, and write the RS232? command with the `fprintf` function. RS232? instructs the scope to return serial port communications settings.

```
s = serial('COM1');
fopen(s)
fprintf(s, 'RS232?')
```

Since the default value for the ReadAsyncMode property is continuous, data is automatically returned to the input buffer.

```
s.BytesAvailable
ans =
17
```

Use `fgets` to read the data returned from the previous write operation, and include the terminator.

```
settings = fgets(s)
settings =
9600; 0; 0; NONE; LF
length(settings)
ans =
17
```

Disconnect `s` from the scope, and remove `s` from memory and the workspace.

```
fclose(s)
delete(s)
clear s
```

See Also**Functions**

`fgetl`, `fopen`

Properties

`BytesAvailable`, `BytesAvailableFcn`, `InputBufferSize`, `Status`, `Terminator`, `Timeout`, `ValuesReceived`

fieldnames

Purpose	Return field names of a structure, or property names of a MATLAB object or Java object
Syntax	<pre>names = fieldnames(s) names = fieldnames(obj) names = fieldnames(obj, '-full')</pre>
Description	<p><code>names = fieldnames(s)</code> returns a cell array of strings containing the structure field names associated with the structure <code>s</code>.</p> <p><code>names = fieldnames(obj)</code> returns a cell array of strings containing the names of the public data fields associated with <code>obj</code>, which is either a MATLAB or a Java object.</p> <p><code>names = fieldnames(obj, '-full')</code> returns a cell array of strings containing the name, type, attributes, and inheritance of each field associated with <code>obj</code>, which is either a MATLAB or a Java object.</p>
Examples	<p>Given the structure</p> <pre>mystr(1, 1).name = 'alice'; mystr(1, 1).ID = 0; mystr(2, 1).name = 'gertrude'; mystr(2, 1).ID = 1</pre> <p>the command <code>n = fieldnames(mystr)</code> yields</p> <pre>n = {'name' 'ID'}</pre> <p>In another example, if <code>x</code> is an object of Java class <code>java.awt.Frame</code>, the command <code>fieldnames(x)</code> results in the display</p> <pre>ans = {'width' 'height'}</pre>
See Also	<code>getfield</code> , <code>setfield</code> , <code>rmfield</code>

Purpose	Test if figure is on screen
Syntax	<pre>[flag] = figflag('figurename') [flag, fig] = figflag('figurename') [...] = figflag('figurename', silent)</pre>
Description	<p>Use <code>figflag</code> to determine if a particular figure exists, bring a figure to the foreground, or set the window focus to a figure.</p> <p><code>[flag] = figflag('figurename')</code> returns a 1 if the figure named '<code>figurename</code>' exists and pops the figure to the foreground; otherwise this function returns 0.</p> <p><code>[flag, fig] = figflag('figurename')</code> returns a 1 in <code>flag</code>, returns the figure's handle in <code>fig</code>, and pops the figure to the foreground, if the figure named '<code>figurename</code>' exists. Otherwise this function returns 0.</p> <p><code>[...] = figflag('figurename', silent)</code> pops the figure window to the foreground if <code>silent</code> is 0, and leaves the figure in its current position if <code>silent</code> is 1.</p>
Examples	<p>To determine if a figure window named 'Fluid Jet Simulation' exists, type</p> <pre>[flag, fig] = figflag('Fluid Jet Simulation')</pre> <p>MATLAB returns:</p> <pre>flag = 1 fig = 1</pre> <p>If two figures with handles 1 and 3 have the name 'Fluid Jet Simulation', MATLAB returns:</p> <pre>flag = 1 fig = 1 3</pre>
See Also	<code>figure</code>

figure

Purpose	Create a figure graphics object
Syntax	<pre>figure figure('PropertyName', PropertyValue, . . .) figure(h) h = figure(. . .)</pre>
Description	<p>figure creates figure graphics objects. figure objects are the individual windows on the screen in which MATLAB displays graphical output.</p> <p>figure creates a new figure object using default property values.</p> <p>figure('PropertyName', PropertyValue, . . .) creates a new figure object using the values of the properties specified. MATLAB uses default values for any properties that you do not explicitly define as arguments.</p> <p>figure(h) does one of two things, depending on whether or not a figure with handle h exists. If h is the handle to an existing figure, figure(h) makes the figure identified by h the current figure, makes it visible, and raises it above all other figures on the screen. The current figure is the target for graphics output. If h is not the handle to an existing figure, but is an integer, figure(h) creates a figure, and assigns it the handle h. figure(h) where h is not the handle to a figure, and is not an integer, is an error.</p> <p>h = figure(. . .) returns the handle to the figure object.</p>
Remarks	<p>To create a figure object, MATLAB creates a new window whose characteristics are controlled by default figure properties (both factory installed and user defined) and properties specified as arguments. See the properties section for a description of these properties.</p> <p>You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see the set and get reference pages for examples of how to specify these data types).</p> <p>Use set to modify the properties of an existing figure or get to query the current values of figure properties.</p> <p>The gcf command returns the handle to the current figure and is useful as an argument to the set and get commands.</p>

Example


To create a figure window that is one quarter the size of your screen and is positioned in the upper-left corner, use the root object's `ScreenSize` property to determine the size. `ScreenSize` is a four-element vector: [left, bottom, width, height]:

```
scrsz = get(0, 'ScreenSize');  
figure('Position', [1 scrsz(4)/2 scrsz(3)/2 scrsz(4)/2])
```

See Also

`axes`, `uicontrol`, `uimenu`, `close`, `clf`, `gcf`, `rootobject`

Object Hierarchy



Setting Default Properties

You can set default figure properties only on the root level.

```
set(0, 'DefaultFigureProperty', PropertyValue...)
```

Where `Property` is the name of the figure property and `PropertyValue` is the value you are specifying. Use `set` and `get` to access figure properties.

figure

Property List The following table lists all figure properties and provides a brief description of each. The property name links bring you an expanded description of the properties.

Property Name	Property Description	Property Value
Positioning the Figure		
Position	Location and size of figure	Value: a 4-element vector [left, bottom, width, height] Default: depends on display
Units	Units used to interpret the Position property	Values: inches, centimeters, normalized, points, pixels, characters Default: pixels
Specifying Style and Appearance		
Color	Color of the figure background	Values: ColorSpec Default: depends on color scheme (see colordef)
MenuBar	Toggle the figure menu bar on and off	Values: none, figure Default: figure
Name	Figure window title	Values: string Default: '' (empty string)
NumberTitle	Display "Figure No. n", where n is the figure number	Values: on, off Default: on
Resize	Specify whether the figure window can be resized using the mouse	Values: on, off Default: on
SelectionHighlight	Highlight figure when selected (Selected property set to on)	Values: on, off Default: on
Visible	Make the figure visible or invisible	Values: on, off Default: on

Property Name	Property Description	Property Value
WindowStyle	Select normal or modal window	Values: normal, modal Default: normal
Controlling the Colormap		
Colormap	The figure colormap	Values: m-by-3 matrix of RGB values Default: jet colormap
Dithermap	Colormap used for truecolor data on pseudocolor displays	Values: m-by-3 matrix of RGB values Default: colormap with full range of colors
DithermapMode	Enable MATLAB-generated dithermap	Values: auto, manual Default: manual
FixedColors	Colors not obtained from colormap	Values: m-by-3 matrix of RGB values (read only)
MinColormap	Minimum number of system color table entries to use	Values: scalar Default: 64
ShareColors	Allow MATLAB to share system color table slots	Values on, off Default: on
Specifying Transparency		
Alphamap	The figure alphamap	m-by-1 matrix of alpha values
Specifying the Renderer		
BackingStore	Enable off screen pixel buffering	Values: on, off Default: on
DoubleBuffer	Flash-free rendering for simple animations	Values: on, off Default: off

figure

Property Name	Property Description	Property Value
Renderer	Rendering method used for screen and printing	Values: painters, zbuffer, OpenGL Default: automatic selection by MATLAB

General Information About the Figure

Children	Handle of any uicontrol, uimenu, and uicontextmenu objects displayed in the figure	Values: vector of handles
FileName	Used by guide	String
Parent	The root object is the parent of all figures	Value: always 0
Selected	Indicate whether figure is in a "selected" state.	Values: on, off Default: on
Tag	User-specified label	Value: any string Default: '' (empty string)
Type	The type of graphics object (read only)	Value: the string 'figure'
UserData	User-specified data	Values: any matrix Default: [] (empty matrix)
RendererMode	Automatic or user-selected renderer	Values: auto, manual Default: auto

Information About Current State

CurrentAxes	Handle of the current axes in this figure	Values: axes handle
CurrentCharacter	The last key pressed in this figure	Values: single character
CurrentObject	Handle of the current object in this figure	Values: graphics object handle

Property Name	Property Description	Property Value
CurrentPoint	Location of the last button click in this figure	Values: 2-element vector [x-coord, y-coord]
SelectionType	Mouse selection type	Values: normal, extended, alt, open
Callback Routine Execution		
BusyAction	Specify how to handle callback routine interruption	Values: cancel, queue Default: queue
ButtonDownFcn	Define a callback routine that executes when a mouse button is pressed on an unoccupied spot in the figure	Values: string Default: empty string
CloseRequestFcn	Define a callback routine that executes when you call the close command	Values: string Default: closereq
CreateFcn	Define a callback routine that executes when a figure is created	Values: string Default: empty string
DeleteFcn	Define a callback routine that executes when the figure is deleted (via close or delete)	Values: string Default: empty string
Interruptible	Determine if callback routine can be interrupted	Values: on, off Default: on (can be interrupted)
KeyPressFcn	Define a callback routine that executes when a key is pressed in the figure window	Values: string Default: empty string
ResizeFcn	Define a callback routine that executes when the figure is resized	Values: string Default: empty string
UIContextMenu	Associate a context menu with the figure	Values: handle of a Uicontextmenu

figure

Property Name	Property Description	Property Value
WindowButtonDownFcn	Define a callback routine that executes when you press the mouse button down in the figure	Values: string Default: empty string
WindowButtonMotionFcn	Define a callback routine that executes when you move the pointer in the figure	Values: string Default: empty string
WindowButtonUpFcn	Define a callback routine that executes when you release the mouse button	Values: string Default: empty string

Controlling Access to Objects

IntegerHandle	Specify integer or noninteger figure handle	Values: on, off Default: on (integer handle)
HandleVisibility	Determine if figure handle is visible to users or not	Values: on, callback, off Default: on
HitTest	Determine if the figure can become the current object (see the figure CurrentObject property)	Values: on, off Default: on
NextPlot	Determine how to display additional graphics to this figure	Values: add, replace, replacechildren Default: add

Defining the Pointer

Pointer	Select the pointer symbol	Values: crosshair, arrow, watch, topleft, topright, bottomleft, bottomright, cross, fleur, left, right, top, bottom, fullcrosshair, ibeam, custom Default: arrow
---------	---------------------------	---

Property Name	Property Description	Property Value
PointerShapeCData	Data that defines the pointer	Values: 16-by-16 matrix Default: set Pointer to custom and see
PointerShapeHotSpot	Specify the pointer active spot	Values: 2-element vector [row, column] Default: [1, 1]

Properties That Affect Printing

InvertHardcopy	Change figure colors for printing	Values: on, off Default: on
PaperOrientation	Horizontal or vertical paper orientation	Values: portrait, landscape Default: portrait
PaperPosition	Control positioning figure on printed page	Values: 4-element vector [left, bottom, width, height]
PaperPositionMode	Enable WYSIWYG printing of figure	Values: auto, manual Default: manual
PaperSize	Size of the current PaperType specified in PaperUnits	Values: [width, height]
PaperType	Select from standard paper sizes	Values: see property description Default: usletter
PaperUnits	Units used to specify the PaperSize and PaperPosition	Values: normalized, inches, centimeters, points Default: inches
Controlling the XWindows Display (UNIX only)		

figure

Property Name	Property Description	Property Value
XDisplay	Specify display for MATLAB (UNIX only)	Values: display identifier Default: :0.0
XVisual	Select visual used by MATLAB (UNIX only)	Values: visual ID
XVisualMode	Auto or manual selection of visual (UNIX only)	Values: auto, manual Default: auto

Modifying Properties

You can set and query graphics object properties in two ways:

- The Property Editor is an interactive tool that enables you to see and change object property values.
- The set and get commands enable you to set and query the values of properties

To change the default value of properties see [SettingCreating_Plots Default Property Values](#).

Figure Property Descriptions

This section lists property names along with the type of values each accepts. Curly braces { } enclose default values.

Alphamap m-by-1 matrix of alpha values

Figure alphamap. This property is an m-by-1 array of non-NaN alpha values. MATLAB accesses alpha values by their row number. For example, an index of 1 specifies the first alpha value, an index of 2 specifies the second alpha value, and so on. Alphamaps can be any length. The default alphamap contains 64 values that progress linearly from 0 to 1.

Alphamaps affect the rendering of surface, image, and patch objects, but do not affect other graphics objects.

BackingStore {on} | off

Off screen pixel buffer. When BackingStore is on, MATLAB stores a copy of the figure window in an off-screen pixel buffer. When obscured parts of the figure window are exposed, MATLAB copies the window contents from this buffer rather than regenerating the objects on the screen. This increases the speed with which the screen is redrawn.

While refreshing the screen quickly is generally desirable, the buffers required do consume system memory. If memory limitations occur, you can set BackingStore to off to disable this feature and release the memory used by the buffers. If your computer does not support backingstore, setting the BackingStore property results in a warning message, but has no other effect.

Setting BackingStore to off can increase the speed of animations because it eliminates the need to draw into both an off-screen buffer and the figure window.

Figure Properties

BusyAction cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback routines. If there is a callback routine executing, subsequently invoked callback routines always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are:

- cancel – discard the event that attempted to execute a second callback routine.
- queue – queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn string

Button press callback function. A callback routine that executes whenever you press a mouse button while the pointer is in the figure window, but not over a child object (i.e., uicontrol, axes, or axes child). Define this routine as a string that is a valid MATLAB expression or the name of an M-file. The expression executes in the MATLAB workspace.

Children vector of handles

Children of the figure. A vector containing the handles of all axes, uicontrol, uicontextmenu, and uimenu objects displayed within the figure. You can change the order of the handles and thereby change the stacking of the objects on the display.

Clipping {on} | off

This property has no effect on figures.

CloseRequestFcn string

Function executed on figure close. This property defines a function that MATLAB executes whenever you issue the close command (either a close(figure_handle) or a close all), when you close a figure window from the computer's window manager menu, or when you quit MATLAB.

The CloseRequestFcn provides a mechanism to intervene in the closing of a figure. It allows you to, for example, display a dialog box to ask a user to confirm or cancel the close operation or to prevent users from closing a figure that contains a GUI.

The basic mechanism is:

- A user issues the close command from the command line, by closing the window from the computer's window manager menu, or by quitting MATLAB.
- The close operation executes the function defined by the figure CloseRequestFcn. The default function is named closereq and is predefined as:

```
shh = get(0, 'ShowHiddenHandles');  
set(0, 'ShowHiddenHandles', 'on');  
currFig = get(0, 'CurrentFigure');  
set(0, 'ShowHiddenHandles', shh);  
delete(currFig);
```

These statements unconditionally delete the current figure, destroying the window. closereq takes advantage of the fact that the close command makes all figures specified as arguments the current figure before calling the respective close request function.

You can set CloseRequestFcn to any string that is a valid MATLAB statement, including the name of an M-file. For example,

```
set(gcf, 'CloseRequestFcn', 'disp(''This window is immortal'')')
```

This close request function never closes the figure window; it simply echoes "This window is immortal" on the command line. Unless the close request function calls delete, MATLAB never closes the figure. (Note that you can always call delete(*figure_handle*) from the command line if you have created a window with a nondestructive close request function.)

A more useful application of the close request function is to display a question dialog box asking the user to confirm the close operation. The following M-file illustrates how to do this.

```
% my_closereq  
% User-defined close request function  
% to display a question dialog box
```

Figure Properties

```
selection = questdlg('Close Specified Figure?', ...
    'Close Request Function', ...
    'Yes', 'No', 'Yes');

switch selection,
case 'Yes',
    delete(gcf)
case 'No'
    return
end
```

Now assign this M-file to the CloseRequestFcn of a figure:

```
set(figure_handle, 'CloseRequestFcn', 'my_closereq')
```

To make this M-file your default close request function, set a default value on the root level.

```
set(0, 'DefaultFigureCloseRequestFcn', 'my_closereq')
```

MATLAB then uses this setting for the CloseRequestFcn of all subsequently created figures.

Color Col orSpec

Background color. This property controls the figure window background color. You can specify a color using a three-element vector of RGB values or one of MATLAB's predefined names. See Col orSpec for more information.

Colormap m-by-3 matrix of RGB values

Figure colormap. This property is an m-by-3 array of red, green, and blue (RGB) intensity values that define m individual colors. MATLAB accesses colors by their row number. For example, an index of 1 specifies the first RGB triplet, an index of 2 specifies the second RGB triplet, and so on. Colormaps can be any length (up to 256 only on MS-Windows), but must be three columns wide. The default figure colormap contains 64 predefined colors.

Colormaps affect the rendering of surface, image, and patch objects, but generally do not affect other graphics objects. See colormap and Col orSpec for more information.

CreateFcn string

Callback routine executed during object creation. This property defines a callback routine that executes when MATLAB creates a figure object. You must define this property as a default value for figures. For example, the statement,

```
set(0, 'DefaultFigureCreateFcn', ...
    'set(gcbo, ''IntegerHandle'', ''off'')')
```

defines a default value on the root level that causes the created figure to use noninteger handles whenever you (or MATLAB) create a figure. MATLAB executes this routine after setting all properties for the figure. Setting this property on an existing figure object has no effect.

The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

CurrentAxes handle of current axes

Target axes in this figure. MATLAB sets this property to the handle of the figure's current axes (i.e., the handle returned by the gca command when this figure is the current figure). In all figures for which axes children exist, there is always a current axes. The current axes does not have to be the topmost axes, and setting an axes to be the CurrentAxes does not restack it above all other axes.

You can make an axes current using the axes and set commands. For example, axes(*axes_handle*) and set(gcf, 'CurrentAxes', *axes_handle*) both make the axes identified by the handle *axes_handle* the current axes. In addition, axes(*axes_handle*) restacks the axes above all other axes in the figure.

If a figure contains no axes, get(gcf, 'CurrentAxes') returns the empty matrix. Note that the gca function actually creates an axes if one does not exist.

CurrentCharacter single character

Last key pressed. MATLAB sets this property to the last key pressed in the figure window. CurrentCharacter is useful for obtaining user input.

CurrentMenu (Obsolete)

This property produces a warning message when queried. It has been superseded by the root CallbackObject property.

Figure Properties

CurrentObject object handle

Handle of current object. MATLAB sets this property to the handle of the object that is under the current point (see the CurrentPoint property). This object is the front-most object in the view. You can use this property to determine which object a user has selected. The function gco provides a convenient way to retrieve the CurrentObject of the CurrentFigure.

CurrentPoint two-element vector: [x-coordinate, y-coordinate]

Location of last button click in this figure. MATLAB sets this property to the location of the pointer at the time of the most recent mouse button press. MATLAB updates this property whenever you press the mouse button while the pointer is in the figure window.

In addition, MATLAB updates CurrentPoint before executing callback routines defined for the figure WindowButtonMotionFcn and WindowButtonUpFcn properties. This enables you to query CurrentPoint from these callback routines. It behaves like this:

- If there is no callback routine defined for the WindowButtonMotionFcn or the WindowButtonUpFcn, then MATLAB updates the CurrentPoint only when the mouse button is pressed down within the figure window.
- If there is a callback routine defined for the WindowButtonMotionFcn, then MATLAB updates the CurrentPoint just before executing the callback. Note that the WindowButtonMotionFcn executes only within the figure window unless the mouse button is pressed down within the window and then held down while the pointer is moved around the screen. In this case, the routine executes (and the CurrentPoint is updated) anywhere on the screen until the mouse button is released.
- If there is a callback routine defined for the WindowButtonUpFcn, MATLAB updates the CurrentPoint just before executing the callback. Note that the WindowButtonUpFcn executes only while the pointer is within the figure window unless the mouse button is pressed down initially within the window. In this case, releasing the button anywhere on the screen triggers callback execution, which is preceded by an update of the CurrentPoint.

The figure CurrentPoint is updated only when certain events occur, as previously described. In some situations, (such as when the WindowButtonMotionFcn takes a long time to execute and the pointer is moved very rapidly) the CurrentPoint may not reflect the actual location of the

pointer, but rather the location at the time when the `WindowButtonMotionFcn` began execution.

The `CurrentPoint` is measured from the lower-left corner of the figure window, in units determined by the `Units` property.

The `RootPointerLocation` property contains the location of the pointer updated synchronously with pointer movement. However, the location is measured with respect to the screen, not a figure window.

See `uicontrol` for information on how this property is set when you click on a `uicontrol` object.

DeleteFcn string

Delete figure callback routine. A callback routine that executes when the figure object is deleted (e.g., when you issue a `delete` or a `close` command). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine.

The handle of the object whose `DeleteFcn` is being executed is accessible only through the `RootCallbackObject` property, which you can query using `gcbobj`.

Dithermap m-by-3 matrix of RGB values

Colormap used for true-color data on pseudocolor displays. This property defines a colormap that MATLAB uses to dither true-color CDATA for display on pseudocolor (8-bit or less) displays. MATLAB maps each RGB color defined as true-color CDATA to the closest color in the dithermap. The default `Dithermap` contains colors that span the full spectrum so any color values map reasonably well.

However, if the true-color data contains a wide range of shades in one color, you may achieve better results by defining your own dithermap. See the `DithermapMode` property.

DithermapMode auto | {manual}

MATLAB generated dithermap. In `manual` mode, MATLAB uses the colormap defined in the `Dithermap` property to display direct color on pseudocolor displays. When `DithermapMode` is `auto`, MATLAB generates a dithermap based on the colors currently displayed. This is useful if the default dithermap does not produce satisfactory results.

Figure Properties

The process of generating the dithermap can be quite time consuming and is repeated whenever MATLAB re-renders the display (e.g., when you add a new object or resize the window). You can avoid unnecessary regeneration by setting this property back to manual and save the generated dithermap (which MATLAB loads into the Dithermap property).

DoubleBuffer on | {off}

Flash-free rendering for simple animations. Double buffering is the process of drawing to an off-screen pixel buffer and then blitting the buffer contents to the screen once the drawing is complete. Double buffering generally produces flash-free rendering for simple animations (such as those involving lines, as opposed to objects containing large numbers of polygons). Use double buffering with the animated objects' EraseMode property set to normal. Use the set command to enable double buffering.

```
set(figure_handle, 'DoubleBuffer', 'on')
```

Double buffering works only when the figure Renderer property is set to painters.

FileName String

GUI FIG-file name. GUIDE stores the name of the FIG-file used to save the GUI layout in this property.

FixedColors m-by-3 matrix of RGB values (read only)

Non-colormap colors. Fixed colors define all colors appearing in a figure window that are not obtained from the figure colormap. These colors include axis lines and labels, the color of line, text, uicontrol, and uimenu objects, and any colors that you explicitly define, for example, with a statement like:

```
set(gcf, 'Color', [0.3, 0.7, 0.9]).
```

Fixed color definitions reside in the system color table and do not appear in the figure colormap. For this reason, fixed colors can limit the number of simultaneously displayed colors if the number of fixed colors plus the number of entries in the figure colormap exceed your system's maximum number of colors.

(See the root ScreenDepth property for information on determining the total number of colors supported on your system. See the MinColorMap and

ShareColors properties for information on how MATLAB shares colors between applications.)

HandleVisibility {on} | callback | off (GUIDE default off)

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when HandleVisibility is on.

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes `get`, `findobj`, `gca`, `gcf`, `gco`, `newplot`, `cla`, `clf`, and `close`.

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's `Children` property, figures do not appear in the root's `CurrentFigure` property, objects do not appear in the root's `CallbackObject` property or in the figure's `CurrentObject` property, and axes do not appear in their parent's `CurrentAxes` property.

You can set the root `ShowHiddenHandles` property to `on` to make all handles visible, regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

Figure Properties

Hi tTest {on} | off

Selectable by mouse click. Hi tTest determines if the figure can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the figure. If Hi tTest is off, clicking on the figure sets the CurrentObject to the empty matrix.

IntegerHandle {on} | off (GUIDE default off)

Figure handle mode. Figure object handles are integers by default. When creating a new figure, MATLAB uses the lowest integer that is not used by an existing figure. If you delete a figure, its integer handle can be reused.

If you set this property to off, MATLAB assigns nonreusable real-number handles (e.g., 67.0001221) instead of integers. This feature is designed for dialog boxes where removing the handle from integer values reduces the likelihood of inadvertently drawing into the dialog box.

Interruptible {on} | off

Callback routine interruption mode. The Interruptible property controls whether a figure callback routine can be interrupted by subsequently invoked callback routines. Only callback routines defined for the ButtonDownFcn, KeyPressFcn, WindowButtonDownFcn, WindowButtonMotionFcn, and WindowButtonUpFcn are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback routine only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

InvertHardcopy {on} | off

Change hardcopy to black objects on white background. This property affects only printed output. Printing a figure having a background color (Color property) that is not white results in poor contrast between graphics objects and the figure background and also consumes a lot of printer toner.

When InvertHardCopy is on, MATLAB eliminates this effect by changing the color of the figure and axes to white and the axis lines, tick marks, axis labels, etc., to black. Lines, text, and the edges of patches and surfaces may be changed depending on the print command options specified.

If you set InvertHardCopy to off, the printed output matches the colors displayed on the screen.

See print for more information on printing MATLAB figures.

KeyPressFcn string

Key press callback function. A callback routine invoked by a key press occurring in the figure window. You can define KeyPressFcn as any legal MATLAB expression or the name of an M-file.

The callback routine can query the figure's CurrentCharacter property to determine what particular key was pressed and thereby limit the callback execution to specific keys.

The callback routine can also query the root PointerWindow property to determine in which figure the key was pressed. Note that pressing a key while the pointer is in a particular figure window does not make that figure the current figure (i.e., the one referred by the gcf command).

MenuBar none | {figure} (GUIDE default none)

Enable-disable figure menu bar. This property enables you to display or hide the menu bar placed at the top of a figure window. The default (figure) is to display the menu bar.

This property affects only built-in menus. Menus defined with the ui menu command are not affected by this property.

MinColormap scalar (default = 64)

Minimum number of color table entries used. This property specifies the minimum number of system color table entries used by MATLAB to store the colormap defined for the figure (see the Colormap property). In certain situations, you may need to increase this value to ensure proper use of colors.

For example, suppose you are running color-intensive applications in addition to MATLAB and have defined a large figure colormap (e.g., 150 to 200 colors). MATLAB may select colors that are close but not exact from the existing colors in the system color table because there are not enough slots available to define all the colors you specified.

To ensure MATLAB uses exactly the colors you define in the figure colormap, set MinColormap equal to the length of the colormap.

```
set(gcf, 'MinColormap', length(get(gcf, 'Colormap')))
```

Note that the larger the value of MinColormap, the greater the likelihood other windows (including other MATLAB figure windows) will display in false colors.

Figure Properties

Name string

Figure window title. This property specifies the title displayed in the figure window. By default, Name is empty and the figure title is displayed as Figure No. 1, Figure No. 2, and so on. When you set this parameter to a string, the figure title becomes Figure No. 1: <string>. See the NumberTitle property.

NextPlot {add} | replace | replacechildren

How to add next plot. NextPlot determines which figure MATLAB uses to display graphics output. If the value of the current figure is:

- add — use the current figure to display graphics (the default).
- replace — reset all figure properties, except Position, to their defaults and delete all figure children before displaying graphics (equivalent to clf reset).
- replacechildren — remove all child objects, but do not reset figure properties (equivalent to clf).

The newplot function provides an easy way to handle the NextPlot property. Also see the NextPlot axes property and Controlling creating_plotsGraphics Output for more information.

NumberTitle {on} | off (GUIDE default off)

Figure window title number. This property determines whether the string Figure No. N (where N is the figure number) is prefixed to the figure window title. See the Name property.

PaperOrientation {portrait} | landscape

Horizontal or vertical paper orientation. This property determines how printed figures are oriented on the page. portrait orients the longest page dimension vertically; landscape orients the longest page dimension horizontally. See the orient command for more detail.

PaperPosition four-element rect vector

Location on printed page. A rectangle that determines the location of the figure on the printed page. Specify this rectangle with a vector of the form

```
rect = [left, bottom, width, height]
```

where left specifies the distance from the left side of the paper to the left side of the rectangle and bottom specifies the distance from the bottom of the page

to the bottom of the rectangle. Together these distances define the lower-left corner of the rectangle. `width` and `height` define the dimensions of the rectangle. The `PaperUnits` property specifies the units used to define this rectangle.

PaperPositionMode `auto` | {`manual`}

WYSIWYG printing of figure. In `manual` mode, MATLAB honors the value specified by the `PaperPosition` property. In `auto` mode, MATLAB prints the figure the same size as it appears on the computer screen, centered on the page.

PaperSize [`width` `height`]

Paper size. This property contains the size of the current `PaperType`, measured in `PaperUnits`. See `PaperType` to select standard paper sizes.

PaperType Select a value from the following table

Selection of standard paper size. This property sets the `PaperSize` to the one of the following standard sizes.

Property Value	Size (Width x Height)
usletter (default)	8.5-by-11 inches
uslegal	11-by-14 inches
tabloid	11-by-17 inches
A0	841-by-1189mm
A1	594-by-841mm
A2	420-by-594mm
A3	297-by-420mm
A4	210-by-297mm
A5	148-by-210mm
B0	1029-by-1456mm
B1	728-by-1028mm
B2	514-by-728mm

Figure Properties

Property Value	Size (Width x Height)
B3	364-by-514mm
B4	257-by-364mm
B5	182-by-257mm
arch-A	9-by-12 inches
arch-B	12-by-18 inches
arch-C	18-by-24 inches
arch-D	24-by-36 inches
arch-E	36-by-48 inches
A	8.5-by-11 inches
B	11-by-17 inches
C	17-by-22 inches
D	22-by-34 inches
E	34-by-43 inches

Note that you may need to change the `PaperPosition` property in order to position the printed figure on the new paper size. One solution is to use `normalized PaperUnits`, which enables MATLAB to automatically size the figure to occupy the same relative amount of the printed page, regardless of the paper size.

PaperUnits `normalized` | `{inches}` | `centimeters` | `points`

Hardcopy measurement units. This property specifies the units used to define the `PaperPosition` and `PaperSize` properties. All units are measured from the lower-left corner of the page. `normalized` units map the lower-left corner of the page to $(0, 0)$ and the upper-right corner to $(1.0, 1.0)$. `inches`, `centimeters`, and `points` are absolute units (one point equals $1/72$ of an inch).

If you change the value of `PaperUnits`, it is good practice to return it to its default value after completing your computation so as not to affect other functions that assume `PaperUnits` is set to the default value.

Parent handle

Handle of figure's parent. The parent of a figure object is the root object. The handle to the root is always 0.

Pointer	crosshair {arrow} watch top
	top bot bot circ cross
	fleur left right top bottom
	full crosshair i beam custom

Pointer symbol selection. This property determines the symbol used to indicate the pointer (cursor) position in the figure window. Setting `Pointer` to `custom` allows you to define your own pointer symbol. See the `PointerShapeCData` property for more information. See also the *Using MATLAB Graphics* manual.

PointerShapeCData 16-by-16 matrix

User-defined pointer. This property defines the pointer that is used when you set the `Pointer` property to `custom`. It is a 16-by-16 element matrix defining the 16-by-16 pixel pointer using the following values:

- 1 – color pixel black
- 2 – color pixel white
- NaN – make pixel transparent (underlying screen shows through)

Element (1,1) of the `PointerShapeCData` matrix corresponds to the upper-left corner of the pointer. Setting the `Pointer` property to one of the predefined pointer symbols does not change the value of the `PointerShapeCData`. Computer systems supporting 32-by-32 pixel pointers fill only one quarter of the available pixmap.

PointerShapeHotSpot 2-element vector

Pointer active area. A two-element vector specifying the row and column indices in the `PointerShapeCData` matrix defining the pixel indicating the pointer location. The location is contained in the `CurrentPoint` property and the root object's `PointerLocation` property. The default value is element (1,1), which is the upper-left corner.

Figure Properties

Position four-element vector

Figure position. This property specifies the size and location on the screen of the figure window. Specify the position rectangle with a four-element vector of the form:

```
rect = [left, bottom, width, height]
```

where `left` and `bottom` define the distance from the lower-left corner of the screen to the lower-left corner of the figure window. `width` and `height` define the dimensions of the window. See the `Units` property for information on the units used in this specification. The `left` and `bottom` elements can be negative on systems that have more than one monitor.

You can use the `get` function to obtain this property and determine the position of the figure and you can use the `set` function to resize and move the figure to a new location.

Renderer painters | zbuffer | OpenGL

Rendering method used for screen and printing. This property enables you to select the method used to render MATLAB graphics. The choices are:

- `painters` – MATLAB's original rendering method is faster when the figure contains only simple or small graphics objects.
- `zbuffer` – MATLAB draws graphics object faster and more accurately because objects are colored on a per pixel basis and MATLAB renders only those pixels that are visible in the scene (thus eliminating front-to-back sorting errors). Note that this method can consume a lot of system memory if MATLAB is displaying a complex scene.
- `OpenGL` – OpenGL is a renderer that is available on many computer systems. This renderer is generally faster than `painters` or `zbuffer` and in some cases enables MATLAB to access graphics hardware that is available on some systems.

Using the OpenGL Renderer

Hardware vs. Software OpenGL Implementations

There are two kinds of OpenGL implementations – hardware and software.

The hardware implementation makes use of special graphics hardware to increase performance and is therefore significantly faster than the software version. Many computers have this special hardware available as an option or may come with this hardware right out of the box.

Software implementations of OpenGL are much like the ZBuffer renderer that is available on MATLAB version 5.0, however, OpenGL generally provides superior performance to ZBuffer.

OpenGL Availability

OpenGL is available on all computers that MATLAB runs on. MATLAB automatically finds hardware versions of OpenGL if they are available. If the hardware version is not available, then MATLAB uses the software version.

The software versions that are available on different platforms are:

- On UNIX systems, MATLAB uses the software version of OpenGL that is included in the MATLAB distribution.
- On MS-Windows NT 4.0, OpenGL is available as part of the operating system.
- On MS-Windows 95, OpenGL is included in the Windows 95 OSR 2 release. If you do not have this release, the libraries are available on the Microsoft ftp site.

Microsoft version is available at the URL:

`ftp://ftp.microsoft.com/softlib/mslfiles/opengl95.exe`

There is also a Silicon Graphics version of OpenGL for Windows 95 that is available at the URL:

`http://www.sgi.com`

Tested Hardware Versions

On MS-Windows platforms, there are many graphics boards that accelerate OpenGL. The MathWorks has tested MATLAB on the AccelECLIPSE board from AccelGraphics.

On UNIX platforms, The MathWorks has tested MATLAB on Sparc Ultra with the Creator 3D board and Silicon Graphics computers running IRIX 6.4 or newer.

Determining What Version You Are Using

To determine the version and vendor of the OpenGL library that MATLAB is using on your system, type the following command at the MATLAB prompt

`opengl info`

Figure Properties

This command also returns a string of extensions to the OpenGL specification that are available with the particular library MATLAB is using. This information is helpful to The MathWorks, so please include this information if you need to report bugs.

OpenGL vs. Other MATLAB Renderers

There are some differences between drawings created with OpenGL and those created with the other renderers. The OpenGL specific differences include:

- OpenGL does not do colormap interpolation. If you create a surface or patch using indexed color and interpolated face or edge coloring, OpenGL will interpolate the colors through the RGB color cube instead of through the colormap.
- OpenGL does not support the phong value for the FaceLighting and EdgeLighting properties of surfaces and patches.

MATLAB issues a warning if you request nonsupported behavior.

Implementations of OpenGL Tested by The MathWorks

The following hardware versions have been tested:

- AccelECLIPSE by AccelGraphics
- Sol2/Creator 3D
- SGI

The following software versions have been tested:

- Mesa
- CosmoGL
- Microsoft's Windows 95 implementation
- NT 4.0

RendererMode { auto } | manual

Automatic, or user selection of Renderer. This property enables you to specify whether MATLAB should choose the Renderer based on the contents of the figure window, or whether the Renderer should remain unchanged.

When the `RendererMode` property is set to `auto`, MATLAB selects the rendering method for printing as well as for screen display based on the size and complexity of the graphics objects in the figure.

For printing, MATLAB switches to `zbuffer` at a greater scene complexity than for screen rendering because printing from a Z-buffered figure can be considerably slower than one using the painters rendering method, and can result in large PostScript files. However, the output does always match what is on the screen. The same holds true for OpenGL: the output is the same as that produced by the `ZBuffer` renderer – a bitmap with a resolution determined by the `print` command's `-r` option.

Criteria for Autoselection of OpenGL Renderer

When the `RendererMode` property is set to `auto`, MATLAB uses the following criteria to determine whether to select the OpenGL renderer:

If the `opengl` autoselection mode is `autoselect`, MATLAB selects OpenGL if:

- The host computer has OpenGL installed and is in True Color mode
- The figure contains no logarithmic axes
- MATLAB would select `zbuffer` based on figure contents
- Patch objects faces have no more than three vertices
- The figure contains less than 10 uicontrols
- No line objects use markers
- Phong lighting is not specified

Or

- Figure objects use transparency

When the `RendererMode` property is set to `manual`, MATLAB does not change the Renderer, regardless of changes to the figure contents.

Resize {on} | off

Window resize mode. This property determines if you can resize the figure window with the mouse. `on` means you can resize the window, `off` means you cannot. When `Resize` is `off`, the figure window does not display any resizing controls (such as boxes at the corners) to indicate that it cannot be resized.

Figure Properties

ResizeFcn string

Window resize callback routine. MATLAB executes the specified callback routine whenever you resize the figure window. You can query the figure's Position property to determine the new size and position of the figure window. During execution of the callback routine, the handle to the figure being resized is accessible only through the root CallbackObject property, which you can query using gcbo.

You can use ResizeFcn to maintain a GUI layout that is not directly supported by MATLAB's Position/Units paradigm.

For example, consider a GUI layout that maintains an object at a constant height in pixels and attached to the top of the figure, but always matches the width of the figure. The following ResizeFcn accomplishes this; it keeps the uicontrol whose Tag is 'StatusBar' 20 pixels high, as wide as the figure, and attached to the top of the figure. Note the use of the Tag property to retrieve the uicontrol handle, and the gcbo function to retrieve the figure handle. Also note the defensive programming regarding figure Units, which the callback requires to be in pixels in order to work correctly, but which the callback also restores to their previous value afterwards.

```
u = findobj('Tag', 'StatusBar');
fig = gcbo;
old_units = get(fig, 'Units');
set(fig, 'Units', 'pixels');
figpos = get(fig, 'Position');
upos = [0, figpos(4) - 20, figpos(3), 20];
set(u, 'Position', upos);
set(fig, 'Units', old_units);
```

You can change the figure Position from within the ResizeFcn callback; however the ResizeFcn is not called again as a result.

Note that the print command can cause the ResizeFcn to be called if the PaperPositionMode property is set to manual and you have defined a resize function. If you do not want your resize function called by print, set the PaperPositionMode to auto.

Selected on | off

Is object selected. This property indicates whether the figure is selected. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight {on} | off

figures do not indicate selection.

SelectionType {normal} | extend | alt | open

Mouse selection type. MATLAB maintains this property to provide information about the last mouse button press that occurred within the figure window. This information indicates the type of selection made. Selection types are actions that are generally associated with particular responses from the user interface software (e.g., single clicking on a graphics object places it in move or resize mode; double-clicking on a filename opens it, etc.).

The physical action required to make these selections varies on different platforms. However, all selection types exist on all platforms.

Selection Type	MS-Windows	X-Windows
Normal	Click left mouse button	Click left mouse button
Extend	Shift - click left mouse button or click both left and right mouse buttons	Shift - click left mouse button or click middle mouse button
Alternate	Control - click left mouse button or click right mouse button	Control - click left mouse button or click right mouse button
Open	Double click any mouse button	Double click any mouse button

Note that the List Box style of uicontrols set the figure SelectionType property to normal to indicate a single mouse click or to open to indicate a double mouse click. See `uicontrol` for information on how this property is set when you click on a uicontrol object.

Figure Properties

ShareColors {on} | off

Share slots in system colortable with like colors. This property affects the way MATLAB stores the figure colormap in the system color table. By default, MATLAB looks at colors already defined and uses those slots to assign pixel colors. This leads to an efficient use of color resources (which are limited on systems capable of displaying 256 or less colors) and extends the number of figure windows that can simultaneously display correct colors.

However, in situations where you want to change the figure colormap quickly without causing MATLAB to re-render the displayed graphics objects, you should disable color sharing (set ShareColors to off). In this case, MATLAB can swap one colormap for another without changing pixel color assignments because all the slots in the system color table used for the first colormap are replaced with the corresponding color in the second colormap. (Note that this applies only in cases where both colormaps are the same length and where the computer hardware allows user modification of the system color table.)

Tag string (GUIDE sets this property)

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines.

For example, suppose you want to direct all graphics output from an M-file to a particular figure, regardless of user actions that may have changed the current figure. To do this, identify the figure with a Tag.

```
figure('Tag', 'Plotting Figure')
```

Then make that figure the current figure before drawing by searching for the Tag with findobj.

```
figure(findobj('Tag', 'Plotting Figure'))
```

Type string (read only)

Object class. This property identifies the kind of graphics object. For figure objects, Type is always the string 'figure'.

UIContextMenu handle of a uicontextmenu object

Associate a context menu with the figure. Assign this property the handle of a uicontextmenu object created in the figure. Use the ui contextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the figure.

Units {pixels | normalized | inches | centimeters | points | characters}
(Guide default characters)

Units of measurement. This property specifies the units MATLAB uses to interpret size and location data. All units are measured from the lower-left corner of the window.

- normalized units map the lower-left corner of the figure window to (0,0) and the upper-right corner to (1.0,1.0).
- inches, centimeters, and points are absolute units (one point equals 1/72 of an inch).
- The size of a pixel depends on screen resolution.
- Characters units are defined by characters from the default system font; the width of one character is the width of the letter x, the height of one character is the distance between the baselines of two lines of text.

This property affects the CurrentPoint and Position properties. If you change the value of Units, it is good practice to return it to its default value after completing your computation so as not to affect other functions that assume Units is set to the default value.

When specifying the units as property/value pairs during object creation, you must set the Units property before specifying the properties that you want to use these units.

UserData matrix

User specified data. You can specify UserData as any matrix you want to associate with the figure object. The object does not use this data, but you can access it using the set and get commands.

Visible {on} | off

Object visibility. The Visible property determines whether an object is displayed on the screen. If the Visible property of a figure is off, the entire figure window is invisible.

Figure Properties

WindowButtonDownFcn string

Button press callback function. Use this property to define a callback routine that MATLAB executes whenever you press a mouse button while the pointer is in the figure window. Define this routine as a string that is a valid MATLAB expression or the name of an M-file. The expression executes in the MATLAB workspace.

See `ui control` for information on how this property is set when you click on a `uicontrol` object.

WindowButtonMotionFcn string

Mouse motion callback function. Use this property to define a callback routine that MATLAB executes whenever you move the pointer within the figure window. Define this routine as a string that is a valid MATLAB expression or the name of an M-file. The expression executes in the MATLAB workspace.

WindowButtonUpFcn string

Button release callback function. Use this property to define a callback routine that MATLAB executes whenever you release a mouse button. Define this routine as a string that is a valid MATLAB expression or the name of an M-file. The expression executes in the MATLAB workspace.

The button up event is associated with the figure window in which the preceding button down event occurred. Therefore, the pointer need not be in the figure window when you release the button to generate the button up event.

If the callback routines defined by `WindowButtonDownFcn` or `WindowButtonMotionFcn` contain `drawnow` commands or call other functions that contain `drawnow` commands and the `Interruptible` property is set to `off`, the `WindowButtonUpFcn` may not be called. You can prevent this problem by setting `Interruptible` to `on`.

WindowState {normal} | modal

Normal or modal window behavior. When `WindowState` is set to `modal`, the figure window traps all keyboard and mouse events over all MATLAB windows as long as they are visible. Windows belonging to applications other than MATLAB are unaffected. Modal figures remain stacked above all normal figures and the MATLAB command window. When multiple modal windows exist, the most recently created window keeps focus and stays above all other

windows until it becomes invisible, or is returned to `WindowStyle` `normal`, or is deleted. At that time, focus reverts to the window that last had focus.

Figures with `WindowStyle` `modal` and `Visible` `off` do not behave modally until they are made visible, so it is acceptable to hide a modal window instead of destroying it when you want to reuse it.

You can change the `WindowStyle` of a figure at any time, including when the figure is visible and contains children. However, on some systems this may cause the figure to flash or disappear and reappear, depending on the windowing-system's implementation of normal and modal windows. For best visual results, you should set `WindowStyle` at creation time or when the figure is invisible.

Modal figures do not display `uimenu` children or built-in menus, but it is not an error to create `uimenus` in a modal figure or to change `WindowStyle` to `modal` on a figure with `uimenu` children. The `uimenu` objects exist and their handles are retained by the figure. If you reset the figure's `WindowStyle` to `normal`, the `uimenus` are displayed.

Use modal figures to create dialog boxes that force the user to respond without being able to interact with other windows. Typing **Control C** at the MATLAB prompt causes all figures with `WindowStyle` `modal` to revert to `WindowStyle` `normal`, allowing you to type at the command line.

XDi spl ay display identifier (UNIX only)

Specify display for MATLAB. You can display figure windows on different displays using the `XDi spl ay` property. For example, to display the current figure on a system called fred, use the command:

```
set(gcf, 'XDi spl ay', 'fred: 0. 0')
```

XVi sual visual identifier (UNIX only)

Select visual used by MATLAB. You can select the visual used by MATLAB by setting the `XVi sual` property to the desired visual ID. This can be useful if you want to test your application on an 8-bit or grayscale visual. To see what visuals are avail on your system, use the UNIX `xdpvi nfo` command. From MATLAB, type

```
!xdpyi nfo
```

Figure Properties

The information returned will contain a line specifying the visual ID. For example,

```
visual id: 0x21
```

To use this visual with the current figure, set the `XVisual` property to the ID.

```
set(gcf, 'XVisual', '0x21')
```

XVisual Mode auto | manual

Auto or manual selection of visual. `Visual` Mode can take on two values – `auto` (the default) and `manual`. In `auto` mode, MATLAB selects the best visual to use based on the number of colors, availability of the OpenGL extension, etc. In `manual` mode, MATLAB does not change the visual from the one currently in use. Setting the `XVisual` property sets this property to `manual`.


Purpose	Display the Current Directory browser, a tool for viewing current directory files
Graphical Interface	As an alternative to the <code>filebrowser</code> function, select Current Directory from the View menu in the MATLAB desktop.
Syntax	<code>filebrowser</code>
Description	<code>filebrowser</code> displays the Current Directory browser.

Use the pathname edit box to view directories and their contents

Click the find button to search for content within M-files

Double-click a file to open it in an appropriate tool

View the help portion of the selected M-file



See Also

`cd`, `pwd`

file formats

Purpose Readable file formats

Description This table shows the file formats that MATLAB is capable of reading.

File Format	Extension	File Content	Read Command	Returns
Text	MAT	Saved MATLAB workspace	load	Variables in the file
	CSV	Comma-separated numbers	csvread	Double array
	DLM	Delimited text	dlmread	Double array
	TAB	Tab-separated text	dlmread	Double array
Scientific Data	CDF	Data in Common Data Format	cdfread	Cell array of CDF records
	FITS	Flexible Image Transport System data	fitsread	Primary or extension table data
	HDF	Data in Hierarchical Data Format	hdfread	HDF or HDF-EOS data set
Spreadsheet	XLS	Excel worksheet	xlsread	Double or cell array
	WK1	Lotus 123 worksheet	wk1read	Double or cell array

file formats

File Format	Extension	File Content	Read Command	Returns
Image	TIFF	TIFF image	<code>imread</code>	Truecolor, grayscale or indexed image(s)
	PNG	PNG image	<code>imread</code>	Truecolor, grayscale or indexed image
	HDF	HDF image	<code>imread</code>	Truecolor, grayscale or indexed image(s)
	BMP	BMP image	<code>imread</code>	Truecolor or indexed image
	JPEG	JPEG image	<code>imread</code>	Truecolor or grayscale image
	GIF	GIF image	<code>imread</code>	Indexed image
	PCX	PCX image	<code>imread</code>	Indexed image
	XWD	XWD image	<code>imread</code>	Indexed image
	CUR	Cursor image	<code>imread</code>	Indexed image
	ICO	Icon image	<code>imread</code>	Indexed image

file formats

File Format	Extension	File Content	Read Command	Returns
Image	TIFF	TIFF image	<code>imread</code>	Truecolor, grayscale or indexed image(s)
	PNG	PNG image	<code>imread</code>	Truecolor, grayscale or indexed image
	HDF	HDF image	<code>imread</code>	Truecolor, grayscale or indexed image(s)
	BMP	BMP image	<code>imread</code>	Truecolor or indexed image
	JPEG	JPEG image	<code>imread</code>	Truecolor or grayscale image
	GIF	GIF image	<code>imread</code>	Indexed image
	PCX	PCX image	<code>imread</code>	Indexed image
	XWD	XWD image	<code>imread</code>	Indexed image
	CUR	Cursor image	<code>imread</code>	Indexed image
	ICO	Icon image	<code>imread</code>	Indexed image

File Format	Extension	File Content	Read Command	Returns
Image	TIFF	TIFF image	<code>imread</code>	Truecolor, grayscale or indexed image(s)
	PNG	PNG image	<code>imread</code>	Truecolor, grayscale or indexed image
	HDF	HDF image	<code>imread</code>	Truecolor, grayscale or indexed image(s)
	BMP	BMP image	<code>imread</code>	Truecolor or indexed image
	JPEG	JPEG image	<code>imread</code>	Truecolor or grayscale image
	GIF	GIF image	<code>imread</code>	Indexed image
	PCX	PCX image	<code>imread</code>	Indexed image
	XWD	XWD image	<code>imread</code>	Indexed image
	CUR	Cursor image	<code>imread</code>	Indexed image
	ICO	Icon image	<code>imread</code>	Indexed image

file formats

File Format	Extension	File Content	Read Command	Returns
Image	TIFF	TIFF image	<code>imread</code>	Truecolor, grayscale or indexed image(s)
	PNG	PNG image	<code>imread</code>	Truecolor, grayscale or indexed image
	HDF	HDF image	<code>imread</code>	Truecolor, grayscale or indexed image(s)
	BMP	BMP image	<code>imread</code>	Truecolor or indexed image
	JPEG	JPEG image	<code>imread</code>	Truecolor or grayscale image
	GIF	GIF image	<code>imread</code>	Indexed image
	PCX	PCX image	<code>imread</code>	Indexed image
	XWD	XWD image	<code>imread</code>	Indexed image
	CUR	Cursor image	<code>imread</code>	Indexed image
	ICO	Icon image	<code>imread</code>	Indexed image

File Format	Extension	File Content	Read Command	Returns
Audio file	AU	NeXT/Sun sound	auread	Sound data and sample rate
	WAV	Microsoft Wave sound	wavread	Sound data and sample rate
Movie	AVI	Movie	avi read	MATLAB movie

See Also

`fscanf`, `fread`, `textread`, `importdata`

fileparts

Purpose	Return filename parts
Syntax	<code>[pathstr, name, ext, versn] = fileparts('filename')</code>
Description	<code>[pathstr, name, ext, versn] = fileparts('filename')</code> returns the path, filename, extension, and version for the specified file. The returned ext field contains a dot (.) before the file extension.
	The <code>fileparts</code> function is platform dependent.
	You can reconstruct the file from the parts using
	<code>fullfile(pathstr, [name ext versn])</code>
Examples	This example returns the parts of file to path, name, ext, and ver. <code>file = '\home\user4\matlab\classpath.txt';</code> <code>[pathstr, name, ext, versn] = fileparts(file)</code> <code>pathstr =</code> <code>\home\user4\matlab</code> <code>name =</code> <code>classpath</code> <code>ext =</code> <code>.txt</code> <code>versn =</code> <code>' '</code>
See Also	<code>fullfile</code>

Purpose	Return the directory separator for this platform
Syntax	<code>f = filesep</code>
Description	<code>f = filesep</code> returns the platform-specific file separator character. The file separator is the character that separates individual directory names in a path string.
Examples	<p>On the PC</p> <pre>i ofun_di r = [' tool box' filesep ' matlab' filesep ' i ofun'] i ofun_di r = tool box\matlab\i ofun</pre> <p>On a UNIX system</p> <pre>i odi r = [' tool box' filesep ' matlab' filesep ' i ofun'] i odi r = tool box/matlab/i ofun</pre>
See Also	<code>fullfile</code> , <code>fileparts</code>

Purpose	Filled two-dimensional polygons
Syntax	<code>fill(X, Y, C)</code> <code>fill(X, Y, Col orSpec)</code> <code>fill(X1, Y1, C1, X2, Y2, C2, ...)</code> <code>fill(..., 'PropertyName', PropertyValue)</code> <code>h = fill(...)</code>
Description	The <code>fill</code> function creates colored polygons. <code>fill(X, Y, C)</code> creates filled polygons from the data in <code>X</code> and <code>Y</code> with vertex color specified by <code>C</code> . <code>C</code> is a vector or matrix used as an index into the colormap. If <code>C</code> is a row vector, <code>length(C)</code> must equal <code>size(X, 2)</code> and <code>size(Y, 2)</code> ; if <code>C</code> is a column vector, <code>length(C)</code> must equal <code>size(X, 1)</code> and <code>size(Y, 1)</code> . If necessary, <code>fill</code> closes the polygon by connecting the last vertex to the first. <code>fill(X, Y, Col orSpec)</code> fills two-dimensional polygons specified by <code>X</code> and <code>Y</code> with the color specified by <code>Col orSpec</code> . <code>fill(X1, Y1, C1, X2, Y2, C2, ...)</code> specifies multiple two-dimensional filled areas. <code>fill(..., 'PropertyName', PropertyValue)</code> allows you to specify property names and values for a patch graphics object. <code>h = fill(...)</code> returns a vector of handles to patch graphics objects, one handle per patch object.
Remarks	If <code>X</code> or <code>Y</code> is a matrix, and the other is a column vector with the same number of elements as rows in the matrix, <code>fill</code> replicates the column vector argument to produce a matrix of the required size. <code>fill</code> forms a vertex from corresponding elements in <code>X</code> and <code>Y</code> and creates one polygon from the data in each column. The type of color shading depends on how you specify color in the argument list. If you specify color using <code>Col orSpec</code> , <code>fill</code> generates flat-shaded polygons by setting the patch object's <code>FaceCol</code> or property to the corresponding RGB triple. If you specify color using <code>C</code> , <code>fill</code> scales the elements of <code>C</code> by the values specified by the axes property <code>CLim</code> . After scaling <code>C</code> , <code>C</code> indexes the current colormap.


If C is a row vector, fill generates flat-shaded polygons where each element determines the color of the polygon defined by the respective column of the X and Y matrices. Each patch object's FaceCol or property is set to 'flat'. Each row element becomes the CDat a property value for the nth patch object, where *n* is the corresponding column in X or Y.

If C is a column vector or a matrix, fill uses a linear interpolation of the vertex colors to generate polygons with interpolated colors. It sets the patch graphics object FaceCol or property to 'interp' and the elements in one column become the CDat a property value for the respective patch object. If C is a column vector, fill replicates the column vector to produce the required sized matrix.

Examples

Create a red octagon.

```
t = (1/16: 1/8: 1)' *2*pi;  
x = sin(t);  
y = cos(t);  
fill(x, y, 'r')  
axis square
```



See Also

axis, caxis, colormap, ColormapSpec, fill3, patch

fill3

Purpose	Filled three-dimensional polygons
Syntax	<code>fill3(X, Y, Z, C)</code> <code>fill3(X, Y, Z, Col orSpec)</code> <code>fill3(X1, Y1, Z1, C1, X2, Y2, Z2, C2, ...)</code> <code>fill3(..., 'PropertyName', PropertyValue)</code> <code>h = fill3(...)</code>
Description	The <code>fill3</code> function creates flat-shaded and Gouraud-shaded polygons.
	<code>fill3(X, Y, Z, C)</code> fills three-dimensional polygons. <code>X</code> , <code>Y</code> , and <code>Z</code> triplets specify the polygon vertices. If <code>X</code> , <code>Y</code> , or <code>Z</code> is a matrix, <code>fill3</code> creates n polygons, where n is the number of columns in the matrix. <code>fill3</code> closes the polygons by connecting the last vertex to the first when necessary.
	<code>C</code> specifies color, where <code>C</code> is a vector or matrix of indices into the current colormap. If <code>C</code> is a row vector, <code>length(C)</code> must equal <code>size(X, 2)</code> and <code>size(Y, 2)</code> ; if <code>C</code> is a column vector, <code>length(C)</code> must equal <code>size(X, 1)</code> and <code>size(Y, 1)</code> .
	<code>fill3(X, Y, Z, Col orSpec)</code> fills three-dimensional polygons defined by <code>X</code> , <code>Y</code> , and <code>Z</code> with color specified by <code>Col orSpec</code> .
	<code>fill3(X1, Y1, Z1, C1, X2, Y2, Z2, C2, ...)</code> specifies multiple filled three-dimensional areas.
	<code>fill3(..., 'PropertyName', PropertyValue)</code> allows you to set values for specific patch properties.
	<code>h = fill3(...)</code> returns a vector of handles to patch graphics objects, one handle per patch.
Algorithm	If <code>X</code> , <code>Y</code> , and <code>Z</code> are matrices of the same size, <code>fill3</code> forms a vertex from the corresponding elements of <code>X</code> , <code>Y</code> , and <code>Z</code> (all from the same matrix location), and creates one polygon from the data in each column. If <code>X</code> , <code>Y</code> , or <code>Z</code> is a matrix, <code>fill3</code> replicates any column vector argument to produce matrices of the required size. If you specify color using <code>Col orSpec</code> , <code>fill3</code> generates flat-shaded polygons and sets the patch object <code>FaceCol</code> or property to an RGB triple.

If you specify color using C, fill3 scales the elements of C by the axes property CLim, which specifies the color axis scaling parameters, before indexing the current colormap.

If C is a row vector, fill3 generates flat-shaded polygons and sets the FaceCol or property of the patch objects to 'flat'. Each element becomes the CData property value for the respective patch object.


If C is a column vector or a matrix, fill3 generates polygons with interpolated colors and sets the patch object FaceCol or property to 'interp'. fill3 uses a linear interpolation of the vertex colormap indices when generating polygons with interpolated colors. The elements in one column become the CData property value for the respective patch object. If C is a column vector, fill3 replicates the column vector to produce the required sized matrix.

Examples

Create four triangles with interpolated colors.

```
X = [0 1 1 2; 1 1 2 2; 0 0 1 1];
Y = [1 1 1 1; 1 0 1 0; 0 0 0 0];
Z = [1 1 1 1; 1 0 1 0; 0 0 0 0];
C = [0.5000 1.0000 1.0000 0.5000;
     1.0000 0.5000 0.5000 0.1667;
     0.3330 0.3330 0.5000 0.5000];
fill3(X, Y, Z, C)
```

fill3



See Also

[axi s](#), [caxis](#), [colormap](#), [ColorSpec](#), [fill](#), [patch](#)

Purpose Filter data with an infinite impulse response (IIR) or finite impulse response (FIR) filter

Syntax

```
y = filter(b, a, X)
[y, zf] = filter(b, a, X)
[y, zf] = filter(b, a, X, zi)
y = filter(b, a, X, zi, dim)
[...] = filter(b, a, X, [], dim)
```

Description The `filter` function filters a data sequence using a digital filter which works for both real and complex inputs. The filter is a *direct form II transposed* implementation of the standard difference equation (see “Algorithm”).

`y = filter(b, a, X)` filters the data in vector `X` with the filter described by numerator coefficient vector `b` and denominator coefficient vector `a`. If `a(1)` is not equal to 1, `filter` normalizes the filter coefficients by `a(1)`. If `a(1)` equals 0, `filter` returns an error.

If `X` is a matrix, `filter` operates on the columns of `X`. If `X` is a multidimensional array, `filter` operates on the first nonsingleton dimension.

`[y, zf] = filter(b, a, X)` returns the final conditions, `zf`, of the filter delays. Output `zf` is a vector of `max(size(a), size(b))` or an array of such vectors, one for each column of `X`.

`[y, zf] = filter(b, a, X, zi)` accepts initial conditions and returns the final conditions, `zi` and `zf` respectively, of the filter delays. Input `zi` is a vector (or an array of vectors) of length `max(length(a), length(b)) - 1`.


`y = filter(b, a, X, zi, dim)` and

`[...] = filter(b, a, X, [], dim)` operate across the dimension `dim`.

filter

Algorithm

The filter function is implemented as a direct form II transposed structure,



or

$$y(n) = b(1)x(n) + b(2)x(n-1) + \dots + b(nb+1)x(n-nb) - a(2)y(n-1) - \dots - a(na+1)y(n-na)$$

where $n-1$ is the filter order, and which handles both FIR and IIR filters [1].

The operation of filter at sample m is given by the time domain difference equations

$$y(m) = b(1)x(m) + z_1(m-1)$$

$$z_1(m) = b(2)x(m) + z_2(m-1) - a(2)y(m)$$

$$\vdots = \vdots \vdots$$

$$z_{n-2}(m) = b(n-1)x(m) + z_{n-1}(m-1) - a(n-1)y(m)$$

$$z_{n-1}(m) = b(n)x(m) - a(n)y(m)$$

The input-output description of this filtering operation in the z -transform domain is a rational transfer function,

$$Y(z) = \frac{b(1) + b(2)z^{-1} + \dots + b(nb+1)z^{-nb}}{1 + a(2)z^{-1} + \dots + a(na+1)z^{-na}} X(z)$$

See Also

filter2

filtfilt in the Signal Processing Toolbox

References

[1] Oppenheim, A. V. and R.W. Schafer. *Discrete-Time Signal Processing*, Englewood Cliffs, NJ: Prentice-Hall, 1989, pp. 311-312.

Purpose	Two-dimensional digital filtering
Syntax	$Y = \text{filter2}(h, X)$ $Y = \text{filter2}(h, X, \text{shape})$
Description	$Y = \text{filter2}(h, X)$ filters the data in X with the two-dimensional FIR filter in the matrix h . It computes the result, Y , using two-dimensional correlation, and returns the central part of the correlation that is the same size as X . $Y = \text{filter2}(h, X, \text{shape})$ returns the part of Y specified by the shape parameter. shape is a string with one of these values: <ul style="list-style-type: none">'full' Returns the full two-dimensional correlation. In this case, Y is larger than X.'same' (default) Returns the central part of the correlation. In this case, Y is the same size as X.'valid' Returns only those parts of the correlation that are computed without zero-padded edges. In this case, Y is smaller than X.
Remarks	Two-dimensional correlation is equivalent to two-dimensional convolution with the filter matrix rotated 180 degrees. See the Algorithm section for more information about how <code>filter2</code> performs linear filtering.
Algorithm	Given a matrix X and a two-dimensional FIR filter h , <code>filter2</code> rotates your filter matrix 180 degrees to create a convolution kernel. It then calls <code>conv2</code> , the two-dimensional convolution function, to implement the filtering operation. <code>filter2</code> uses <code>conv2</code> to compute the full two-dimensional convolution of the FIR filter with the input matrix. By default, <code>filter2</code> then extracts the central part of the convolution that is the same size as the input matrix, and returns this as the result. If the shape parameter specifies an alternate part of the convolution for the result, <code>filter2</code> returns the appropriate part.
See Also	<code>conv2</code> , <code>filter</code>

find

Purpose	Find indices and values of nonzero elements
Syntax	<pre>k = find(x) [i,j] = find(X) [i,j,v] = find(X)</pre>
Description	<p><code>k = find(X)</code> returns the indices of the array <code>X</code> that point to nonzero elements. If none is found, <code>find</code> returns an empty matrix.</p> <p><code>[i,j] = find(X)</code> returns the row and column indices of the nonzero entries in the matrix <code>X</code>. This is often used with sparse matrices.</p> <p><code>[i,j,v] = find(X)</code> returns a column vector <code>v</code> of the nonzero entries in <code>X</code>, as well as row and column indices.</p> <p>In general, <code>find(X)</code> regards <code>X</code> as <code>X(:)</code>, which is the long column vector formed by concatenating the columns of <code>X</code>.</p>
Examples	<p><code>[i,j,v] = find(X~=0)</code> produces a vector <code>v</code> with all 1s, and returns the row and column indices.</p> <p>Some operations on a vector</p> <pre>x = [11 0 33 0 55]'; find(x) ans = 1 3 5 find(x == 0) ans = 2 4 find(0 < x & x < 10*pi)</pre>

```
ans =
```

```
1
```

And on a matrix

```
M = magic(3)
```

```
M =
```

```
8      1      6  
3      5      7  
4      9      2
```

```
[i,j,v] = find(M > 6)
```

```
i =           j =           v =
```

```
1           1           1  
3           2           1  
2           3           1
```

See Also

`nonzeros`, `sparse`, `colon`, `logical operators`, `relational operators`

findall

Purpose	Find handles of all graphics objects
Syntax	<pre>object_handles = findall(handle_list)</pre> <pre>object_handles = findall(handle_list, 'property', 'value', ...)</pre>
Description	<pre>object_handles = findall(handle_list)</pre> returns the handles of all objects in the hierarchy under the objects identified in handle_list. <pre>object_handles = findall(handle_list, 'property', 'value', ...)</pre> returns the handles of all objects in the hierarchy under the objects identified in handle_list that have the specified properties set to the specified values.
Remarks	findall is similar to findobj, except that it finds objects even if their HandleVisibility is set to off.
Examples	<pre>plot(1:10)</pre> <pre>xlabel xlabel</pre> <pre>a = findall(gcf)</pre> <pre>b = findobj(gcf)</pre> <pre>c = findall(b, 'Type', 'text') % return the xlabel handle twice</pre> <pre>d = findobj(b, 'Type', 'text') % can't find the xlabel handle</pre>
See Also	allchild, findobj

Purpose	Find visible off-screen figures
Syntax	<code>findfigs</code>
Description	<p><code>findfigs</code> finds all visible figure windows whose display area is off the screen and positions them on the screen.</p> <p>A window appears to MATLAB to be off-screen when its display area (the area not covered by the window's title bar, menu bar, and toolbar) does not appear on the screen.</p> <p>This function is useful when bringing an application from a larger monitor to a smaller one (or one with lower resolution). Windows visible on the larger monitor may appear off-screen on a smaller monitor. Using <code>findfigs</code> ensures that all windows appear on the screen.</p>

findobj

Purpose	Locate graphics objects
Syntax	<pre>h = findobj h = findobj ('PropertyName', PropertyValue, ...) h = findobj (objhandles, ...) h = findobj (objhandles, 'flat', 'PropertyName', PropertyValue, ...)</pre>
Description	<p><code>findobj</code> locates graphics objects and returns their handles. You can limit the search to objects with particular property values and along specific branches of the hierarchy.</p> <p><code>h = findobj</code> returns the handles of the root object and all its descendants.</p> <p><code>h = findobj ('PropertyName', PropertyValue, ...)</code> returns the handles of all graphics objects having the property <code>PropertyName</code>, set to the value <code>PropertyValue</code>. You can specify more than one property/value pair, in which case, <code>findobj</code> returns only those objects having all specified values.</p> <p><code>h = findobj (objhandles, ...)</code> restricts the search to objects listed in <code>objhandles</code> and their descendants.</p> <p><code>h = findobj (objhandles, 'flat', 'PropertyName', PropertyValue, ...)</code> restricts the search to those objects listed in <code>objhandles</code> and does not search descendants.</p>
Remarks	<p><code>findobj</code> returns an error if a handle refers to a non-existent graphics object.</p> <p><code>Findobj</code> correctly matches any legal property value. For example,</p> <pre>findobj ('Color', 'r')</pre> <p>finds all objects having a <code>Color</code> property set to red, <code>r</code>, or <code>[1 0 0]</code>.</p> <p>When a graphics object is a descendant of more than one object identified in <code>objhandles</code>, MATLAB searches the object each time <code>findobj</code> encounters its handle. Therefore, implicit references to a graphics object can result in its handle being returned multiple times.</p>
Examples	<p>Find all line objects in the current axes:</p> <pre>h = findobj (gca, 'Type', 'line')</pre>

See Also

`copyobj`, `gcf`, `gca`, `gcbo`, `gco`, `get`, `set`

Graphics objects include:

`axes`, `figure`, `image`, `light`, `line`, `patch`, `surface`, `text`, `uicontrol`, `uimenu`

findstr

Purpose	Find a string within another, longer string
Syntax	<code>k = findstr(str1, str2)</code>
Description	<code>k = findstr(str1, str2)</code> searches the longer of the two input strings for any occurrences of the shorter string, returning the starting index of each such occurrence in the double array, <code>k</code> . If no occurrences are found, then <code>findstr</code> returns the empty array, <code>[]</code> .
	The search performed by <code>findstr</code> is case sensitive. Any leading and trailing blanks in either input string are explicitly included in the comparison.
	Unlike the <code>strfind</code> function, the order of the input arguments to <code>findstr</code> is not important. This can be useful if you are not certain which of the two input strings is the longer one.
Examples	<pre>s = 'Find the starting indices of the shorter string.'; findstr(s, 'the') ans = 6 30 findstr('the', s) ans = 6 30</pre>
See Also	<code>strfind</code> , <code>strmatch</code> , <code>strtok</code> , <code>strcmp</code> , <code>strncmp</code> , <code>strcmpi</code> , <code>strncmpi</code>

Purpose	MATLAB termination M-file
Description	When MATLAB quits, it runs a script called <code>fini sh. m</code> , if it exists and is on the MATLAB search path. This is a file that you create yourself in order to have MATLAB perform any final tasks just prior to terminating. For example, you may want to save the data in your workspace to a MAT-file before MATLAB exits.
	<code>fini sh. m</code> is invoked whenever you do one of the following:
	<ul style="list-style-type: none"> • Select the close box  in the MATLAB Desktop • Select Exit MATLAB from the desktop File menu • Type <code>quit</code> or <code>exit</code> at the Command Window prompt
Remarks	When using Handle Graphics in <code>fini sh. m</code> , use <code>ui wai t</code> , <code>wai tfor</code> , or <code>drawnow</code> so that figures are visible. See the reference pages for these functions for more information.
Examples	<p>Two sample <code>fini sh. m</code> files are provided with MATLAB in tool box/local. Use them to help you create your own <code>fini sh. m</code>, or rename one of the files to <code>fini sh. m</code> to use it.</p> <ul style="list-style-type: none"> • <code>fini shsav. m</code> - saves the workspace to a MAT-file when MATLAB quits. • <code>fini shdl g. m</code> - displays a dialog allowing you to cancel quitting; it uses <code>qui t cancel</code> and contains the following code. <pre>button = questdlg('Ready to quit?', ... 'Exit Dialog', 'Yes', 'No', 'No'); switch button case 'Yes', disp('Exiting MATLAB'); %Save variables to matlab.mat save case 'No', qui t cancel; end</pre>
See Also	<code>qui t</code> , <code>startup</code>

fitsinfo

Purpose	Return information about a FITS file
Syntax	<code>S = fitsinfo(filename)</code>
Description	<code>S = fitsinfo(filename)</code> returns a structure whose fields contain information about the contents of a Flexible Image Transport System (FITS) file. <code>filename</code> is a string that specifies the name of the FITS file.

The structure, S, obtained from a basic FITS file, contains the following fields.

Information Returned From a Basic FITS File

Fieldname	Description	Return Type
Contents	List of extensions in the file in the order that they occur	Cell array of Strings
FileModDate	File modification date	String
Filename	Name of the file	String
FileSize	Size of the file in bytes	Double
PrimaryData	Information about the primary data in the FITS file	Structure array

A FITS file may also include any number of extensions. For such files, `fitsinfo` returns a structure, S, with the fields listed above plus one or more of the following structure arrays.

Additional Information Returned From FITS Extensions

Fieldname	Description	Return Type
AsciiTable	ASCII Table extensions	Structure array
BinaryTable	Binary Table extensions	Structure array
Image	Image extensions	Structure array
Unknown	Nonstandard extensions	Structure array

The tables that follow show the fields of each of the structure arrays that can be returned by `fitsinfo`.

Note For all `Intercept` and `Slope` fieldnames below, the equation used to calculate actual values is, `actual_value = (Slope * array_value) + Intercept`.

Fields of the PrimaryData Structure Array

Fieldname	Description	Return Type
<code>DataSize</code>	Size of the primary data in bytes	Double
<code>DataType</code>	Precision of the data	String
<code>Intercept</code>	Value, used with <code>Slope</code> , to calculate actual pixel values from the array pixel values	Double
<code>Keywords</code>	Keywords, values and comments of the header in each column	Cell array of strings
<code>MissingDataValue</code>	Value used to represent undefined data	Double
<code>Offset</code>	Number of bytes from beginning of the file to the first data value	Double
<code>Size</code>	Sizes of each dimension	Double array
<code>Slope</code>	Value, used along with <code>Intercept</code> , to calculate actual pixel values from the array pixel values	Double

Fields of the AsciiTable Structure Array

Fieldname	Description	Return Type
DataSize	Size of the data in the ASCII Table in bytes	Double
FieldFormat	Formats in which each field is encoded, using FORTRAN-77 format codes	Cell array of strings
FieldPos	Starting column for each field	Double array
FieldPrecision	Precision in which the values in each field are stored	Cell array of strings
FieldWidth	Number of characters in each field	Double array
Intercept	Values, used along with Slope, to calculate actual data values from the array data values	Double array
Keywords	Keywords, values and comments in the ASCII table header	Cell array of strings
MissingDataValue	Representation of undefined data in each field	Cell array of strings
NFields	Number of fields in each row	Double array
Offset	Number of bytes from beginning of the file to the first data value	Double
Rows	Number of rows in the table	Double
RowSize	Number of characters in each row	Double
Slope	Values, used with Intercept, to calculate actual data values from the array data values	Double array

Fields of the BinaryTable Structure Array

Fieldname	Description	Return Type
DataSize	Size of the data in the Binary Table, in bytes. Includes any data past the main part of the Binary Table.	Double
ExtensionOffset	Number of bytes from the beginning of the file to any data past the main part of the Binary Table	Double
ExtensionSize	Size of any data past the main part of the Binary Table, in bytes	Double
FieldFormat	Data type for each field, using FITS binary table format codes	Cell array of strings
FieldPrecision	Precisions in which the values in each field are stored	Cell array of strings
FieldSize	Number of values in each field	Double array
Intercept	Values, used along with Slope, to calculate actual data values from the array data values	Double array
Keywords	Keywords, values and comments in the Binary Table header	Cell array of strings
MissingDataValue	Representation of undefined data in each field	Cell array of double
NFields	Number of fields in each row	Double
Offset	Number of bytes from beginning of the file to the first data value	Double
Rows	Number of rows in the table	Double

Fields of the BinaryTable Structure Array

Fieldname	Description	Return Type
RowSize	Number of bytes in each row	Double
Sl ope	Values, used with Intercept, to calculate actual data values from the array data values	Double array

Fields of the Image Structure Array

Fieldname	Description	Return Type
DataSize	Size of the data in the Image extension in bytes	Double
DataType	Precision of the data	String
Intercept	Value, used along with Sl ope, to calculate actual pixel values from the array pixel values	Double
Keywords	Keywords, values and comments in the Image header	Cell array of strings
MissingDataValue	Representation of undefined data	Double
Offset	Number of bytes from the beginning of the file to the first data value	Double
Si ze	Sizes of each dimension	Double array
Sl ope	Value, used along with Intercept, to calculate actual pixel values from the array pixel values	Double

Fields of the Unknown Structure Array

Fieldname	Description	Return Type
DataSize	Size of the data in nonstandard extensions, in bytes	Double
DataType	Precision of the data	String
Intercept	Value, used along with Slope, to calculate actual data values from the array data values	Double
Keywords	Keywords, values and comments in the extension header	Cell array of strings
MissingDataValue	Representation of undefined data	Double
Offset	Number of bytes from beginning of the file to the first data value	Double
Size	Sizes of each dimension	Double array
Slope	Value, used along with Intercept, to calculate actual data values from the array data values	Double

Example

Use fitsinfo to obtain information about FITS file, `tst0012.fits`. In addition to its primary data, the file also contains three extensions: Binary Table, Image, and ASCII Table.

```
S = fitsinfo('tst0012.fits');
S =
    Flename: 'tst0012.fits'
    FileModDate: '27-Nov-2000 13:25:55'
    FileSize: 109440
    Contents: {'Primary' 'Binary Table' 'Image' 'ASCII'}
    PrimaryData: [1x1 struct]
    BinaryTable: [1x1 struct]
    Image: [1x1 struct]
    AsciiTable: [1x1 struct]
```

The PrimaryData substructure shows that the data resides in a 102-by-109 matrix of single-precision values. There are 44,472 bytes of primary data starting at an offset of 2,880 bytes from the start of the file.

```
S. PrimaryData
ans =
    DataType: 'single'
    Size: [102 109]
    DataSize: 44472
    MissingDataValue: []
    Intercept: 0
    Slope: 1
    Offset: 2880
    Keywords: {25x3 cell}
```

Examining the ASCII Table substructure, you can see that this table has 53 rows, 59 columns, and contains 8 fields per row. The last field in each row, for example, begins in the 55th column and contains a 4-digit integer.

```
S. Ascii Table
ans =
    Rows: 53
    RowSize: 59
    NFields: 8
    FieldFormat: {1x8 cell}
    FieldPrecision: {1x8 cell}
    FieldWidth: [9 6 2000 3 10 4000 20 1500 5 1 4]
    FieldPos: [1 11 18 22 33 54 54 55]
    DataSize: 3127
    MissingDataValue: {'*' '-' '-' '-' '*' [] '*' '*' '*' ''}
    Intercept: [0 0 -70 2000 0 0 0 0 0]
    Slope: [1 1 2 1000 1 1 1 1 1]
    Offset: 103680
    Keywords: {65x3 cell}
```

```
S. Ascii Table. FieldFormat
ans =
    'A9'    'F6.2'    'I3'    'E10.4'    'D20.15'    'A5'    'A1'    'I4'
```

The ASCII Table includes 65 keyword entries arranged in a 65-by-3 cell array.

```
key = S. Ascii Table. Keywords
```

```
key =
S. Asci i Tabl e. Keywords
ans =
' XTENSI ON'      ' TABLE'          [ 1x48 char]
' BITPIX'         [             8]  [ 1x48 char]
' NAXI S'         [             2]  [ 1x48 char]
' NAXIS1'         [            59]  [ 1x48 char]
.
.
.
.
```

One of the entries in this cell array is shown here. Each row of the array contains a keyword, its value, and comment.

```
key{ 2, : }

ans =
BITPIX                      % Keyword

ans =
8                           % Keyword val ue

ans =
Character data 8 bits per pixel    % Keyword comment
```

See Also

[fitsread](#)

fitsread

Purpose	Extract data from a FITS file												
Syntax	<pre>data = fitsread(filename) data = fitsread(filename, 'raw') data = fitsread(filename, extname) data = fitsread(filename, extname, index)</pre>												
Description	<p><code>data = fitsread(filename)</code> reads the primary data of the Flexible Image Transport System (FITS) file specified by <code>filename</code>. Undefined data values are replaced by NaN. Numeric data are scaled by the slope and intercept values and are always returned in double precision.</p> <p><code>data = fitsread(filename, extname)</code> reads data from a FITS file according to the data array or extension specified in <code>extname</code>. You can specify only one <code>extname</code>. The valid choices for <code>extname</code> are shown in the following table.</p>												
Data Arrays or Extensions													
<table border="1"><thead><tr><th><code>extname</code></th><th>Description</th></tr></thead><tbody><tr><td>'primary'</td><td>Read data from the primary data array</td></tr><tr><td>'table'</td><td>Read data from the ASCII Table extension</td></tr><tr><td>'binarytable'</td><td>Read data from the Binary Table extension</td></tr><tr><td>'image'</td><td>Read data from the Image extension</td></tr><tr><td>'unknown'</td><td>Read data from the Unknown extension</td></tr></tbody></table>		<code>extname</code>	Description	'primary'	Read data from the primary data array	'table'	Read data from the ASCII Table extension	'binarytable'	Read data from the Binary Table extension	'image'	Read data from the Image extension	'unknown'	Read data from the Unknown extension
<code>extname</code>	Description												
'primary'	Read data from the primary data array												
'table'	Read data from the ASCII Table extension												
'binarytable'	Read data from the Binary Table extension												
'image'	Read data from the Image extension												
'unknown'	Read data from the Unknown extension												
<p><code>data = fitsread(filename, extname, index)</code> is the same as the above syntax, except that if there is more than one of the specified extension type <code>extname</code> in the file, then only the one at the specified <code>index</code> is read.</p>													
<p><code>data = fitsread(filename, 'raw', ...)</code> reads the primary or extension data of the FITS file, but, unlike the above syntaxes, does not replace undefined data values with NaN and does not scale the data. The data returned has the same class as the data stored in the file.</p>													

Example

Read FITS file, `tst0012.fits`, into a 109-by-102 matrix called `data`.

```
data = fitsread('tst0012.fits');

whos data
  Name      Size            Bytes  Class
  data      109x102        88944  double array
```

Here is the beginning of the data read from the file.

```
data(1:5, 1:6)
ans =
  135.2000  134.9436  134.1752  132.8980  131.1165  128.8378
  137.1568  134.9436  134.1752  132.8989  131.1167  126.3343
  135.9946  134.9437  134.1752  132.8989  131.1185  128.1711
  134.0093  134.9440  134.1749  132.8983  131.1201  126.3349
  131.5855  134.9439  134.1749  132.8989  131.1204  126.3356
```

Read only the Binary Table extension from the file.

```
data = fitsread('tst0012.fits', 'bintable')

data =
  Columns 1 through 4
    {11x1 cell}  [11x1 int16]  [11x3 uint8]  [11x2 double]
  Columns 5 through 9
    [11x3 cell]  {11x1 cell}  [11x1 int8]  {11x1 cell}  [11x3 int32]
  Columns 10 through 13
    [11x2 int32]  [11x2 single]  [11x1 double]  [11x1 uint8]
```

See Also

`fitsinfo`

fix

Purpose	Round towards zero
Syntax	<code>B = fix(A)</code>
Description	<code>B = fix(A)</code> rounds the elements of <code>A</code> toward zero, resulting in an array of integers. For complex <code>A</code> , the imaginary and real parts are rounded independently.
Examples	<pre>a = [-1.9, -0.2, 3.4, 5.6, 7.0, 2.4+3.6i]</pre> <pre>a = Columns 1 through 4 -1.9000 -0.2000 3.4000 5.6000 Columns 5 through 6 7.0000 2.4000 + 3.6000i</pre> <pre>fix(a)</pre> <pre>ans = Columns 1 through 4 -1.0000 0 3.0000 5.0000 Columns 5 through 6 7.0000 2.0000 + 3.0000i</pre>
See Also	<code>ceil</code> , <code>floor</code> , <code>round</code>

Purpose Flip array along a specified dimension

Syntax $B = \text{fliplr}(A, \text{dim})$

Description $B = \text{fliplr}(A, \text{dim})$ returns A with dimension dim flipped.

When the value of dim is 1, the array is flipped row-wise down. When dim is 2, the array is flipped columnwise left to right. $\text{fliplr}(A, 1)$ is the same as $\text{fliplr}(A)$, and $\text{fliplr}(A, 2)$ is the same as $\text{fliplr}(A)$.

Examples $\text{fliplr}(A, 1)$ where

$A =$

1	4
2	5
3	6

produces

3	6
2	5
1	4

See Also fliplr , fliplr , permute , rot90

flplr

Purpose	Flip matrices left-right
Syntax	<code>B = flplr(A)</code>
Description	<code>B = flplr(A)</code> returns <code>A</code> with columns flipped in the left-right direction, that is, about a vertical axis.
	If <code>A</code> is a row vector, then <code>flplr(A)</code> returns a vector of the same length with the order of its elements reversed. If <code>A</code> is a column vector, then <code>flplr(A)</code> simply returns <code>A</code> .
Examples	If <code>A</code> is the 3-by-2 matrix,
	$A = \begin{matrix} 1 & 4 \\ 2 & 5 \\ 3 & 6 \end{matrix}$
	then <code>flplr(A)</code> produces
	$\begin{matrix} 4 & 1 \\ 5 & 2 \\ 6 & 3 \end{matrix}$
	If <code>A</code> is a row vector,
	$A = \begin{matrix} 1 & 3 & 5 & 7 & 9 \end{matrix}$
	then <code>flplr(A)</code> produces
	$\begin{matrix} 9 & 7 & 5 & 3 & 1 \end{matrix}$
Limitations	The array being operated on cannot have more than two dimensions. This limitation exists because the axis upon which to flip a multidimensional array would be undefined.
See Also	<code>flipdim</code> , <code>flipud</code> , <code>rot90</code>

Purpose	Flip matrices up-down
Syntax	$B = \text{fliplr}(A)$
Description	$B = \text{fliplr}(A)$ returns A with rows flipped in the up-down direction, that is, about a horizontal axis. If A is a column vector, then $\text{fliplr}(A)$ returns a vector of the same length with the order of its elements reversed. If A is a row vector, then $\text{fliplr}(A)$ simply returns A .
Examples	If A is the 3-by-2 matrix, $A = \begin{matrix} 1 & 4 \\ 2 & 5 \\ 3 & 6 \end{matrix}$ then $\text{fliplr}(A)$ produces $\begin{matrix} 3 & 6 \\ 2 & 5 \\ 1 & 4 \end{matrix}$
	If A is a column vector, $A = \begin{matrix} 3 \\ 5 \\ 7 \end{matrix}$ then $\text{fliplr}(A)$ produces $\begin{matrix} 7 \\ 5 \\ 3 \end{matrix}$
Limitations	The array being operated on cannot have more than two dimensions. This limitation exists because the axis upon which to flip a multidimensional array would be undefined.

flipud

See Also

[fli pdim](#), [fliplr](#), [rot90](#)

Purpose	Round towards minus infinity
Syntax	$B = \text{floor}(A)$
Description	$B = \text{floor}(A)$ rounds the elements of A to the nearest integers less than or equal to A. For complex A, the imaginary and real parts are rounded independently.
Examples	<pre>a = [-1.9, -0.2, 3.4, 5.6, 7.0, 2.4+3.6i]</pre> <pre>a = Columns 1 through 4 -1.9000 -0.2000 3.4000 5.6000 Columns 5 through 6 7.0000 2.4000 + 3.6000i</pre> <pre>floor(a)</pre> <pre>ans = Columns 1 through 4 -2.0000 -1.0000 3.0000 5.0000 Columns 5 through 6 7.0000 2.0000 + 3.0000i</pre>
See Also	ceil , fix , round

flops

Purpose	Count floating-point operations
Description	This is an obsolete function. With the incorporation of LAPACK in MATLAB version 6, counting floating-point operations is no longer practical.

Purpose	A simple function of three variables
Syntax	$v = \text{flow}$ $v = \text{flow}(n)$ $v = \text{flow}(x, y, z)$ $[x, y, z, v] = \text{flow}(\dots)$
Description	<p><code>flow</code>, a function of three variables, is the speed profile of a submerged jet within a infinite tank. <code>flow</code> is useful for demonstrating <code>slice</code>, <code>interp3</code>, and for generating scalar volume data.</p> <p><code>v = flow</code> produces a 50-by-25-by-25 array.</p> <p><code>v = flow(n)</code> produces a $2n$-by-n-by-n array.</p> <p><code>v = flow(x, y, z)</code> evaluates the speed profile at the points <code>x</code>, <code>y</code>, and <code>z</code>.</p> <p><code>[x, y, z, v] = flow(…)</code> returns the coordinates as well as the volume data.</p>

fmin

Purpose	Minimize a function of one variable						
<hr/>							
Note	The <code>fmin</code> function was replaced by <code>fminbnd</code> in Release 11 (MATLAB 5.3). In Release 12 (MATLAB 6.0), <code>fmin</code> displays a warning message and calls <code>fminbnd</code> .						
<hr/>							
Syntax	<pre>x = fmin('fun', x1, x2) x = fmin('fun', x1, x2, options) x = fmin('fun', x1, x2, options, P1, P2, ...) [x, options] = fmin(...)</pre>						
Description	<p><code>x = fmin('fun', x1, x2)</code> returns a value of <code>x</code> which is a local minimizer of <code>fun(x)</code> in the interval $x_1 < x < x_2$.</p> <p><code>x = fmin('fun', x1, x2, options)</code> does the same as the above, but uses <code>options</code> control parameters.</p> <p><code>x = fmin('fun', x1, x2, options, P1, P2, ...)</code> does the same as the above, but passes arguments to the objective function, <code>fun(x, P1, P2, ...)</code>. Pass an empty matrix for <code>options</code> to use the default value.</p> <p><code>[x, options] = fmin(...)</code> returns, in <code>options(10)</code>, a count of the number of steps taken.</p>						
Arguments	<table><tr><td><code>x1, x2</code></td><td>Interval over which <code>fun</code> is minimized.</td></tr><tr><td><code>P1, P2, ...</code></td><td>Arguments to be passed to <code>fun</code>.</td></tr><tr><td><code>fun</code></td><td>A string containing the name of the function to be minimized.</td></tr></table>	<code>x1, x2</code>	Interval over which <code>fun</code> is minimized.	<code>P1, P2, ...</code>	Arguments to be passed to <code>fun</code> .	<code>fun</code>	A string containing the name of the function to be minimized.
<code>x1, x2</code>	Interval over which <code>fun</code> is minimized.						
<code>P1, P2, ...</code>	Arguments to be passed to <code>fun</code> .						
<code>fun</code>	A string containing the name of the function to be minimized.						

options A vector of control parameters. Only three of the 18 components of options are referenced by fmin; Optimization Toolbox functions use the others. The three control options used by fmin are:

- options(1) — If this is nonzero, intermediate steps in the solution are displayed. The default value of options(1) is 0.
- options(2) — This is the termination tolerance. The default value is 1. e- 4.
- options(14) — This is the maximum number of steps. The default value is 500.

Examples

fmin('cos', 3, 4) computes π to a few decimal places.

fmin('cos', 3, 4, [1, 1. e- 12]) displays the steps taken to compute π to 12 decimal places.

To find the minimum of the function $f(x) = x^3 - 2x - 5$ on the interval (0, 2), write an M-file called f.m.

```
function y = f(x)
y = x.^3- 2*x- 5;
```

Then invoke fmin with

```
x = fmin('f', 0, 2)
```

The result is

```
x =
0.8165
```

The value of the function at the minimum is

```
y = f(x)
```

```
y =
-6.0887
```

Algorithm

The algorithm is based on golden section search and parabolic interpolation. A Fortran program implementing the same algorithms is given in [1].

See Also fmins, fzero, foptions in the Optimization Toolbox (or type help foptions).

References [1] Forsythe, G. E., M. A. Malcolm, and C. B. Moler, *Computer Methods for Mathematical Computations*, Prentice-Hall, 1976.

Purpose	Minimize a function of one variable on a fixed interval								
Syntax	$x = \text{fminbnd}(\text{fun}, x_1, x_2)$ $x = \text{fminbnd}(\text{fun}, x_1, x_2, \text{options})$ $x = \text{fminbnd}(\text{fun}, x_1, x_2, \text{options}, P_1, P_2, \dots)$ $[x, fval] = \text{fminbnd}(\dots)$ $[x, fval, exitflag] = \text{fminbnd}(\dots)$ $[x, fval, exitflag, output] = \text{fminbnd}(\dots)$								
Description	<p><code>fminbnd</code> finds the minimum of a function of one variable within a fixed interval.</p> <p><code>x = fminbnd(fun, x1, x2)</code> returns a value <code>x</code> that is a local minimizer of the function that is described in <code>fun</code> in the interval $x_1 < x < x_2$.</p> <p><code>x = fminbnd(fun, x1, x2, options)</code> minimizes with the optimization parameters specified in the structure <code>options</code>. You can define these parameters using the <code>optimset</code> function. <code>fminbnd</code> uses these <code>options</code> structure fields:</p> <table border="0"> <tr> <td><code>Display</code></td> <td>Level of display. '<code>off</code>' displays no output; '<code>iter</code>' displays output at each iteration; '<code>final</code>' displays just the final output; '<code>notify</code>' (default) displays output only if the function does not converge.</td> </tr> <tr> <td><code>MaxFunEvals</code></td> <td>Maximum number of function evaluations allowed.</td> </tr> <tr> <td><code>MaxIter</code></td> <td>Maximum number of iterations allowed.</td> </tr> <tr> <td><code>TolX</code></td> <td>Termination tolerance on <code>x</code>.</td> </tr> </table> <p><code>x = fminbnd(fun, x1, x2, options, P1, P2, ...)</code> provides for additional arguments, <code>P1</code>, <code>P2</code>, etc., which are passed to the objective function, <code>fun(x, P1, P2, ...)</code>. Use <code>options=[]</code> as a placeholder if no options are set.</p> <p><code>[x, fval] = fminbnd(...)</code> returns the value of the objective function computed in <code>fun</code> at <code>x</code>.</p> <p><code>[x, fval, exitflag] = fminbnd(...)</code> returns a value <code>exitflag</code> that describes the exit condition of <code>fminbnd</code>:</p>	<code>Display</code>	Level of display. ' <code>off</code> ' displays no output; ' <code>iter</code> ' displays output at each iteration; ' <code>final</code> ' displays just the final output; ' <code>notify</code> ' (default) displays output only if the function does not converge.	<code>MaxFunEvals</code>	Maximum number of function evaluations allowed.	<code>MaxIter</code>	Maximum number of iterations allowed.	<code>TolX</code>	Termination tolerance on <code>x</code> .
<code>Display</code>	Level of display. ' <code>off</code> ' displays no output; ' <code>iter</code> ' displays output at each iteration; ' <code>final</code> ' displays just the final output; ' <code>notify</code> ' (default) displays output only if the function does not converge.								
<code>MaxFunEvals</code>	Maximum number of function evaluations allowed.								
<code>MaxIter</code>	Maximum number of iterations allowed.								
<code>TolX</code>	Termination tolerance on <code>x</code> .								

fminbnd

- >0 Indicates that the function converged to a solution x .
- 0 Indicates that the maximum number of function evaluations was exceeded.
- <0 Indicates that the function did not converge to a solution.

`[x, fval, exitflag, output] = fminbnd(...)` returns a structure `output` that contains information about the optimization:

- `output.algorithm` The algorithm used
- `output.funcCount` The number of function evaluations
- `output.iterations` The number of iterations taken

Arguments

`fun` is the function to be minimized. `fun` accepts a scalar x and returns a scalar f , the objective function evaluated at x . The function `fun` can be specified as a function handle.

```
x = fminbnd(@myfun, x0)
```

where `myfun` is a MATLAB function such as

```
function f = myfun(x)
f = ... % Compute function value at x.
```

`fun` can also be an inline object.

```
x = fminbnd(inline('sin(x*x)'), x0);
```

Other arguments are described in the syntax descriptions above.

Examples

`x = fminbnd(@cos, 3, 4)` computes π to a few decimal places and gives a message on termination.

```
[x, fval, exitflag] =
fminbnd(@cos, 3, 4, optimset('TolX', 1e-12, 'Display', 'off'))
```

computes π to about 12 decimal places, suppresses output, returns the function value at x , and returns an `exitflag` of 1.

The argument `fun` can also be an inline function. To find the minimum of the function $f(x) = x^3 - 2x - 5$ on the interval $(0, 2)$, create an inline object `f`

```
f = inline('x.^3-2*x-5');
```

Then invoke fminbnd with

```
x = fminbnd(f, 0, 2)
```

The result is

```
x =
0.8165
```

The value of the function at the minimum is

```
y = f(x)
```

```
y =
-6.0887
```

Algorithm

The algorithm is based on Golden Section search and parabolic interpolation. A Fortran program implementing the same algorithm is given in [1].

Limitations

The function to be minimized must be continuous. fminbnd may only give local solutions.

fminbnd often exhibits slow convergence when the solution is on a boundary of the interval.

fminbnd only handles real variables.

See Also

fminsearch, fzero, optimset, function_handle(@), inline

References

- [1] Forsythe, G. E., M. A. Malcolm, and C. B. Moler, *Computer Methods for Mathematical Computations*, Prentice-Hall, 1976.

fmins

Purpose	Minimize a function of several variables								
<hr/>									
Note	The <code>fmins</code> function was replaced by <code>fminsearch</code> in Release 11 (MATLAB 5.3). In Release 12 (MATLAB 6.0), <code>fmins</code> displays a warning message and calls <code>fminsearch</code> .								
Syntax	<pre>x = fmins('fun', x0) x = fmins('fun', x0, options) x = fmins('fun', x0, options, [], P1, P2, ...) [x, options] = fmins(...)</pre>								
Description	<p><code>x = fmins('fun', x0)</code> returns a vector <code>x</code> which is a local minimizer of <code>fun(x)</code> near x_0.</p> <p><code>x = fmins('fun', x0, options)</code> does the same as the above, but uses <code>options</code> control parameters.</p> <p><code>x = fmins('fun', x0, options, [], P1, P2, ...)</code> does the same as above, but passes arguments to the objective function, <code>fun(x, P1, P2, ...)</code>. Pass an empty matrix for <code>options</code> to use the default value.</p> <p><code>[x, options] = fmins(...)</code> returns, in <code>options(10)</code>, a count of the number of steps taken.</p>								
Arguments	<table><tr><td><code>x0</code></td><td>Starting vector.</td></tr><tr><td><code>P1, P2, ...</code></td><td>Arguments to be passed to <code>fun</code>.</td></tr><tr><td><code>[]</code></td><td>Argument needed to provide compatibility with <code>fminu</code> in the Optimization Toolbox.</td></tr><tr><td><code>fun</code></td><td>A string containing the name of the objective function to be minimized. <code>fun(x)</code> is a scalar valued function of a vector variable.</td></tr></table>	<code>x0</code>	Starting vector.	<code>P1, P2, ...</code>	Arguments to be passed to <code>fun</code> .	<code>[]</code>	Argument needed to provide compatibility with <code>fminu</code> in the Optimization Toolbox.	<code>fun</code>	A string containing the name of the objective function to be minimized. <code>fun(x)</code> is a scalar valued function of a vector variable.
<code>x0</code>	Starting vector.								
<code>P1, P2, ...</code>	Arguments to be passed to <code>fun</code> .								
<code>[]</code>	Argument needed to provide compatibility with <code>fminu</code> in the Optimization Toolbox.								
<code>fun</code>	A string containing the name of the objective function to be minimized. <code>fun(x)</code> is a scalar valued function of a vector variable.								

options A vector of control parameters. Only four of the 18 components of options are referenced by fmns; Optimization Toolbox functions use the others. The four control options used by fmns are:

- options(1) — If this is nonzero, intermediate steps in the solution are displayed. The default value of options(1) is 0.
- options(2) and options(3) — These are the termination tolerances for x and function(x), respectively. The default values are 1.e-4.
- options(14) — This is the maximum number of steps. The default value is 500.

Examples

A classic test example for multidimensional minimization is the Rosenbrock banana function

$$f(x) = 100(x_2 - x_1^2)^2 + (1 - x_1)^2$$

The minimum is at (1, 1) and has the value 0. The traditional starting point is (-1.2, 1). The M-file banana.m defines the function.

```
function f = banana(x)
f = 100*(x(2)-x(1)^2)^2+(1-x(1))^2;
```

The statements

```
[x, out] = fmns('banana', [-1.2, 1]);
x
out(10)
```

produce

```
x =
1. 0000    1. 0000
```

```
ans =
```

This indicates that the minimizer was found to at least four decimal places in 165 steps.

Move the location of the minimum to the point [a, a²] by adding a second parameter to banana. m.

```
function f = banana(x, a)
if nargin < 2, a = 1; end
f = 100*(x(2)-x(1)^2)^2+(a-x(1))^2;
```

Then the statement

```
[x, out] = fmins('banana', [-1, 2, 1], [0, 1.e-8], [], sqrt(2));
```

sets the new parameter to `sqrt(2)` and seeks the minimum to an accuracy higher than the default.

Algorithm

The algorithm is the Nelder-Mead simplex search described in the two references. It is a direct search method that does not require gradients or other derivative information. If n is the length of x, a simplex in n-dimensional space is characterized by the n+1 distinct vectors which are its vertices. In two-space, a simplex is a triangle; in three-space, it is a pyramid.

At each step of the search, a new point in or near the current simplex is generated. The function value at the new point is compared with the function's values at the vertices of the simplex and, usually, one of the vertices is replaced by the new point, giving a new simplex. This step is repeated until the diameter of the simplex is less than the specified tolerance.

See Also

`fmin, foptions` in the Optimization Toolbox (or type `help foptions`).

References

- [1] Nelder, J. A. and R. Mead, "A Simplex Method for Function Minimization," *Computer Journal*, Vol. 7, p. 308-313.
- [2] Dennis, J. E. Jr. and D. J. Woods, "New Computing Environments: Microcomputers in Large-Scale Computing," edited by A. Wouk, *SIAM*, 1987, pp. 116-122.

Purpose	Minimize a function of several variables								
Syntax	<pre>x = fminsearch(fun, x0) x = fminsearch(fun, x0, options) x = fminsearch(fun, x0, options, P1, P2, ...) [x, fval] = fminsearch(...) [x, fval, exitflag] = fminsearch(...) [x, fval, exitflag, output] = fminsearch(...)</pre>								
Description	<p>fminsearch finds the minimum of a scalar function of several variables, starting at an initial estimate. This is generally referred to as <i>unconstrained nonlinear optimization</i>.</p> <p><code>x = fminsearch(fun, x0)</code> starts at the point <code>x0</code> and finds a local minimum <code>x</code> of the function described in <code>fun</code>. <code>x0</code> can be a scalar, vector, or matrix.</p> <p><code>x = fminsearch(fun, x0, options)</code> minimizes with the optimization parameters specified in the structure <code>options</code>. You can define these parameters using the <code>optimset</code> function. <code>fminsearch</code> uses these <code>options</code> structure fields:</p> <table> <tr> <td><code>Display</code></td> <td>Level of display. '<code>off</code>' displays no output; '<code>iter</code>' displays output at each iteration; '<code>final</code>' displays just the final output; '<code>notify</code>' (default) displays output only if the function does not converge.</td> </tr> <tr> <td><code>MaxFunEvals</code></td> <td>Maximum number of function evaluations allowed.</td> </tr> <tr> <td><code>MaxIter</code></td> <td>Maximum number of iterations allowed.</td> </tr> <tr> <td><code>TolX</code></td> <td>Termination tolerance on <code>x</code>.</td> </tr> </table> <p><code>x = fminsearch(fun, x0, options, P1, P2, ...)</code> passes the problem-dependent parameters <code>P1</code>, <code>P2</code>, etc., directly to the function <code>fun</code>. Use <code>options = []</code> as a placeholder if no options are set.</p> <p><code>[x, fval] = fminsearch(...)</code> returns in <code>fval</code> the value of the objective function <code>fun</code> at the solution <code>x</code>.</p>	<code>Display</code>	Level of display. ' <code>off</code> ' displays no output; ' <code>iter</code> ' displays output at each iteration; ' <code>final</code> ' displays just the final output; ' <code>notify</code> ' (default) displays output only if the function does not converge.	<code>MaxFunEvals</code>	Maximum number of function evaluations allowed.	<code>MaxIter</code>	Maximum number of iterations allowed.	<code>TolX</code>	Termination tolerance on <code>x</code> .
<code>Display</code>	Level of display. ' <code>off</code> ' displays no output; ' <code>iter</code> ' displays output at each iteration; ' <code>final</code> ' displays just the final output; ' <code>notify</code> ' (default) displays output only if the function does not converge.								
<code>MaxFunEvals</code>	Maximum number of function evaluations allowed.								
<code>MaxIter</code>	Maximum number of iterations allowed.								
<code>TolX</code>	Termination tolerance on <code>x</code> .								

fminsearch

[x , $fval$, $exitflag$] = fminsearch(. . .) returns a value $exitflag$ that describes the exit condition of fminsearch:

- >0 Indicates that the function converged to a solution x .
- 0 Indicates that the maximum number of function evaluations was exceeded.
- <0 Indicates that the function did not converge to a solution.

[x , $fval$, $exitflag$, $output$] = fminsearch(. . .) returns a structure $output$ that contains information about the optimization:

- $output.algorithm$ The algorithm used
- $output.funcCount$ The number of function evaluations
- $output.iterations$ The number of iterations taken

Arguments

fun is the function to be minimized. It accepts a scalar x and returns a scalar f , the objective function evaluated at x . The function fun can be specified as a function handle.

```
x = fminsearch(@myfun, x0, A, b)
```

where $myfun$ is a MATLAB function such as

```
function f = myfun(x)
f = ... % Compute function value at x
```

fun can also be an inline object.

```
x = fminsearch(inline('sin(x*x)'), x0, A, b);
```

Other arguments are described in the syntax descriptions above.

Examples

A classic test example for multidimensional minimization is the Rosenbrock banana function

$$f(x) = 100(x_2 - x_1^2)^2 + (1 - x_1)^2$$

The minimum is at (1, 1) and has the value 0. The traditional starting point is (-1.2, 1). The M-file `banana.m` defines the function.

```
function f = banana(x)
f = 100*(x(2)-x(1)^2)^2+(1-x(1))^2;
```

The statement

```
[x, fval] = fminsearch(@banana, [-1, 2, 1])
```

produces

```
x =
1. 0000    1. 0000
fval =
8. 1777e-010
```

This indicates that the minimizer was found to at least four decimal places with a value near zero.

Move the location of the minimum to the point $[a, a^2]$ by adding a second parameter to banana. n.

```
function f = banana(x, a)
if nargin < 2, a = 1; end
f = 100*(x(2)-x(1)^2)^2+(a-x(1))^2;
```

Then the statement

```
[x, fval] = fminsearch(@banana, [-1, 2, 1], ...
optimset('TolX', 1e-8), sqrt(2));
```

sets the new parameter to `sqrt(2)` and seeks the minimum to an accuracy higher than the default on x.

Algorithm

`fminsearch` uses the simplex search method of [1]. This is a direct search method that does not use numerical or analytic gradients.

If n is the length of x, a simplex in n-dimensional space is characterized by the $n+1$ distinct vectors that are its vertices. In two-space, a simplex is a triangle; in three-space, it is a pyramid. At each step of the search, a new point in or near the current simplex is generated. The function value at the new point is compared with the function's values at the vertices of the simplex and, usually,

one of the vertices is replaced by the new point, giving a new simplex. This step is repeated until the diameter of the simplex is less than the specified tolerance.

Limitations

`fminsearch` can often handle discontinuity, particularly if it does not occur near the solution. `fminsearch` may only give local solutions.

`fminsearch` only minimizes over the real numbers, that is, x must only consist of real numbers and $f(x)$ must only return real numbers. When x has complex variables, they must be split into real and imaginary parts.

See Also

`fminbnd`, `optimset`, `function_handle (@)`, `inline`

References

[1] Lagarias, J.C., J. A. Reeds, M. H. Wright, and P. E. Wright, “Convergence Properties of the Nelder-Mead Simplex Method in Low Dimensions,” *SIAM Journal of Optimization*, Vol. 9 Number 1, pp. 112-147, 1998.

Purpose	Open a file or obtain information about open files																
Syntax	<pre>fid = fopen(filename) fid = fopen(filename, permission) [fid, message] = fopen(filename, permission, machineformat) fid = fopen('all') [filename, permission, machineformat] = fopen(fid)</pre>																
Description	<p><code>fid = fopen(filename)</code> opens the file <code>filename</code> for read access. (On PCs, <code>fopen</code> opens files for binary read access.)</p> <p><code>fid</code> is a scalar MATLAB integer, called a file identifier. You use the <code>fid</code> as the first argument to other file input/output routines. If <code>fopen</code> cannot open the file, it returns -1. Two file identifiers are automatically available and need not be opened. They are <code>fid=1</code> (standard output) and <code>fid=2</code> (standard error).</p> <p><code>fid = fopen(filename, permission)</code> opens the file <code>filename</code> in the mode specified by <code>permission</code>. <code>permission</code> can be:</p> <table border="1"> <tr> <td>'r'</td> <td>Open file for reading (default).</td> </tr> <tr> <td>'w'</td> <td>Open file, or create new file, for writing; discard existing contents, if any.</td> </tr> <tr> <td>'a'</td> <td>Open file, or create new file, for writing; append data to the end of the file.</td> </tr> <tr> <td>'r+'</td> <td>Open file for reading and writing.</td> </tr> <tr> <td>'w+'</td> <td>Open file, or create a new file, for reading and writing; discard existing contents, if any.</td> </tr> <tr> <td>'a+'</td> <td>Open file, or create new file, for reading and writing; append data to the end of the file.</td> </tr> <tr> <td>'A'</td> <td>Append without automatic flushing; used with tape drives</td> </tr> <tr> <td>'W'</td> <td>Write without automatic flushing; used with tape drives</td> </tr> </table> <p><code>filename</code> can be a MATLABPATH relative partial pathname if the file is opened for reading only. A relative path is always searched for first with respect to the</p>	'r'	Open file for reading (default).	'w'	Open file, or create new file, for writing; discard existing contents, if any.	'a'	Open file, or create new file, for writing; append data to the end of the file.	'r+'	Open file for reading and writing.	'w+'	Open file, or create a new file, for reading and writing; discard existing contents, if any.	'a+'	Open file, or create new file, for reading and writing; append data to the end of the file.	'A'	Append without automatic flushing; used with tape drives	'W'	Write without automatic flushing; used with tape drives
'r'	Open file for reading (default).																
'w'	Open file, or create new file, for writing; discard existing contents, if any.																
'a'	Open file, or create new file, for writing; append data to the end of the file.																
'r+'	Open file for reading and writing.																
'w+'	Open file, or create a new file, for reading and writing; discard existing contents, if any.																
'a+'	Open file, or create new file, for reading and writing; append data to the end of the file.																
'A'	Append without automatic flushing; used with tape drives																
'W'	Write without automatic flushing; used with tape drives																

fopen

current directory. If it is not found and reading only is specified or implied then fopen does an additional search of the MATLABPATH

Files can be opened in binary mode (the default) or in text mode. In binary mode, no characters are singled out for special treatment. In text mode on the PC, , the carriage return character preceding a newline character is deleted on input and added before the newline character on output. To open in text mode, add "t" to the permission string, for example ' rt' and ' wt+'. (On Unix, text and binary mode are the same so this has no effect. But on PC systems this is critical.)

Note If the file is opened in update mode ('+'), an input command like fread, fscanf, fgets, or fgetl cannot be immediately followed by an output command like fwrite or fprintf without an intervening fseek or frewind. The reverse is also true. Namely, an output command like fwrite or fprintf cannot be immediately followed by an input command like fread, fscanf, fgets, or fgetl without an intervening fseek or frewind.

[`fid`, `message`] = fopen(`filename`, `permission`) opens a file as above. If it cannot open the file, `fid` equals -1 and `message` contains a system-dependent error message. If fopen successfully opens a file, the value of `message` is empty.

[`fid`, `message`] = fopen(`filename`, `permission`, `machinformat`) opens the specified file with the specified permission and treats data read using fread or data written using fwrite as having a format given by `machinformat`. `machinformat` is one of the following strings:

'cray' or 'c'	Cray floating point with big-endian byte ordering
'ieee-be' or 'b'	IEEE floating point with big-endian byte ordering
'ieee-le' or 'l'	IEEE floating point with little-endian byte ordering

'ieee-be.164' or 's'	IEEE floating point with big-endian byte ordering and 64-bit long data type
'ieee-le.164' or 'a'	IEEE floating point with little-endian byte ordering and 64-bit long data type
'native' or 'n'	Numeric format of the machine on which MATLAB is running (the default).
'vaxd' or 'd'	VAX D floating point and VAX ordering
'vaxg' or 'g'	VAX G floating point and VAX ordering

`fids = fopen('all')` returns a row vector containing the file identifiers of all open files, not including 1 and 2 (standard output and standard error). The number of elements in the vector is equal to the number of open files.

`[filename, permission, machineformat] = fopen(fid)` returns the filename, permission string, and machineformat string associated with the specified file. An invalid fid returns empty strings for all output arguments.

The 'W' and 'A' permissions are designed for use with tape drives and do not automatically perform a flush of the current output buffer after output operations. For example, open a 1/4" cartridge tape on a SPARCstation for writing with no auto-flush:

```
fid = fopen('/dev/rst0', 'W')
```

Example

The example uses `fopen` to open a file and then passes the fid, returned by `fopen`, to other file I/O functions to read data from the file and then close the file.

```
fid=fopen('fgetl.m');
while 1
    tline = fgetl(fid);
    if ~ischar(tline), break, end
    disp(tline)
end
fclose(fid);
```

See Also

`fclose`, `ferror`, `fprintf`, `fread`, `fscanf`, `fseek`, `ftell`, `fwrite`

fopen (serial)

Purpose	Connect a serial port object to the device
Syntax	<code>fopen(obj)</code>
Arguments	<code>obj</code> A serial port object or an array of serial port objects.
Description	<code>fopen(obj)</code> connects <code>obj</code> to the device.
Remarks	<p>Before you can perform a read or write operation, <code>obj</code> must be connected to the device with the <code>fopen</code> function. When <code>obj</code> is connected to the device:</p> <ul style="list-style-type: none">• Data remaining in the input buffer or the output buffer is flushed.• The <code>Status</code> property is set to <code>open</code>.• The <code>BytesAvailable</code>, <code>BytesReceived</code>, <code>BytesSent</code>, and <code>BytesToOutput</code> properties are set to 0. <p>An error is returned if you attempt to perform a read or write operation while <code>obj</code> is not connected to the device. You can connect only one serial port object to a given device.</p> <p>Some properties are read-only while the serial port object is open (connected), and must be configured before using <code>fopen</code>. Examples include <code>InputBufferSize</code> and <code>OutputBufferSize</code>. Refer to the property reference pages to determine which properties have this constraint.</p> <p>The values for some properties are verified only after <code>obj</code> is connected to the device. If any of these properties are incorrectly configured, then an error is returned when <code>fopen</code> is issued and <code>obj</code> is not connected to the device. Properties of this type include <code>BaudRate</code>, and are associated with device settings.</p> <p>If you use the <code>help</code> command to display help for <code>fopen</code>, then you need to supply the pathname shown below.</p> <pre>help serial /fopen</pre>

Example This example creates the serial port object `s`, connects `s` to the device using `fopen`, writes and reads text data, and then disconnects `s` from the device.

```
s = serial('COM1');
```

```
fopen(s)
fprintf(s, '*IDN?')
idn = fscanf(s);
fclose(s)
```

See Also

Functions

`fclose`

Properties

`BytesAvailable`, `BytesToOutput`, `Status`, `ValuesReceived`, `ValuesSent`

for

Purpose	Repeat statements a specific number of times
Syntax	<pre>for variable = expression statements end</pre>
Description	The general format is <pre>for variable = expression statement ... statement end</pre>
	The columns of the <i>expression</i> are stored one at a time in the variable while the following statements, up to the end, are executed.
	In practice, the <i>expression</i> is almost always of the form scalar : scalar, in which case its columns are simply scalars.
	The scope of the for statement is always terminated with a matching end.
Examples	Assume k has already been assigned a value. Create the Hilbert matrix, using zeros to preallocate the matrix to conserve memory: <pre>a = zeros(k, k) % Preallocate matrix for m = 1:k for n = 1:k a(m, n) = 1/(m+n - 1); end end</pre>
	Step s with increments of -0.1 <pre>for s = 1.0: -0.1: 0.0, . . . , end</pre>
	Successively set e to the unit n-vectors: <pre>for e = eye(n), . . . , end</pre>
	The line <pre>for V = A, . . . , end</pre>

has the same effect as

```
for k = 1:n, V = A(:,k); . . . , end
```

except k is also set here.

See Also

`break`, `end`, `if`, `return`, `switch`, `while`, `colon`

format

Purpose	Control display format for output
Graphical Interface	As an alternative to <code>format</code> , use preferences. Select Preferences from the File menu in the MATLAB desktop and use Command Window preferences.
Syntax	<code>format</code> <code>format type</code> <code>format('type')</code>
Description	MATLAB performs all computations in double precision. Use the <code>format</code> function to control the output format of the numeric values displayed in the Command Window. The <code>format</code> function affects only how numbers are displayed, not how MATLAB computes or saves them. The specified format applies only to the current session. To maintain a format across sessions, use MATLAB preferences. <code>format</code> by itself, changes the output format to the default type, <code>short</code> , which is 5-digit scaled, fixed-point values. <code>format type</code> changes the format to the specified <code>type</code> . The table below describes the allowable values for <code>type</code> . To see the current <code>type</code> file, use <code>get(0, 'Format')</code> , or for <code>compact</code> versus <code>loose</code> , use <code>get(0, 'FormatSpacing')</code> .

Value for type	Result	Example
<code>+</code>	<code>+, -, blank</code>	<code>+</code>
<code>bank</code>	Fixed dollars and cents	<code>3.14</code>
<code>compact</code>	Suppresses excess line feeds to show more output in a single screen. Contrast with <code>loose</code> .	<code>theta = pi /2</code> <code>theta=</code> <code>1.5708</code>
<code>hex</code>	Hexadecimal	<code>400921fb54442d18</code>
<code>long</code>	15-digit scaled fixed point	<code>3.14159265358979</code>
<code>long e</code>	15-digit floating point	<code>3.141592653589793e+00</code>

Value for type	Result	Example
long g	Best of 15-digit fixed or floating point	3. 14159265358979
loose	Adds linefeeds to make output more readable. Contrast with compact.	theta = pi /2 theta= 1. 5708
rat	Ratio of small integers	355/113
short	5-digit scaled fixed point	3. 1416
short e	5-digit floating point	3. 1416e+00
short g	Best of 5-digit fixed or floating point	3. 1416

`format (' type')` is the function form of the syntax.

Examples

Change the format for pi to long by typing.

```
format long
```

View the result by typing

```
pi
```

and MATLAB returns

```
ans =
3. 14159265358979
```

View the current format by typing

```
get(0, 'Format')
```

MATLAB returns

```
ans =
long
```

Set the format to short e by typing

format

```
format short e
```

or use the function form of the syntax

```
format('short','e')
```

Algorithms

If the largest element of a matrix is larger than 10^3 or smaller than 10^{-3} , MATLAB applies a common scale factor for the short and long formats. The function `format +` displays +, -, and blank characters for positive, negative, and zero elements. `format hex` displays the hexadecimal representation of a binary double-precision number. `format rat` uses a continued fraction algorithm to approximate floating-point values by ratios of small integers. See `rat.m` for the complete code.

See Also

`display`, `fprintf`, `num2str`, `rat`, `sprintf`, `spy`

Purpose	Plot a function between specified limits
Syntax	<pre>fplot('function', limits) fplot('function', limits, LineSpec) fplot('function', limits, tol) fplot('function', limits, tol, LineSpec) fplot('function', limits, n) [X, Y] = fplot('function', limits, ...) [...] = plot('function', limits, tol, n, LineSpec, P1, P2, ...)</pre>
Description	<p>fplot plots a function between specified limits. The function must be of the form $y = f(x)$, where x is a vector whose range specifies the limits, and y is a vector the same size as x and contains the function's value at the points in x (see the first example). If the function returns more than one value for a given x, then y is a matrix whose columns contain each component of $f(x)$ (see the second example).</p> <p>fplot('function', limits) plots 'function' between the limits specified by limits. limits is a vector specifying the x-axis limits ([xmin xmax]), or the x- and y-axis limits, ([xmin xmax ymin ymax]).</p> <p>'function' must be the name of an M-file function or a string with variable x that may be passed to eval, such as 'sin(x)', 'diric(x, 10)' or '[sin(x), cos(x)]'.</p> <p>The function $f(x)$ must return a row vector for each element of vector x. For example, if $f(x)$ returns [f1(x), f2(x), f3(x)] then for input [x1; x2] the function should return the matrix</p> <pre>f1(x1) f2(x1) f3(x1) f1(x2) f2(x2) f3(x2)</pre> <p>fplot('function', limits, LineSpec) plots 'function' using the line specification LineSpec.</p> <p>fplot('function', limits, tol) plots 'function' using the relative error tolerance tol (The default is 2e-3, i.e., 0.2 percent accuracy).</p>

fplot

`fplot('function', limits, tol, LineSpec)` plots '*function*' using the relative error tolerance `tol` and a line specification that determines line type, marker symbol, and color.

`fplot('function', limits, n)` with $n \geq 1$ plots the function with a minimum of $n+1$ points. The default `n` is 1. The maximum step size is restricted to be $(1/n) * (x_{\max} - x_{\min})$.

`fplot(fun, limits, ...)` accepts combinations of the optional arguments `tol`, `n`, and `LineSpec`, in any order.

`[X, Y] = fplot('function', limits, ...)` returns the abscissas and ordinates for '*function*' in `X` and `Y`. No plot is drawn on the screen, however you can plot the function using `plot(X, Y)`.

`[...] = plot('function', limits, tol, n, LineSpec, P1, P2, ...)` enables you to pass parameters `P1`, `P2`, etc. directly to the function '*function*' :

```
Y = function(X, P1, P2, ...)
```

To use default values for `tol`, `n`, or `LineSpec`, you can pass in the empty matrix `([])`.


Remarks

`fplot` uses adaptive step control to produce a representative graph, concentrating its evaluation in regions where the function's rate of change is the greatest.

Examples

Plot the hyperbolic tangent function from -2 to 2:

```
fplot('tanh', [-2 2])
```




Create an M-file, `myfun`, that returns a two column matrix:

```
function Y = myfun(x)
Y(:, 1) = 200*sin(x(:))./x(:);
Y(:, 2) = x(:).^2;
```

Plot the function with the statement:

```
fplot('myfun', [-20 20])
```

fplot



Addition Examples

```
subplot(2, 2, 1); fplot('humps', [0 1])
subplot(2, 2, 2); fplot('abs(exp(-j*x*(0:9))*ones(10,1)'), [0 2*pi])
subplot(2, 2, 3); fplot(' [tan(x), sin(x), cos(x)] ', 2*pi *[-1 1 -1 1])
subplot(2, 2, 4); fplot('sin(1./x)', [0.01 0.1], 1e-3)
```

See Also

`eval`, `feval`, `LineSpec`, `plot`

Purpose	Write formatted data to file
Syntax	<code>count = fprintf(fid, format, A, . . .)</code>
Description	<p><code>count = fprintf(fid, format, A, . . .)</code> formats the data in the real part of matrix <code>A</code> (and in any additional matrix arguments) under control of the specified format string, and writes it to the file associated with file identifier <code>fid</code>. <code>fprintf</code> returns a count of the number of bytes written.</p> <p>Argument <code>fid</code> is an integer file identifier obtained from <code>fopen</code>. (It may also be 1 for standard output (the screen) or 2 for standard error. See <code>fopen</code> for more information.) Omitting <code>fid</code> causes output to appear on the screen.</p>


Format String

The format argument is a string containing C language conversion specifications. A conversion specification controls the notation, alignment, significant digits, field width, and other aspects of output format. The format string can contain escape characters to represent non-printing characters such as newline characters and tabs.

Conversion specifications begin with the % character and contain these optional and required elements:

- Flags (optional)
- Width and precision fields (optional)
- A subtype specifier (optional)
- Conversion character (required)

You specify these elements in the following order:



fprintf

Flags

You can control the alignment of the output using any of these optional flags.

Character	Description	Example
A minus sign (-)	Left-justifies the converted argument in its field.	%-5. 2d
A plus sign (+)	Always prints a sign character (+ or -).	%+5. 2d
Zero (0)	Pad with zeros rather than spaces.	%05. 2d

Field Width and Precision Specifications

You can control the width and precision of the output by including these options in the format string.

Character	Description	Example
Field width	A digit string specifying the minimum number of digits to be printed.	%6f
Precision	A digit string including a period (.) specifying the number of digits to be printed to the right of the decimal point.	%6. 2f

Conversion Characters

Conversion characters specify the notation of the output.

Specifier	Description
%c	Single character
%d	Decimal notation (signed)
%e	Exponential notation (using a lowercase e as in 3. 1415e+00)
%E	Exponential notation (using an uppercase E as in 3. 1415E+00)

Specifier	Description
%f	Fixed-point notation
%g	The more compact of %e or %f, as defined in [2]. Insignificant zeros do not print.
%G	Same as %g, but using an uppercase E
%i	Decimal notation (signed)
%o	Octal notation (unsigned)
%s	String of characters
%u	Decimal notation (unsigned)
%x	Hexadecimal notation (using lowercase letters a-f)
%X	Hexadecimal notation (using uppercase letters A-F)

Conversion characters %o, %u, %x, and %X support subtype specifiers. See Remarks for more information.

Escape Characters

This table lists the escape character sequences you use to specify non-printing characters in a format specification.

Character	Description
\b	Backspace
\f	Form feed
\n	New line
\r	Carriage return
\t	Horizontal tab
\\\	Backslash

fprintf

Character	Description
\" or " (two single quotes)	Single quotation mark
%%	Percent character

Remarks

The `fprintf` function behaves like its ANSI C language namesake with these exceptions and extensions.

- If you use `fprintf` to convert a MATLAB double into an integer, and the double contains a value that cannot be represented as an integer (for example, it contains a fraction), MATLAB ignores the specified conversion and outputs the value in exponential format. To successfully perform this conversion, use the `fix`, `floor`, `ceil`, or `round` functions to change the value in the double into a value that can be represented as an integer before passing it to `sprintf`.
- The following, non-standard subtype specifiers are supported for the conversion characters `%o`, `%u`, `%x`, and `%X`.

b	The underlying C data type is a double rather than an unsigned integer. For example, to print a double-precision value in hexadecimal, use a format like ' <code>%bx</code> '.
t	The underlying C data type is a float rather than an unsigned integer.

For example, to print a double value in hexadecimal use the format '`%bx`'

- The `fprintf` function is vectorized for nonscalar arguments. The function recycles the format string through the elements of A (columnwise) until all the elements are used up. The function then continues in a similar manner through any additional matrix arguments.

Note `fprintf` displays negative zero (-0) differently on some platforms, as shown in the following table.

Platform	Conversion Character		
	%e or %E	%f	%g or %G
PC	0.000000e+000	0.000000	0
SGI	0.000000e+00	0.000000	0
HP700	-0.000000e+00	-0.000000	0
Others	-0.000000e+00	-0.000000	-0

Examples

The statements

```
x = 0: .1: 1;
y = [x; exp(x)];
fid = fopen('exp.txt', 'w');
fprintf(fid, '%.2f %.12.8f\n', y);
fclose(fid)
```

create a text file called `exp.txt` containing a short table of the exponential function:

```
0.00    1.00000000
0.10    1.10517092
...
1.00    2.71828183
```

The command

```
fprintf('A unit circle has circumference %g.\n', 2*pi)
```

displays a line on the screen:

```
A unit circle has circumference 6.283186.
```

fprintf

To insert a single quotation mark in a string, use two single quotation marks together. For example,

```
fprintf(1, 'It''s Friday.\n')
```

displays on the screen:

```
It's Friday.
```

The commands

```
B = [8.8 7.7; 8800 7700]
fprintf(1, 'X is %6.2f meters or %8.3f mm\n', 9.9, 9900, B)
```

display the lines:

```
X is 9.90 meters or 9900.000 mm
X is 8.80 meters or 8800.000 mm
X is 7.70 meters or 7700.000 mm
```

Explicitly convert MATLAB double-precision variables to integral values for use with an integral conversion specifier. For instance, to convert signed 32-bit data to hexadecimal format:

```
a = [6 10 14 44];
fprintf('%9X\n', a + (a<0)*2^32)
   6
    A
     E
    2C
```

See Also

`fclose`, `ferror`, `fopen`, `fread`, `fscanf`, `fseek`, `ftell`, `fwrite`, `disp`

References

- [1] Kernighan, B.W. and D.M. Ritchie, *The C Programming Language*, Second Edition, Prentice-Hall, Inc., 1988.
- [2] ANSI specification X3.159-1989: “Programming Language C,” ANSI, 1430 Broadway, New York, NY 10018.

Purpose	Write text to the device	
Syntax	<pre>fprintf(obj, 'cmd') fprintf(obj, 'format', 'cmd') fprintf(obj, 'cmd', 'mode') fprintf(obj, 'format', 'cmd', 'mode')</pre>	
Arguments	obj	A serial port object.
	' cmd'	The string written to the device.
	' format'	C language conversion specification.
	'mode'	Specifies whether data is written synchronously or asynchronously.
Description	<p><code>fprintf(obj, 'cmd')</code> writes the string <code>cmd</code> to the device connected to <code>obj</code>. The default format is <code>%s\n</code>. The write operation is synchronous and blocks the command line until execution is complete.</p> <p><code>fprintf(obj, 'format', 'cmd')</code> writes the string using the format specified by <code>format</code>. <code>format</code> is a C language conversion specification. Conversion specifications involve the % character and the conversion characters d, i, o, u, x, X, f, e, E, g, G, c, and s. Refer to the <code>sprintf</code> file I/O format specifications or a C manual for more information.</p> <p><code>fprintf(obj, 'cmd', 'mode')</code> writes the string with command line access specified by <code>mode</code>. If <code>mode</code> is sync, <code>cmd</code> is written synchronously and the command line is blocked. If <code>mode</code> is async, <code>cmd</code> is written asynchronously and the command line is not blocked. If <code>mode</code> is not specified, the write operation is synchronous.</p> <p><code>fprintf(obj, 'format', 'cmd', 'mode')</code> writes the string using the specified format. If <code>mode</code> is sync, <code>cmd</code> is written synchronously. If <code>mode</code> is async, <code>cmd</code> is written asynchronously.</p>	
Remarks	Before you can write text to the device, it must be connected to <code>obj</code> with the <code>fopen</code> function. A connected serial port object has a <code>Status</code> property value of	

fprintf (serial)

open. An error is returned if you attempt to perform a write operation while obj is not connected to the device.

The `ValuesSent` property value is increased by the number of values written each time `fprintf` is issued.

An error occurs if the output buffer cannot hold all the data to be written. You can specify the size of the output buffer with the `OutputBufferSize` property.

If you use the `help` command to display help for `fprintf`, then you need to supply the pathname shown below.

```
help serial/fprintf
```

Synchronous Versus Asynchronous Write Operations

By default, text is written to the device synchronously and the command line is blocked until the operation completes. You can perform an asynchronous write by configuring the `mode` input argument to be `async`. For asynchronous writes:

- The `BytesToOutput` property value is continuously updated to reflect the number of bytes in the output buffer.
- The M-file callback function specified for the `OutputEmptyFcn` property is executed when the output buffer is empty.

You can determine whether an asynchronous write operation is in progress with the `TransferStatus` property.

Synchronous and asynchronous write operations are discussed in more detail in [Controlling Access to the MATLAB Command Line](#).

Rules for Completing a Write Operation with `fprintf`

A synchronous or asynchronous write operation using `fprintf` completes when:

- The specified data is written.
- The time specified by the `Timeout` property passes.

Additionally, you can stop an asynchronous write operation with the `stopasync` function.

Rules for Writing the Terminator

All occurrences of \n in cmd are replaced with the Terminator property value. Therefore, when using the default format %s\n, all commands written to the device will end with this property value. The terminator required by your device will be described in its documentation.

Example

Create the serial port object s, connect s to a Tektronix TDS 210 oscilloscope, and write the RS232? command with the fprintf function. RS232? instructs the scope to return serial port communications settings.

```
s = serial('COM1');  
fopen(s)  
fprintf(s, 'RS232?')
```

Since the default format for fprintf is %s\n, the terminator specified by the Terminator property was automatically written. However, in some cases you may want to suppress writing the terminator. To do so, you must explicitly specify a format for the data that does not include the terminator, or configure the terminator to empty.

```
fprintf(s, '%s', 'RS232?')
```

See Also

Functions

fopen, fwrite, stopasync

Properties

BytesToOutput, OutputBufferSize, OutputEmptyFcn, Status,
TransferStatus, ValuesSent

frame2im

Purpose	Convert movie frame to indexed image
Syntax	<code>[X, Map] = frame2im(F)</code>
Description	<code>[X, Map] = frame2im(F)</code> converts the single movie frame <code>F</code> into the indexed image <code>X</code> and associated colormap <code>Map</code> . The functions <code>getframe</code> and <code>im2frame</code> create a movie frame. If the frame contains truecolor data, then <code>Map</code> is empty.
See Also	<code>getframe</code> , <code>im2frame</code> , <code>movie</code>

Purpose Create and edit print frames for Simulink and Stateflow block diagrams

Syntax `frameedit`

`frameedit filename`

Description

`frameedit` starts the PrintFrame Editor, a graphical user interface you use to create borders for Simulink and Stateflow block diagrams. With no argument, `frameedit` opens the **PrintFrame Editor** window with a new file.

`frameedit filename` opens the **PrintFrame Editor** window with the specified filename, where `filename` is a figure file (`.fig`) previously created and saved using `frameedit`.


frameedit

Remarks

This illustrates the main features of the PrintFrame Editor.

Use the File menu for page setup, and saving and opening print frames.
Get help for the PrintFrame Editor.

Change the information in a cell, and resize, add, and remove cells.



Closing the PrintFrame Editor

To close the **PrintFrame Editor** window, click the close box in the upper right corner, or select **Close** from the **File** menu.

Printing Simulink Block Diagrams with Print Frames

Select **Print** from the Simulink **File** menu. Check the **Frame** box and supply the filename for the print frame you want to use. Click **OK** in the **Print** dialog box.

Getting Help for the PrintFrame Editor

For further instructions on using the PrintFrame Editor, select **PrintFrame Editor Help** from the **Help** menu in the PrintFrame Editor.

fread

Purpose	Read binary data from file
Syntax	<pre>[A, count] = fread(fid, size, precision) [A, count] = fread(fid, size, precision, skip)</pre>
Description	<p><code>[A, count] = fread(fid, size, precision)</code> reads binary data from the specified file and writes it into matrix A. Optional output argument count returns the number of elements successfully read. fid is an integer file identifier obtained from fopen.</p> <p>size is an optional argument that determines how much data is read. If size is not specified, fread reads to the end of the file and the file pointer is at the end of the file (see feof for details). Valid options are:</p> <ul style="list-style-type: none">n Reads n elements into a column vector.inf Reads to the end of the file, resulting in a column vector containing the same number of elements as are in the file.[m, n] Reads enough elements to fill an m-by-n matrix, filling in elements in column order, padding with zeros if the file is too small to fill the matrix. n can be specified as inf, but m cannot. <p>precision is a string that specifies the format of the data to be read. It commonly contains a datatype specifier such as int or float, followed by an integer giving the size in bits. Any of the strings in the following table, either the MATLAB version or their C or Fortran equivalent, may be used. If precision is not specified, the default is 'uchar' ..</p>
MATLAB	C or Fortran
'schar'	'signed char'
'uchar'	'unsigned char'
'int8'	'integer*1'
'int16'	'integer*2'
'int32'	'integer*4'

MATLAB	C or Fortran	Interpretation
'int64'	'integer*8'	Integer; 64 bits
'uint8'	'integer*1'	Unsigned integer; 8 bits
'uint16'	'integer*2'	Unsigned integer; 16 bits
'uint32'	'integer*4'	Unsigned integer; 32 bits
'uint64'	'integer*8'	Unsigned integer; 64 bits
'float32'	'real*4'	Floating-point; 32 bits
'float64'	'real*8'	Floating-point; 64 bits
'double'	'real*8'	Floating-point; 64 bits

The following platform dependent formats are also supported but they are not guaranteed to be the same size on all platforms.

MATLAB	C or Fortran	Interpretation
'char'	'char*1'	Character; 8 bits
'short'	'short'	Integer; 16 bits
'int'	'int'	Integer; 32 bits
'long'	'long'	Integer; 32 or 64 bits
'ushort'	'unsigned short'	Unsigned integer; 16 bits
'uint'	'unsigned int'	Unsigned integer; 32 bits
'ulong'	'unsigned long'	Unsigned integer; 32 or 64 bits
'float'	'float'	Floating-point; 32 bits

fread

The following formats map to an input stream of bits rather than bytes.

MATLAB	C or Fortran	Interpretation
'bi tN'	-	Signed integer; N bits ($1 \leq N \leq 64$)
'ubi tN'	-	Unsigned integer; N bits ($1 \leq N \leq 64$)

By default, numeric values are returned in class double arrays. To return numeric values stored in classes other than double, create your precision argument by first specifying your source format, and then following it with the characters “=>”, and finally specifying your destination format. You are not required to use the exact name of a MATLAB class type for destination. (See class for details). fread translates the name to the most appropriate MATLAB class type. If the source and destination formats are the same, the following shorthand notation can be used.

*source

which means

source=>source

This table shows some example precision format strings.

'ui nt8=>ui nt8'	Read in unsigned 8-bit integers and save them in an unsigned 8-bit integer array.
'*ui nt8'	Shorthand version of the above.
'bi t4=>i nt8'	Read in signed 4-bit integers packed in bytes and save them in a signed 8-bit array. Each 4-bit integer becomes an 8-bit integer.
'doubl e=>real *4'	Read in doubles, convert and save as a 32-bit floating point array.

[A, count] = fread(fid, size, precision, skip) includes an optional skip argument that specifies the number of bytes to skip after each precision value

is read. If precision specifies a bit format, like 'bitN' or 'ubitN', the skip argument is interpreted as the number of bits to skip.

When skip is used, the precision string may contain a positive integer repetition factor of the form 'N*' which prepends the source format specification, such as '40*uchar'.

Note Do not confuse the asterisk (*) used in the repetition factor with the asterisk used as precision format shorthand. The format string '40*uchar' is equivalent to '40*uchar=>double', not '40*uchar=>uchar'.

When skip is specified, fread reads in, at most, a repetition factor number of values (default is 1), skips the amount of input specified by the skip argument, reads in another block of values, again skips input, and so on, until size number of values have been read. If a skip argument is not specified, the repetition factor is ignored. Use the repetition factor with the skip argument to extract data in noncontiguous fields from fixed length records.

If the input stream is bytes and fread reaches the end of file (see feof) in the middle of reading the number of bytes required for an element, the partial result is ignored. However, if the input stream is bits, then the partial result is returned as the last value. If an error occurs before reaching the end of file, only full elements read up to that point are used.

Examples

For example,

```
type fread.m
```

displays the complete M-file containing this fread help entry. To simulate this command using fread, enter the following:

```
fid = fopen('fread.m', 'r');
F = fread(fid);
s = char(F)
```

In the example, the fread command assumes the default size, inf, and the default precision, 'uchar'. fread reads the entire file, converting the unsigned characters into a column vector of class 'double' (double precision floating point). To display the result as readable text, the 'double' column vector is

fread

transposed to a row vector and converted to class 'char' using the char function.

As another example,

```
s = fread(fid, 120, '40*uchar=>uchar', 8);
```

reads in 120 characters in blocks of 40, each separated by 8 characters. Note that the class type of s is 'uint8' since it is the appropriate class corresponding to the destination format, 'uchar'. Also, since 40 evenly divides 120, the last block read is a full block which means that a final skip will be done before the command is finished. If the last block read is not a full block then fread will not finish with a skip.

See fopen for information about reading Big and Little Endian files.

See Also

`fclose`, `ferror`, `fopen`, `fprintf`, `fread`, `fscanf`, `fseek`, `ftell`, `fwrite`, `feof`

Purpose	Read binary data from the device												
Syntax	<pre>A = fread(obj, size) A = fread(obj, size, 'precision') [A, count] = fread(... [A, count, msg] = fread(...</pre>												
Arguments	<table border="0"> <tr> <td>obj</td><td>A serial port object.</td></tr> <tr> <td>size</td><td>The number of values to read.</td></tr> <tr> <td>'precision'</td><td>The number of bits read for each value, and the interpretation of the bits as character, integer, or floating-point values.</td></tr> <tr> <td>A</td><td>Binary data returned from the device.</td></tr> <tr> <td>count</td><td>The number of values read.</td></tr> <tr> <td>msg</td><td>A message indicating if the read operation was unsuccessful.</td></tr> </table>	obj	A serial port object.	size	The number of values to read.	'precision'	The number of bits read for each value, and the interpretation of the bits as character, integer, or floating-point values.	A	Binary data returned from the device.	count	The number of values read.	msg	A message indicating if the read operation was unsuccessful.
obj	A serial port object.												
size	The number of values to read.												
'precision'	The number of bits read for each value, and the interpretation of the bits as character, integer, or floating-point values.												
A	Binary data returned from the device.												
count	The number of values read.												
msg	A message indicating if the read operation was unsuccessful.												
Description	<p><code>A = fread(obj, size)</code> reads binary data from the device connected to <code>obj</code>, and returns the data to <code>A</code>. The maximum number of values to read is specified by <code>size</code>. Valid options for <code>size</code> are:</p> <ul style="list-style-type: none"> <code>n</code> Read at most <code>n</code> values into a column vector. <code>[m, n]</code> Read at most <code>m</code>-by-<code>n</code> values filling an <code>m</code>-by-<code>n</code> matrix in column order. <p><code>size</code> cannot be <code>inf</code>, and an error is returned if the specified number of values cannot be stored in the input buffer. You specify the size, in bytes, of the input buffer with the <code>InputBufferSize</code> property. A value is defined as a byte multiplied by the <code>precision</code> (see below).</p> <p><code>A = fread(obj, size, 'precision')</code> reads binary data with precision specified by <code>precision</code>.</p> <p><code>precision</code> controls the number of bits read for each value and the interpretation of those bits as integer, floating-point, or character values. If <code>precision</code> is not specified, <code>uchar</code> (an 8-bit unsigned character) is used. By</p>												

fread (serial)

default, numeric values are returned in double-precision arrays. The supported values for *precision* are listed below in Remarks.

[A, count] = fread(...) returns the number of values read to count.

[A, count, msg] = fread(...) returns a warning message to msg if the read operation was unsuccessful.

Remarks

Before you can read data from the device, it must be connected to obj with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt to perform a read operation while obj is not connected to the device.

If msg is not included as an output argument and the read operation was not successful, then a warning message is returned to the command line.

The ValuesReceived property value is increased by the number of values read, each time fread is issued.

If you use the help command to display help for fread, then you need to supply the pathname shown below.

```
help serial/fread
```

Rules for Completing a Binary Read Operation

A read operation with fread blocks access to the MATLAB command line until:

- The specified number of values are read.
- The time specified by the Timeout property passes.

Note The Terminator property is not used for binary read operations.

Supported Precisions

The supported values for *precision* are listed below.

Data Type	Precision	Interpretation
Character	uchar	8-bit unsigned character
	schar	8-bit signed character
	char	8-bit signed or unsigned character
Integer	int8	8-bit integer
	int16	16-bit integer
	int32	32-bit integer
	uint8	8-bit unsigned integer
	uint16	16-bit unsigned integer
	uint32	32-bit unsigned integer
	short	16-bit integer
	int	32-bit integer
	long	32- or 64-bit integer
	ushort	16-bit unsigned integer
	uint	32-bit unsigned integer
	ulong	32- or 64-bit unsigned integer
Floating-point	single	32-bit floating point
	float32	32-bit floating point
	float	32-bit floating point
	double	64-bit floating point
	float64	64-bit floating point

fread (serial)

See Also

Functions

fgetl, fgets, fopen, fscanf

Properties

BytesAvailable, BytesAvailableFcn, InputBufferSize, Status, Terminator, ValueReceived

Purpose	Release MATLAB's hold on a serial port
Syntax	<code>freeserial (' port')</code> <code>freeserial (obj)</code>
Arguments	<code>' port'</code> A serial port name, or a cell array of serial port names <code>obj</code> A serial port object, or an array of serial port objects.
Description	<code>freeserial (' port')</code> releases MATLAB's hold on the serial port specified by <code>port</code> . <code>port</code> can be a cell array of strings. <code>freeserial (obj)</code> releases MATLAB's hold on the serial port associated with the serial port object specified by <code>obj</code> . <code>obj</code> can be an array of serial port objects.
Remarks	An error is returned if a serial port object is connected to the port that is being freed. Use the <code>fclose</code> function to disconnect the serial port object from the serial port. The serial port object uses the <code>javax.comm</code> package to communicate with the serial port. Due to a memory leak in <code>javax.comm</code> , the serial port object is not released from memory until you exit from MATLAB or use <code>freeserial</code> . <code>freeserial</code> is necessary only on Windows platforms. You should use <code>freeserial</code> if you need to connect to the serial port from another application after a serial port object has been connected to that port, and you do not want to exit MATLAB.
See Also	Functions <code>fclose</code>

freqspace


Purpose	Determine frequency spacing for frequency response
Syntax	<pre>[f1, f2] = freqspace(n) [f1, f2] = freqspace([m n]) [x1, y1] = freqspace(..., 'meshgrid') f = freqspace(N) f = freqspace(N, 'whole')</pre>
Description	<p><code>freqspace</code> returns the implied frequency range for equally spaced frequency responses. <code>freqspace</code> is useful when creating desired frequency responses for various one- and two-dimensional applications.</p> <p><code>[f1, f2] = freqspace(n)</code> returns the two-dimensional frequency vectors <code>f1</code> and <code>f2</code> for an <code>n</code>-by-<code>n</code> matrix.</p> <p>For <code>n</code> odd, both <code>f1</code> and <code>f2</code> are <code>[-n+1: 2: n-1]/n</code>.</p> <p>For <code>n</code> even, both <code>f1</code> and <code>f2</code> are <code>[-n: 2: n-2]/n</code>.</p> <p><code>[f1, f2] = freqspace([m n])</code> returns the two-dimensional frequency vectors <code>f1</code> and <code>f2</code> for an <code>m</code>-by-<code>n</code> matrix.</p> <p><code>[x1, y1] = freqspace(..., 'meshgrid')</code> is equivalent to</p> <pre>[f1, f2] = freqspace(...); [x1, y1] = meshgrid(f1, f2);</pre> <p><code>f = freqspace(N)</code> returns the one-dimensional frequency vector <code>f</code> assuming <code>N</code> evenly spaced points around the unit circle. For <code>N</code> even or odd, <code>f</code> is <code>(0: 2/N: 1)</code>. For <code>N</code> even, <code>freqspace</code> therefore returns <code>(N+2)/2</code> points. For <code>N</code> odd, it returns <code>(N+1)/2</code> points.</p> <p><code>f = freqspace(N, 'whole')</code> returns <code>N</code> evenly spaced points around the whole unit circle. In this case, <code>f</code> is <code>0: 2/N: 2*(N-1)/N</code>.</p>
See Also	<code>meshgrid</code>

Purpose	Move the file position indicator to the beginning of an open file
Syntax	<code>frewind(fid)</code>
Description	<code>frewind(fid)</code> sets the file position indicator to the beginning of the file specified by <code>fid</code> , an integer file identifier obtained from <code>fopen</code> .
Remarks	Rewinding a <code>fid</code> associated with a tape device may not work even though <code>frewind</code> does not generate an error message.
See Also	<code>fclose</code> , <code>ferror</code> , <code>fopen</code> , <code>fprintf</code> , <code>fread</code> , <code>fscanf</code> , <code>fseek</code> , <code>ftell</code> , <code>fwrite</code>

fscanf

Purpose	Read formatted data from file
Syntax	$A = \text{fscanf}(\text{fid}, \text{format})$ $[A, \text{count}] = \text{fscanf}(\text{fid}, \text{format}, \text{size})$
Description	$A = \text{fscanf}(\text{fid}, \text{format})$ reads all the data from the file specified by <code>fid</code> , converts it according to the specified <code>format</code> string, and returns it in matrix <code>A</code> . Argument <code>fid</code> is an integer file identifier obtained from <code>fopen</code> . <code>format</code> is a string specifying the format of the data to be read. See “Remarks” for details. $[A, \text{count}] = \text{fscanf}(\text{fid}, \text{format}, \text{size})$ reads the amount of data specified by <code>size</code> , converts it according to the specified <code>format</code> string, and returns it along with a count of elements successfully read. <code>size</code> is an argument that determines how much data is read. Valid options are: <ul style="list-style-type: none"><code>n</code> Read <code>n</code> elements into a column vector.<code>inf</code> Read to the end of the file, resulting in a column vector containing the same number of elements as are in the file.<code>[m, n]</code> Read enough elements to fill an <code>m</code>-by-<code>n</code> matrix, filling the matrix in column order. <code>n</code> can be <code>Inf</code>, but not <code>m</code>.
	<code>fscanf</code> differs from its C language namesakes <code>scanf()</code> and <code>fscanf()</code> in an important respect — it is <i>vectorized</i> in order to return a matrix argument. The <code>format</code> string is cycled through the file until an end-of-file is reached or the amount of data specified by <code>size</code> is read in.
Remarks	When MATLAB reads a specified file, it attempts to match the data in the file to the <code>format</code> string. If a match occurs, the data is written into the matrix in column order. If a partial match occurs, only the matching data is written to the matrix, and the read operation stops. The <code>format</code> string consists of ordinary characters and/or conversion specifications. Conversion specifications indicate the type of data to be

matched and involve the character %, optional width fields, and conversion characters, organized as shown below:



Add one or more of these characters between the % and the conversion character:

- | | |
|-----------------|---|
| An asterisk (*) | Skip over the matched value, if the value is matched but not stored in the output matrix. |
| A digit string | Maximum field width. |
| A letter | The size of the receiving object; for example, h for short as in %hd for a short integer, or l for long as in %ld for a long integer or %lg for a double floating-point number. |

Valid conversion characters are:

%c	Sequence of characters; number specified by field width
%d	Decimal numbers
%e, %f, %g	Floating-point numbers
%i	Signed integer
%o	Signed octal integer
%s	A series of non-white-space characters
%u	Signed decimal integer
%x	Signed hexadecimal integer
[. . .]	Sequence of characters (scanlist)

If %s is used, an element read may use several MATLAB matrix elements, each holding one character. Use %c to read space characters or %s to skip all white space.

fscanf

Mixing character and numeric conversion specifications cause the resulting matrix to be numeric and any characters read to appear as their ASCII values, one character per MATLAB matrix element.

For more information about format strings, refer to the `scanf()` and `fscanf()` routines in a C language reference manual.

Examples

The example in `fprintf` generates an ASCII text file called `exp.txt` that looks like:

```
0.00    1.0000000  
0.10    1.10517092  
...  
1.00    2.71828183
```

Read this ASCII file back into a two-column MATLAB matrix:

```
fid = fopen('exp.txt');  
a = fscanf(fid, '%g %g', [2 inf]) % It has two rows now.  
a = a';  
fclose(fid)
```

See Also

`fgetl`, `fgets`, `fread`, `fprintf`, `fscanf`, `input`, `sscanf`, `textread`

Purpose	Read data from the device, and format as text												
Syntax	<pre>A = fscanf(obj) A = fscanf(obj, 'format') A = fscanf(obj, 'format', size) [A, count] = fscanf(... [A, count, msg] = fscanf(...</pre>												
Arguments	<table border="0"> <tr> <td>obj</td><td>A serial port object.</td></tr> <tr> <td>'format'</td><td>C language conversion specification.</td></tr> <tr> <td>size</td><td>The number of values to read.</td></tr> <tr> <td>A</td><td>Data read from the device and formatted as text.</td></tr> <tr> <td>count</td><td>The number of values read.</td></tr> <tr> <td>msg</td><td>A message indicating if the read operation was unsuccessful.</td></tr> </table>	obj	A serial port object.	'format'	C language conversion specification.	size	The number of values to read.	A	Data read from the device and formatted as text.	count	The number of values read.	msg	A message indicating if the read operation was unsuccessful.
obj	A serial port object.												
'format'	C language conversion specification.												
size	The number of values to read.												
A	Data read from the device and formatted as text.												
count	The number of values read.												
msg	A message indicating if the read operation was unsuccessful.												
Description	<p>A = fscanf(obj) reads data from the device connected to obj, and returns it to A. The data is converted to text using the %c format.</p> <p>A = fscanf(obj, 'format') reads data and converts it according to <i>format</i>. <i>format</i> is a C language conversion specification. Conversion specifications involve the % character and the conversion characters d, i, o, u, x, X, f, e, E, g, G, c, and s. Refer to the sscanf file I/O format specifications or a C manual for more information.</p> <p>A = fscanf(obj, 'format', size) reads the number of values specified by size. Valid options for size are:</p> <ul style="list-style-type: none"> n Read at most n values into a column vector. [m, n] Read at most m-by-n values filling an m-by-n matrix in column order. <p>size cannot be inf, and an error is returned if the specified number of values cannot be stored in the input buffer. If size is not of the form [m, n], and a character conversion is specified, then A is returned as a row vector. You specify</p>												

fscanf (serial)

the size, in bytes, of the input buffer with the InputBufferSize property. An ASCII value is one byte.

[A, count] = fscanf(...) returns the number of values read to count.

[A, count, msg] = fscanf(...) returns a warning message to msg if the read operation did not complete successfully.

Remarks

Before you can read data from the device, it must be connected to obj with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt to perform a read operation while obj is not connected to the device.

If msg is not included as an output argument and the read operation was not successful, then a warning message is returned to the command line.

The ValuesReceived property value is increased by the number of values read – including the terminator – each time fscanf is issued.

If you use the help command to display help for fscanf, then you need to supply the pathname shown below.

```
help serial/fscanf
```

Rules for Completing a Read Operation with fscanf

A read operation with fscanf blocks access to the MATLAB command line until:

- The terminator specified by the Terminator property is read.
- The time specified by the Timeout property passes.
- The number of values specified by size is read.
- The input buffer is filled (unless size is specified)

Example

Create the serial port object s and connect s to a Tektronix TDS 210 oscilloscope, which is displaying sine wave.

```
s = serial('COM1');  
fopen(s)
```

Use the `fprintf` function to configure the scope to measure the peak-to-peak voltage of the sine wave, return the measurement type, and return the peak-to-peak voltage.

```
fprintf(s, 'MEASUREMENT: IMMED:TYPE PK2PK')
fprintf(s, 'MEASUREMENT: IMMED:TYPE?')
fprintf(s, 'MEASUREMENT: IMMED:VALUE?')
```

Since the default value for the `ReadAsyncMode` property is `continuous`, data associated with the two query commands is automatically returned to the input buffer.

```
s.BytesAvailable
ans =
21
```

Use `fscanf` to read the measurement type. The operation will complete when the first terminator is read.

```
meas = fscanf(s)
meas =
PK2PK
```

Use `fscanf` to read the peak-to-peak voltage as a floating-point number, and exclude the terminator.

```
pk2pk = fscanf(s, '%e', 14)
pk2pk =
2.0200
```

Disconnect `s` from the scope, and remove `s` from memory and the workspace.

```
fclose(s)
delete(s)
clear s
```

See Also

Functions

`fgetl`, `fgets`, `fopen`, `fread`, `strread`

Properties

`BytesAvailable`, `BytesAvailableFcn`, `InputBufferSize`, `Status`, `Terminator`, `Timeout`

fseek

Purpose	Set file position indicator								
Syntax	<code>status = fseek(fd, offset, origin)</code>								
Description	<code>status = fseek(fd, offset, origin)</code> repositions the file position indicator in the file with the given <code>fd</code> to the byte with the specified <code>offset</code> relative to <code>origin</code> .								
Arguments	<table><tr><td><code>fd</code></td><td>An integer file identifier obtained from <code>fopen</code>.</td></tr><tr><td><code>offset</code></td><td>A value that is interpreted as follows:<ul style="list-style-type: none"><code>offset > 0</code> Move position indicator <code>offset</code> bytes toward the end of the file.<code>offset = 0</code> Do not change position.<code>offset < 0</code> Move position indicator <code>offset</code> bytes toward the beginning of the file.</td></tr><tr><td><code>origin</code></td><td>A string whose legal values are:<ul style="list-style-type: none">'b0f' -1: Beginning of file.'c0f' 0: Current position in file.'e0f' 1: End of file.</td></tr><tr><td><code>status</code></td><td>A returned value that is 0 if the <code>fseek</code> operation is successful and -1 if it fails. If an error occurs, use the function <code>ferror</code> to get more information.</td></tr></table>	<code>fd</code>	An integer file identifier obtained from <code>fopen</code> .	<code>offset</code>	A value that is interpreted as follows: <ul style="list-style-type: none"><code>offset > 0</code> Move position indicator <code>offset</code> bytes toward the end of the file.<code>offset = 0</code> Do not change position.<code>offset < 0</code> Move position indicator <code>offset</code> bytes toward the beginning of the file.	<code>origin</code>	A string whose legal values are: <ul style="list-style-type: none">'b0f' -1: Beginning of file.'c0f' 0: Current position in file.'e0f' 1: End of file.	<code>status</code>	A returned value that is 0 if the <code>fseek</code> operation is successful and -1 if it fails. If an error occurs, use the function <code>ferror</code> to get more information.
<code>fd</code>	An integer file identifier obtained from <code>fopen</code> .								
<code>offset</code>	A value that is interpreted as follows: <ul style="list-style-type: none"><code>offset > 0</code> Move position indicator <code>offset</code> bytes toward the end of the file.<code>offset = 0</code> Do not change position.<code>offset < 0</code> Move position indicator <code>offset</code> bytes toward the beginning of the file.								
<code>origin</code>	A string whose legal values are: <ul style="list-style-type: none">'b0f' -1: Beginning of file.'c0f' 0: Current position in file.'e0f' 1: End of file.								
<code>status</code>	A returned value that is 0 if the <code>fseek</code> operation is successful and -1 if it fails. If an error occurs, use the function <code>ferror</code> to get more information.								
See Also	<code>fopen</code> , <code>ftell</code>								

Purpose	Get file position indicator
Syntax	<code>position = ftell(fd)</code>
Description	<code>position = ftell(fd)</code> returns the location of the file position indicator for the file specified by <code>fd</code> , an integer file identifier obtained from <code>fopen</code> . The <code>position</code> is a nonnegative integer specified in bytes from the beginning of the file. A returned value of <code>-1</code> for <code>position</code> indicates that the query was unsuccessful; use <code>ferror</code> to determine the nature of the error.
See Also	<code>fclose</code> , <code>ferror</code> , <code>fopen</code> , <code>fprintf</code> , <code>fread</code> , <code>fscanf</code> , <code>fseek</code> , <code>fwrite</code>

full

Purpose	Convert sparse matrix to full matrix												
Syntax	<code>A = full(S)</code>												
Description	<code>A = full(S)</code> converts a sparse matrix <code>S</code> to full storage organization. If <code>S</code> is a full matrix, it is left unchanged. If <code>A</code> is full, <code>issparse(A)</code> is 0.												
Remarks	Let <code>X</code> be an m -by- n matrix with $nz = nnz(X)$ nonzero entries. Then <code>full(X)</code> requires space to store $m \cdot n$ real numbers while <code>sparse(X)</code> requires space to store nz real numbers and $(nz+n)$ integers. On most computers, a real number requires twice as much storage as an integer. On such computers, <code>sparse(X)</code> requires less storage than <code>full(X)</code> if the density, $nz / \text{prod}(\text{size}(X))$, is less than one third. Operations on sparse matrices, however, require more execution time per element than those on full matrices, so density should be considerably less than two-thirds before sparse storage is used.												
Examples	Here is an example of a sparse matrix with a density of about two-thirds. <code>sparse(S)</code> and <code>full(S)</code> require about the same number of bytes of storage. <pre>S = sparse(rand(200, 200) < 2/3); A = full(S); whos</pre> <table><thead><tr><th>Name</th><th>Size</th><th>Bytes</th><th>Class</th></tr></thead><tbody><tr><td>A</td><td>200X200</td><td>320000</td><td>double array (logical)</td></tr><tr><td>S</td><td>200X200</td><td>318432</td><td>sparse array (logical)</td></tr></tbody></table>	Name	Size	Bytes	Class	A	200X200	320000	double array (logical)	S	200X200	318432	sparse array (logical)
Name	Size	Bytes	Class										
A	200X200	320000	double array (logical)										
S	200X200	318432	sparse array (logical)										
See Also	<code>sparse</code>												

Purpose	Build a full filename from parts
Syntax	<pre>fullfile('dir1','dir2',...,'filename') f = fullfile('dir1','dir2',...,'filename')</pre>
Description	<p><code>fullfile(dir1, dir2, ..., filename)</code> builds a full filename from the directories and filename specified. This is conceptually equivalent to</p> <pre>f = [dir1 dirsep dir2 dirsep ... dirsep filename]</pre> <p>except that care is taken to handle the cases when the directories begin or end with a directory separator.</p>
Examples	To create the full filename from a disk name, directories, and filename,
	<pre>f = fullfile('C:','Applications','matlab','myfun.m') f = C:\Applications\matlab\myfun.m</pre>
	The following examples both produce the same result on UNIX, but only the second one works on all platforms.
	<pre>fullfile(matlabroot,'toolbox/matlab/general/Contents.m') and fullfile(matlabroot,'toolbox','matlab','general','Contents.m')</pre>
See Also	fileparts

func2str

Purpose	Constructs a function name string from a function handle
Syntax	<code>s = func2str(fhandl e)</code>
Description	<code>func2str(fhandl e)</code> constructs a string, <i>s</i> , that holds the name of the function to which the function handle, <i>fhandl e</i> , belongs. When you need to perform a string operation, such as compare or display, on a function handle, you can use <code>func2str</code> to construct a string bearing the function name.
Examples	To create a function name string from the function handle, <code>@humps</code> <code>funname = func2str(@humps)</code> <code>funname =</code> <code>humps</code>
See Also	<code>function_handl e</code> , <code>str2func</code> , <code>functions</code>

Purpose	Function M-files
Description	<p>You add new functions to MATLAB's vocabulary by expressing them in terms of existing commands and functions that compose the new function reside in a text file called an <i>M-file</i>.</p> <p>M-files can be either <i>scripts</i> or <i>functions</i>. Scripts are simply files containing a sequence of MATLAB statements. Functions make use of their own local variables and accept input arguments.</p> <p>The name of an M-file begins with an alphabetic character, and has a filename extension of <code>.m</code>. The M-file name, less its extension, is what MATLAB searches for when you try to use the script or function.</p> <p>A line at the top of a function M-file contains the syntax definition. The name of a function, as defined in the first line of the M-file, should be the same as the name of the file without the <code>.m</code> extension. For example, the existence of a file on disk called <code>stat.m</code> with</p> <pre>function [mean, stdev] = stat(x) n = length(x); mean = sum(x)/n; stdev = sqrt(sum((x-mean).^2/n));</pre> <p>defines a new function called <code>stat</code> that calculates the mean and standard deviation of a vector. The variables within the body of the function are all local variables.</p> <p>A <i>subfunction</i>, visible only to the other functions in the same file, is created by defining a new function with the <code>function</code> keyword after the body of the preceding function or subfunction. For example, <code>avg</code> is a subfunction within the file <code>stat.m</code>:</p> <pre>function [mean, stdev] = stat(x) n = length(x); mean = avg(x, n); stdev = sqrt(sum((x-avg(x, n)).^2)/n); function mean = avg(x, n) mean = sum(x)/n;</pre>

Subfunctions are not visible outside the file where they are defined. Functions normally return when the end of the function is reached. Use a return statement to force an early return.

When MATLAB does not recognize a function by name, it searches for a file of the same name on disk. If the function is found, MATLAB compiles it into memory for subsequent use. In general, if you input the name of something to MATLAB, the MATLAB interpreter:

- 1 Checks to see if the name is a variable.
- 2 Checks to see if the name is an internal function (`eig`, `sin`) that was not overloaded.
- 3 Checks to see if the name is a local function (local in sense of multifunction file).
- 4 Checks to see if the name is a function in a private directory.
- 5 Locates any and all occurrences of function in method directories and on the path. Order is of no importance.

At execution, MATLAB:

- 6 Checks to see if the name is wired to a specific function (2, 3, & 4 above)
- 7 Uses precedence rules to determine which instance from 5 above to call (we may default to an internal MATLAB function). Constructors have higher precedence than anything else.

When you call an M-file function from the command line or from within another M-file, MATLAB parses the function and stores it in memory. The parsed function remains in memory until cleared with the `clear` command or you quit MATLAB. The `pcode` command performs the parsing step and stores the result on the disk as a P-file to be loaded later.

See Also

`nargin`, `nargout`, `pcode`, `varargin`, `varargout`, `what`

Purpose	MATLAB data type that is a handle to a function
Syntax	<code>handle = @function</code>
Description	<code>@function</code> returns a handle to the specified MATLAB function. A function handle is a MATLAB data type that contains information used in referencing a function. When you create a function handle, MATLAB stores in the handle all the information about the function that it needs to execute, or <i>evaluate</i> , it later on. Typically, a function handle is passed in an argument list to other functions. It is then used in conjunction with <code>feval</code> to evaluate the function to which the handle belongs.
	A MATLAB function handle is more than just a reference to a single function. It often represents a collection of function methods, overloaded to handle different argument types. When you create a handle to a function, MATLAB takes a snapshot of all built-in and M-file methods of that name that are on the MATLAB path and in scope at that time, and stores access information for all of those methods in the handle.
	When you evaluate a function handle, it is the combination of which function methods are mapped to by the handle and what arguments the handle is evaluated with that determines the actual function that MATLAB dispatches to.
	As a standard MATLAB data type, a function handle can be manipulated and operated on in the same manner as other MATLAB data types.
	Function handles enable you to do all of the following:
	<ul style="list-style-type: none">• Pass function access information to other functions• Capture all methods of an overloaded function• Allow wider access to subfunctions and private functions• Ensure reliability when evaluating functions• Reduce the number of files that define your functions• Improve performance in repeated operations• Manipulate handles in arrays, structures, and cell arrays
Examples	The following example creates a function handle for the <code>humps</code> function and assigns it to the variable, <code>fhandle</code> .

function_handle (@)

```
fhandl e = @humps;
```

Pass the handle to another function in the same way you would pass any argument. This example passes the function handle just created to fminbnd, which then minimizes over the interval [0.3, 1].

```
x = fminbnd (@humps, 0.3, 1)
x =
    0.6370
```

See Also

[str2func](#), [func2str](#), [functions](#)

Purpose	Return information about a function handle
Syntax	<code>f = functions(funhandle)</code>
Description	<code>f = functions(funhandle)</code> returns, in a MATLAB structure, the function name, type, and filename for the function handle stored in the variable, <code>funhandle</code> . For overloaded functions, it also returns a substructure identifying the classes and M-files that overload the function.

Note The `functions` function is provided for querying and debugging purposes. Its behavior may change in subsequent releases, so it should not be relied upon for programming purposes.

Examples

To obtain information on a function handle for the `display` function,

```
f = functions(@deblank)
f =
  function: 'deblank'
  type: 'overloaded'
  file: 'matlabroot\toolbox\matlab\strfun\deblank.m'
  methods: [1x1 struct]
```

The `methods` field is a substructure containing one fieldname for each class that overloads the function. The value of each field is the path and name of the file that defines the method.

```
f = functions(@display);
f.methods

ans =
  polynom: '\home\user4\@polynom\display.m'
  inline: 'matlabroot\toolbox\matlab\funfun\@inline\display.m'
  serial: 'matlabroot\toolbox\matlab\iofun\@serial\display.m'
  avifile: 'matlabroot\toolbox\matlab\iofun\@avifile\display.m'
```

See Also

`function_handle`

funm

Purpose	Evaluate general matrix function
Syntax	<pre>F = funm(A, fun) [F, esterr] = funm(A, fun)</pre>
Description	<p><code>F = funm(A, fun)</code> for a square matrix argument <code>A</code>, evaluates the matrix version of the function <code>fun</code>. For matrix exponentials, logarithms and square roots, use <code>expm(A)</code>, <code>logm(A)</code> and <code>sqrtm(A)</code> instead.</p> <p><code>[F, esterr] = funm(A, fun)</code> does not print any message, but returns a very rough estimate of the relative error in the computed result.</p> <p>If <code>A</code> is symmetric or Hermitian, then its Schur form is diagonal and <code>funm</code> is able to produce an accurate result.</p> <p><code>L = logm(A)</code> uses <code>funm</code> to do its computations, but it can get more reliable error estimates by comparing <code>expm(L)</code> with <code>A</code>. <code>S = sqrtm(A)</code> and <code>E = expm(A)</code> use completely different algorithms.</p>
Examples	<p>Example 1. <code>fun</code> can be specified using <code>@</code>:</p> <pre>F = funm(magic(3), @sin)</pre> <p>is the matrix sine of the 3-by-3 magic matrix.</p> <p>Example 2. The statements</p> <pre>S = funm(X, @sin); C = funm(X, @cos);</pre> <p>produce the same results to within roundoff error as</p> <pre>E = expm(i*X); C = real(E); S = imag(E);</pre> <p>In either case, the results satisfy <code>S*S+C*C = I</code>, where <code>I = eye(size(X))</code>.</p>
Algorithm	<p><code>funm</code> uses a potentially unstable algorithm. If <code>A</code> is close to a matrix with multiple eigenvalues and poorly conditioned eigenvectors, <code>funm</code> may produce inaccurate results. An attempt is made to detect this situation and print a</p>

warning message. The error detector is sometimes too sensitive and a message is printed even though the the computed result is accurate.

The matrix functions are evaluated using Parlett's algorithm, which is described in [1].

See Also

`expm`, `logm`, `sqrtm`, `function_handle (@)`

References

[1] Golub, G. H. and C. F. Van Loan, *Matrix Computation*, Johns Hopkins University Press, 1983, p. 384.

[2] Moler, C. B. and C. F. Van Loan, "Nineteen Dubious Ways to Compute the Exponential of a Matrix," *SIAM Review 20*, 1979, pp. 801-836.

fwrite

Purpose	Write binary data to a file
Syntax	<pre>count = fwrite(fid, A, precision) count = fwrite(fid, A, precision, skip)</pre>
Description	<p><code>count = fwrite(fid, A, precision)</code> writes the elements of matrix <code>A</code> to the specified file, translating MATLAB values to the specified precision. The data is written to the file in column order, and a count is kept of the number of elements written successfully.</p> <p><code>fid</code> is an integer file identifier obtained from <code>fopen</code>, or 1 for standard output or 2 for standard error.</p> <p><code>precision</code> controls the form and size of the result. See <code>fread</code> for a list of allowed precisions. For '<code>bitN</code>' or '<code>ubitN</code>' precisions, <code>fwrite</code> sets all bits in <code>A</code> when the value is out-of-range.</p> <p><code>count = fwrite(fid, A, precision, skip)</code> includes an optional <code>skip</code> argument that specifies the number of bytes to skip before each <code>precision</code> value is written. With the <code>skip</code> argument present, <code>fwrite</code> skips and writes one value, skips and writes another value, etc. until all of <code>A</code> is written. If <code>precision</code> is a bit format like '<code>bitN</code>' or '<code>ubitN</code>', <code>skip</code> is specified in bits. This is useful for inserting data into noncontiguous fields in fixed-length records.</p>
Examples	<p>For example,</p> <pre>fid = fopen('magic5.bin', 'wb'); fwrite(fid, magic(5), 'integer*4')</pre> <p>creates a 100-byte binary file, containing the 25 elements of the 5-by-5 magic square, stored as 4-byte integers.</p>
See Also	<code>fclose</code> , <code>ferror</code> , <code>fopen</code> , <code>fprintf</code> , <code>fread</code> , <code>fscanf</code> , <code>fseek</code> , <code>fтел</code>

Purpose	Write binary data to the device	
Syntax	<pre>fwrite(obj, A) fwrite(obj, A, 'precision') fwrite(obj, A, 'mode') fwrite(obj, A, 'precision', 'mode')</pre>	
Arguments	obj	A serial port object.
	A	The binary data written to the device.
	'precision'	The number of bits written for each value, and the interpretation of the bits as character, integer, or floating-point values.
	'mode'	Specifies whether data is written synchronously or asynchronously.
Description	<p><code>fwrite(obj, A)</code> writes the binary data <code>A</code> to the device connected to <code>obj</code>.</p> <p><code>fwrite(obj, A, 'precision')</code> writes binary data with precision specified by <code>precision</code>. <code>precision</code> controls the number of bits written for each value and the interpretation of those bits as integer, floating-point, or character values. If <code>precision</code> is not specified, <code>uchar</code> (an 8-bit unsigned character) is used. The supported values for <code>precision</code> are listed below in Remarks.</p> <p><code>fwrite(obj, A, 'mode')</code> writes binary data with command line access specified by <code>mode</code>. If <code>mode</code> is <code>sync</code>, <code>A</code> is written synchronously and the command line is blocked. If <code>mode</code> is <code>async</code>, <code>A</code> is written asynchronously and the command line is not blocked. If <code>mode</code> is not specified, the write operation is synchronous.</p> <p><code>fwrite(obj, A, 'precision', 'mode')</code> writes binary data with precision specified by <code>precision</code> and command line access specified by <code>mode</code>.</p>	
Remarks	Before you can write data to the device, it must be connected to <code>obj</code> with the <code>open</code> function. A connected serial port object has a <code>Status</code> property value of <code>open</code> . An error is returned if you attempt to perform a write operation while <code>obj</code> is not connected to the device.	

fwrite (serial)

The `ValuesSent` property value is increased by the number of values written each time `fwrite` is issued.

An error occurs if the output buffer cannot hold all the data to be written. You can specify the size of the output buffer with the `OutputBufferSize` property.

If you use the `help` command to display help for `fwrite`, then you need to supply the pathname shown below.

```
help serial /fwrite
```

Synchronous Versus Asynchronous Write Operations

By default, data is written to the device synchronously and the command line is blocked until the operation completes. You can perform an asynchronous write by configuring the `mode` input argument to be `async`. For asynchronous writes:

- The `BytesToOutput` property value is continuously updated to reflect the number of bytes in the output buffer.
- The M-file callback function specified for the `OutputEmptyFcn` property is executed when the output buffer is empty.

You can determine whether an asynchronous write operation is in progress with the `TransferStatus` property.

Synchronous and asynchronous write operations are discussed in more detail in [Writing Data](#).

Rules for Completing a Write Operation with `fwrite`

A binary write operation using `fwrite` completes when:

- The specified data is written.
- The time specified by the `Timeout` property passes.

Note The `Terminator` property is not used with binary write operations.

Supported Precisions

The supported values for *precision* are listed below.

Data Type	Precision	Interpretation
Character	uchar	8-bit unsigned character
	schar	8-bit signed character
	char	8-bit signed or unsigned character
Integer	int8	8-bit integer
	int16	16-bit integer
	int32	32-bit integer
	uint8	8-bit unsigned integer
	uint16	16-bit unsigned integer
	uint32	32-bit unsigned integer
	short	16-bit integer
	int	32-bit integer
	long	32- or 64-bit integer
	ushort	16-bit unsigned integer
	uint	32-bit unsigned integer
	ulong	32- or 64-bit unsigned integer
Floating-point	single	32-bit floating point
	float32	32-bit floating point
	float	32-bit floating point
	double	64-bit floating point
	float64	64-bit floating point

fwrite (serial)

See Also

Functions

`fopen`, `fprintf`

Properties

`BytesToOutput`, `OutputBufferSize`, `OutputEmptyFcn`, `Status`, `Timeout`,
`TransferStatus`, `ValuesSent`

Purpose	Find zero of a function of one variable				
Syntax	$x = \text{fzero}(\text{fun}, x_0)$ $x = \text{fzero}(\text{fun}, x_0, \text{options})$ $x = \text{fzero}(\text{fun}, x_0, \text{options}, P1, P2, \dots)$ $[x, fval] = \text{fzero}(\dots)$ $[x, fval, exitflag] = \text{fzero}(\dots)$ $[x, fval, exitflag, output] = \text{fzero}(\dots)$				
Description	<p>$x = \text{fzero}(\text{fun}, x_0)$ tries to find a zero of fun near x_0, if x_0 is a scalar. The value x returned by fzero is near a point where fun changes sign, or NaN if the search fails. In this case, the search terminates when the search interval is expanded until an Inf, NaN, or complex value is found.</p> <p>If x_0 is a vector of length two, fzero assumes x_0 is an interval where the sign of $\text{fun}(x_0(1))$ differs from the sign of $\text{fun}(x_0(2))$. An error occurs if this is not true. Calling fzero with such an interval guarantees fzero will return a value near a point where fun changes sign.</p> <p>$x = \text{fzero}(\text{fun}, x_0, \text{options})$ minimizes with the optimization parameters specified in the structure options. You can define these parameters using the optimset function. fzero uses these options structure fields:</p> <table> <tr> <td>Display</td> <td>Level of display. 'off' displays no output; 'iter' displays output at each iteration; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.</td> </tr> <tr> <td>TolX</td> <td>Termination tolerance on x.</td> </tr> </table> <p>$x = \text{fzero}(\text{fun}, x_0, \text{options}, P1, P2, \dots)$ provides for additional arguments passed to the function, fun. Use $\text{options} = []$ as a placeholder if no options are set.</p> <p>$[x, fval] = \text{fzero}(\dots)$ returns the value of the objective function fun at the solution x.</p>	Display	Level of display. 'off' displays no output; 'iter' displays output at each iteration; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.	TolX	Termination tolerance on x .
Display	Level of display. 'off' displays no output; 'iter' displays output at each iteration; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.				
TolX	Termination tolerance on x .				

fzero

[x , $fval$, $exitflag$] = $fzero(\dots)$ returns a value $exitflag$ that describes the exit condition of $fzero$:

- >0 Indicates that the function found a zero x .
- <0 No interval was found with a sign change, or a NaN or Inf function value was encountered during search for an interval containing a sign change, or a complex function value was encountered during the search for an interval containing a sign change.

[x , $fval$, $exitflag$, $output$] = $fzero(\dots)$ returns a structure $output$ that contains information about the optimization:

- $output.algorithm$ The algorithm used
- $output.funcCount$ The number of function evaluations
- $output.iterations$ The number of iterations taken

Note For the purposes of this command, zeros are considered to be points where the function actually crosses, not just touches, the x -axis.

Arguments

fun is the function whose zero is to be computed. It accepts a vector x and returns a scalar f , the objective function evaluated at x . The function fun can be specified as a function handle.

```
x = fzero(@myfun, x0)
```

where $myfun$ is a MATLAB function such as

```
function f = myfun(x)
f = ... % Compute function value at x
```

fun can also be an inline object.

```
x = fzero(inline('sin(x*x)'), x0);
```

Other arguments are described in the syntax descriptions above.

Examples

Example 1. Calculate π by finding the zero of the sine function near 3.

```
x = fzero(@sin, 3)
x =
3. 1416
```

Example 2. To find the zero of cosine between 1 and 2

```
x = fzero(@cos, [1 2])
x =
1.5708
```

Note that $\cos(1)$ and $\cos(2)$ differ in sign.

Example 3. To find a zero of the function $f(x) = x^3 - 2x - 5$

write an M-file called f.m.

```
function y = f(x)
y = x.^3- 2*x- 5;
```

To find the zero near 2

```
z = fzero(@f, 2)
z =
2. 0946
```

Because this function is a polynomial, the statement `roots([1 0 -2 -5])` finds the same real zero, and a complex conjugate pair of zeros.

```
2. 0946
- 1. 0473 + 1. 1359i
- 1. 0473 - 1. 1359i
```

Algorithm

The `fzero` command is an M-file. The algorithm, which was originated by T. Dekker, uses a combination of bisection, secant, and inverse quadratic interpolation methods. An Algol 60 version, with some improvements, is given in [1]. A Fortran version, upon which the `fzero` M-file is based, is in [2].

Limitations

The `fzero` command finds a point where the function changes sign. If the function is *continuous*, this is also a point where the function has a value near zero. If the function is not continuous, `fzero` may return values that are discontinuous points instead of zeros. For example, `fzero(@tan, 1)` returns 1. 5708, a discontinuous point in `tan`.

Furthermore, the `fzero` command defines a *zero* as a point where the function crosses the x -axis. Points where the function touches, but does not cross, the x -axis are not valid zeros. For example, $y = x.^2$ is a parabola that touches the x -axis at 0. Because the function never crosses the x -axis, however, no zero is found. For functions with no valid zeros, `fzero` executes until `Inf`, `NaN`, or a complex value is detected.

See Also

`roots`, `fminbnd`, `function_handle(@)`, `inline`, `optimset`

References

- [1] Brent, R., *Algorithms for Minimization Without Derivatives*, Prentice-Hall, 1973.
- [2] Forsythe, G. E., M. A. Malcolm, and C. B. Moler, *Computer Methods for Mathematical Computations*, Prentice-Hall, 1976.

Purpose	Test matrices
Syntax	$[A, B, C, \dots] = \text{gallery}(' \text{tmfun}', P1, P2, \dots)$ <code>gallery(3)</code> a badly conditioned 3-by-3 matrix <code>gallery(5)</code> an interesting eigenvalue problem
Description	$[A, B, C, \dots] = \text{gallery}(' \text{tmfun}', P1, P2, \dots)$ returns the test matrices specified by string <code>tmfun</code> . <code>tmfun</code> is the name of a matrix family selected from the table below. <code>P1, P2, ...</code> are input parameters required by the individual matrix family. The number of optional parameters <code>P1, P2, ...</code> used in the calling syntax varies from matrix to matrix. The exact calling syntaxes are detailed in the individual matrix descriptions below. The gallery holds over fifty different test matrix functions useful for testing algorithms and other purposes.

Test Matrices			
cauchy	chebspec	chebvand	chow
ci rcul	cl ement	compar	condex
cycol	dorr	dramadah	fi edl er
forsythe	frank	gearmat	grcar
hanowa	house	i nvhess	i nvol
i pj fact	j ordbl oc	kahan	kms
krylov	l auchl i	lehmer	l esp
l otki n	mi ni j	mol er	neumann
orthog	parter	pei	poi sson
prolate	randcol u	randcorr	rando
randhess	randsvd	redheff	riemann
ris	rosser	smoke	toeppd

Test Matrices (Continued)

tri diag	triw	vander	wathen
wilk			

cauchy—Cauchy matrix

`C = gallery('cauchy', x, y)` returns an n-by-n matrix, $C(i, j) = 1/(x(i)+y(j))$. Arguments `x` and `y` are vectors of length `n`. If you pass in scalars for `x` and `y`, they are interpreted as vectors `1:x` and `1:y`.

`C = gallery('cauchy', x)` returns the same as above with `y = x`. That is, the command returns $C(i, j) = 1/(x(i)+x(j))$.

Explicit formulas are known for the inverse and determinant of a Cauchy matrix. The determinant $\det(C)$ is nonzero if `x` and `y` both have distinct elements. `C` is totally positive if $0 < x(1) < \dots < x(n)$ and $0 < y(1) < \dots < y(n)$.

chebspec—Chebyshev spectral differentiation matrix

`C = gallery('chebspec', n, switch)` returns a Chebyshev spectral differentiation matrix of order `n`. Argument `switch` is a variable that determines the character of the output matrix. By default, `switch = 0`.

For `switch = 0` (“no boundary conditions”), `C` is nilpotent ($C^n = 0$) and has the null vector `ones(n, 1)`. The matrix `C` is similar to a Jordan block of size `n` with eigenvalue zero.

For `switch = 1`, `C` is nonsingular and well-conditioned, and its eigenvalues have negative real parts.

The eigenvector matrix `V` of the Chebyshev spectral differentiation matrix is ill-conditioned.

chebvand—Vandermonde-like matrix for the Chebyshev polynomials

`C = gallery('chebvand', p)` produces the (primal) Chebyshev Vandermonde matrix based on the vector of points `p`, which define where the Chebyshev polynomial is calculated.

`C = gallery('chebvand', m, p)` where `m` is scalar, produces a rectangular version of the above, with `m` rows.

If `p` is a vector, then $C(i, j) = T_{i-1}(p(j))$ where T_{i-1} is the Chebyshev polynomial of degree $i - 1$. If `p` is a scalar, then `p` equally spaced points on the interval $[0, 1]$ are used to calculate `C`.

chow—Singular Toeplitz lower Hessenberg matrix

`A = gallery('chow', n, al pha, del ta)` returns `A` such that

$A = H(\text{al pha}) + \text{del ta} * \text{eye}(n)$, where $H_{i,j}(\alpha) = \alpha^{(i-j+1)}$ and argument `n` is the order of the Chow matrix. `al pha` and `del ta` are scalars with default values 1 and 0, respectively.

`H(al pha)` has $p = \text{floor}(n/2)$ eigenvalues that are equal to zero. The rest of the eigenvalues are equal to $4 * \text{al pha} * \cos(k * \pi / (n+2))^2$, $k=1:n-p$.

circul—Circulant matrix

`C = gallery('ci rcul', v)` returns the circulant matrix whose first row is the vector `v`.

A circulant matrix has the property that each row is obtained from the previous one by cyclically permuting the entries one step forward. It is a special Toeplitz matrix in which the diagonals “wrap around.”

If `v` is a scalar, then `C = gallery('ci rcul', 1: v)`.

The eigensystem of `C` (n-by-n) is known explicitly: If `t` is an nth root of unity, then the inner product of `v` with $w = [1 \ t^2 \ \dots \ t^{(n-1)}]$ is an eigenvalue of `C` and $w(n:-1:1)$ is an eigenvector.

clement—Tridiagonal matrix with zero diagonal entries

`A = gallery('clement', n, sym)` returns an `n` by `n` tridiagonal matrix with zeros on its main diagonal and known eigenvalues. It is singular if order `n` is odd. About 64 percent of the entries of the inverse are zero. The eigenvalues include plus and minus the numbers $n-1, n-3, n-5, \dots$, as well as (for odd `n`) a final eigenvalue of 1 or 0.

Argument `sym` determines whether the Clement matrix is symmetric. For `sym = 0` (the default) the matrix is nonsymmetric, while for `sym = 1`, it is symmetric.

compar—Comparison matrices

`A = gallery('compar', A, 1)` returns `A` with each diagonal element replaced by its absolute value, and each off-diagonal element replaced by minus the absolute value of the largest element in absolute value in its row. However, if `A` is triangular `compar(A, 1)` is too.

`gallery('compar', A)` is `diag(B) - triu(B, -1) - triu(B, 1)`, where `B = abs(A)`. `compar(A)` is often denoted by $M(A)$ in the literature.

`gallery('compar', A, 0)` is the same as `compar(A)`.

condex—Counter-examples to matrix condition number estimators

`A = gallery('condex', n, k, theta)` returns a “counter-example” matrix to a condition estimator. It has order `n` and scalar parameter `theta` (default 100).

The matrix, its natural size, and the estimator to which it applies are specified by `k`:

<code>k = 1</code>	4-by-4	LINPACK (rcond)
<code>k = 2</code>	3-by-3	LINPACK (rcond)
<code>k = 3</code>	arbitrary	LINPACK (rcond) (independent of <code>theta</code>)
<code>k = 4</code>	<code>n >= 4</code>	SONEST (Higham 1988) (default)

If `n` is not equal to the natural size of the matrix, then the matrix is padded out with an identity matrix to order `n`.

cyclo—Matrix whose columns repeat cyclically

`A = gallery('cyclo', [m n], k)` returns an `m`-by-`n` matrix with cyclically repeating columns, where one “cycle” consists of `randn(m, k)`. Thus, the rank of matrix `A` cannot exceed `k`. `k` must be a scalar.

Argument `k` defaults to `round(n/4)`, and need not evenly divide `n`.

`A = gallery('cyc1', n, k)`, where n is a scalar, is the same as
`gallery('cyc1', [n n], k)`.

dorr—Diagonally dominant, ill-conditioned, tridiagonal matrix

`[c, d, e] = gallery('dorr', n, theta)` returns the vectors defining a row diagonally dominant, tridiagonal order n matrix that is ill-conditioned for small nonnegative values of θ . The default value of θ is 0.01. The Dorr matrix itself is the same as `gallery('tridiag', c, d, e)`.

`A = gallery('dorr', n, theta)` returns the matrix itself, rather than the defining vectors.

dramadah—Matrix of zeros and ones whose inverse has large integer entries

`A = gallery('dramadah', n, k)` returns an n -by- n matrix of 0's and 1's for which $\text{mu}(A) = \text{norm}(\text{inv}(A), 'fro')$ is relatively large, although not necessarily maximal. An anti-Hadamard matrix A is a matrix with elements 0 or 1 for which $\text{mu}(A)$ is maximal.

n and k must both be scalars. Argument k determines the character of the output matrix:

$k = 1$ Default. A is Toeplitz, with $\text{abs}(\det(A)) = 1$, and $\text{mu}(A) > c(1.75)^n$, where c is a constant. The inverse of A has integer entries.

$k = 2$ A is upper triangular and Toeplitz. The inverse of A has integer entries.

$k = 3$ A has maximal determinant among lower Hessenberg (0,1) matrices. $\det(A) =$ the n th Fibonacci number. A is Toeplitz. The eigenvalues have an interesting distribution in the complex plane.

fiedler—Symmetric matrix

`A = gallery('fiedler', c)`, where c is a length n vector, returns the n -by- n symmetric matrix with elements $\text{abs}(n(i) - n(j))$. For scalar c ,
`A = gallery('fiedler', 1: c)`.

Matrix A has a dominant positive eigenvalue and all the other eigenvalues are negative.

Explicit formulas for $i \operatorname{nv}(A)$ and $\det(A)$ are given in [Todd, J., *Basic Numerical Mathematics*, Vol. 2: Numerical Algebra, Birkhauser, Basel, and Academic Press, New York, 1977, p. 159] and attributed to Fiedler. These indicate that $i \operatorname{nv}(A)$ is tridiagonal except for nonzero (1, n) and (n, 1) elements.

forsythe—Perturbed Jordan block

`A = gallery('forsythe', n, al pha, l ambda)` returns the n-by-n matrix equal to the Jordan block with eigenvalue `l ambda`, excepting that $A(n, 1) = al pha$. The default values of scalars `al pha` and `l ambda` are `sqr(eps)` and 0, respectively.

The characteristic polynomial of A is given by:

$$\det(A - t^*I) = (l ambda - t)^N - al pha^*(-1)^n.$$

frank—Matrix with ill-conditioned eigenvalues

`F = gallery('frank', n, k)` returns the Frank matrix of order n. It is upper Hessenberg with determinant 1. If `k = 1`, the elements are reflected about the anti-diagonal (1, n)—(n, 1). The eigenvalues of F may be obtained in terms of the zeros of the Hermite polynomials. They are positive and occur in reciprocal pairs; thus if n is odd, 1 is an eigenvalue. F has `floor(n/2)` ill-conditioned eigenvalues—the smaller ones.

gearmat—Gear matrix

`A = gallery('gearmat', n, i, j)` returns the n-by-n matrix with ones on the sub- and super-diagonals, `si gn(i)` in the $(1, \operatorname{abs}(i))$ position, `si gn(j)` in the $(n, n+1-\operatorname{abs}(j))$ position, and zeros everywhere else. Arguments `i` and `j` default to `n` and `-n`, respectively.

Matrix A is singular, can have double and triple eigenvalues, and can be defective.

All eigenvalues are of the form $2 * \cos(a)$ and the eigenvectors are of the form $[\sin(w+a), \sin(w+2a), \dots, \sin(w+Na)]$, where `a` and `w` are given in Gear,

C. W., "A Simple Set of Test Matrices for Eigenvalue Programs", *Math. Comp.*, Vol. 23 (1969), pp. 119-125.

grcar—Toeplitz matrix with sensitive eigenvalues

`A = gallery(' grcar' , n, k)` returns an n-by-n Toeplitz matrix with - 1s on the subdiagonal, 1s on the diagonal, and k superdiagonals of 1s. The default is k = 3. The eigenvalues are sensitive.

hanowa—Matrix whose eigenvalues lie on a vertical line in the complex plane

`A = gallery(' hanowa' , n, d)` returns an n-by-n block 2-by-2 matrix of the form:

$$\begin{bmatrix} d^*eye(m) & -diag(1:m) \\ diag(1:m) & d^*eye(m) \end{bmatrix}$$

Argument n is an even integer n=2*m. Matrix A has complex eigenvalues of the form $d \pm k*i$, for $1 \leq k \leq m$. The default value of d is -1.

house—Householder matrix

`[v, beta] = gallery(' house' , x)` takes x, a scalar or n-element column vector, and returns v and beta such that $eye(n, n) - beta*v*v'$ is a Householder matrix. A Householder matrix H satisfies the relationship

$$H*x = -\text{sign}(x(1)) * \text{norm}(x) * e1$$

where e1 is the first column of $eye(n, n)$. Note that if x is complex, then $\text{sign}(x) = \exp(i * \text{arg}(x))$ (which equals $x / \text{abs}(x)$ when x is nonzero).

If x = 0, then v = 0 and beta = 1.

invhess—Inverse of an upper Hessenberg matrix

`A = gallery(' invhess' , x, y)`, where x is a length n vector and y a length n-1 vector, returns the matrix whose lower triangle agrees with that of

`ones(n, 1) *x'` and whose strict upper triangle agrees with that of
`[1 y]*ones(1, n)`.

The matrix is nonsingular if $x(1) \approx 0$ and $x(i+1) \approx y(i)$ for all i , and its inverse is an upper Hessenberg matrix. Argument `y` defaults to `-x(1:n-1)`.

If `x` is a scalar, `invhess(x)` is the same as `invhess(1:x)`.

invol—Involutory matrix

`A = gallery('invol', n)` returns an n -by- n involutory ($A^*A = eye(n)$) and ill-conditioned matrix. It is a diagonally scaled version of `hilb(n)`.

`B = (eye(n) - A)/2` and `B = (eye(n) + A)/2` are idempotent ($B^*B = B$).

ipjfact—Hankel matrix with factorial elements

`[A, d] = gallery('ipjfact', n, k)` returns `A`, an n -by- n Hankel matrix, and `d`, the determinant of `A`, which is known explicitly. If $k = 0$ (the default), then the elements of `A` are $A(i, j) = (i+j)!$. If $k = 1$, then the elements of `A` are $A(i, j) = 1/(i+j)$.

Note that the inverse of `A` is also known explicitly.

jordbloc—Jordan block

`A = gallery('jordbloc', n, lambda)` returns the n -by- n Jordan block with eigenvalue `lambda`. The default value for `lambda` is 1.

kahan—Upper trapezoidal matrix

`A = gallery('kahan', n, theta, pert)` returns an upper trapezoidal matrix that has interesting properties regarding estimation of condition and rank.

If `n` is a two-element vector, then `A` is `n(1)`-by-`n(2)`; otherwise, `A` is n -by- n . The useful range of `theta` is $0 < theta < pi$, with a default value of 1.2.

To ensure that the QR factorization with column pivoting does not interchange columns in the presence of rounding errors, the diagonal is perturbed by `pert*eps*diag([n:-1:1])`. The default `pert` is 25, which ensures no interchanges for `gallery('kahan', n)` up to at least $n = 90$ in IEEE arithmetic.

kms—Kac-Murdock-Szegö Toeplitz matrix

`A = gallery('kms', n, rho)` returns the n-by-n Kac-Murdock-Szegö Toeplitz matrix such that $A(i, j) = \rho^{\alpha}(\text{abs}(i-j))$, for real ρ .

For complex ρ , the same formula holds except that elements below the diagonal are conjugated. ρ defaults to 0.5.

The KMS matrix A has these properties:

- An LDL' factorization with $L = \text{inv}(\text{triu}(n, -\rho, 1)')$, and $D(i, i) = (1 - \text{abs}(\rho)^2) * \text{eye}(n)$, except $D(1, 1) = 1$.
- Positive definite if and only if $0 < \text{abs}(\rho) < 1$.
- The inverse $\text{inv}(A)$ is tridiagonal.

krylov—Krylov matrix

`B = gallery('krylov', A, x, j)` returns the Krylov matrix

$$[x, Ax, A^2x, \dots, A^{(j-1)}x]$$

where A is an n-by-n matrix and x is a length n vector. The defaults are $x = \text{ones}(n, 1)$, and $j = n$.

`B = gallery('krylov', n)` is the same as `gallery('krylov', (randn(n))`.

lauchli—Rectangular matrix

`A = gallery('lauchli', n, mu)` returns the $(n+1)$ -by-n matrix

$$[\text{ones}(1, n); \mu * \text{eye}(n)]$$

The Lauchli matrix is a well-known example in least squares and other problems that indicates the dangers of forming $A' * A$. Argument μ defaults to $\text{sqrt}(\text{eps})$.

lehmer—Symmetric positive definite matrix

`A = gallery('lehmer', n)` returns the symmetric positive definite n-by-n matrix such that $A(i, j) = i/j$ for $j \geq i$.

The Lehmer matrix A has these properties:

- A is totally nonnegative.
- The inverse $\text{inv}(A)$ is tridiagonal and explicitly known.
- The order $n \leq \text{cond}(A) \leq 4*n^2$.

lesp—Tridiagonal matrix with real, sensitive eigenvalues

`A = gallery('lesp', n)` returns an n-by-n matrix whose eigenvalues are real and smoothly distributed in the interval approximately $[-2\sqrt{n} - 3.5, -4.5]$.

The sensitivities of the eigenvalues increase exponentially as the eigenvalues grow more negative. The matrix is similar to the symmetric tridiagonal matrix with the same diagonal entries and with off-diagonal entries 1, via a similarity transformation with $D = \text{diag}(1!, 2!, \dots, n!)$.

lotkin—Lotkin matrix

`A = gallery('lotkin', n)` returns the Hilbert matrix with its first row altered to all ones. The Lotkin matrix A is nonsymmetric, ill-conditioned, and has many negative eigenvalues of small magnitude. Its inverse has integer entries and is known explicitly.

minij—Symmetric positive definite matrix

`A = gallery('minij', n)` returns the n-by-n symmetric positive definite matrix with $A(i, j) = \min(i, j)$.

The `minij` matrix has these properties:

- The inverse $\text{inv}(A)$ is tridiagonal and equal to -1 times the second difference matrix, except its (n, n) element is 1.
- Givens' matrix, $2*A - \text{ones}(\text{size}(A))$, has tridiagonal inverse and eigenvalues $0.5 * \sec((2*r-1)*\pi/(4*n))^2$, where $r=1:n$.
- $(n+1)*\text{ones}(\text{size}(A)) - A$ has elements that are $\max(i, j)$ and a tridiagonal inverse.

moler—Symmetric positive definite matrix

`A = gallery('moler', n, alpha)` returns the symmetric positive definite n -by- n matrix U^*U , where $U = \text{triw}(n, \alpha)$.

For the default $\alpha = -1$, $A(i, j) = \min(i, j) - 2$, and $A(i, i) = i$. One of the eigenvalues of A is small.

neumann—Singular matrix from the discrete Neumann problem (sparse)

`C = gallery('neumann', n)` returns the singular, row-diagonally dominant matrix resulting from discretizing the Neumann problem with the usual five-point operator on a regular mesh. Argument n is a perfect square

integer $n = m^2$ or a two-element vector. C is sparse and has a one-dimensional null space with null vector `ones(n, 1)`.

orthog—Orthogonal and nearly orthogonal matrices

`Q = gallery('orthog', n, k)` returns the k th type of matrix of order n , where $k > 0$ selects exactly orthogonal matrices, and $k < 0$ selects diagonal scalings of orthogonal matrices. Available types are:

$k = 1$ $Q(i, j) = \sqrt{2/(n+1)} * \sin(i * j * \pi / (n+1))$

Symmetric eigenvector matrix for second difference matrix. This is the default.

$k = 2$ $Q(i, j) = 2 / (\sqrt{2 * n + 1}) * \sin(2 * i * j * \pi / (2 * n + 1))$
Symmetric.

$k = 3$ $Q(r, s) = \exp(2 * \pi * i * (r - 1) * (s - 1) / n) / \sqrt{n}$
Unitary, the Fourier matrix. Q^4 is the identity. This is essentially the same matrix as `fft(eye(n)) / sqrt(n)`!

$k = 4$ Helmert matrix: a permutation of a lower Hessenberg matrix, whose first row is `ones(1:n) / sqrt(n)`.

$k = 5$ $Q(i, j) = \sin(2 * \pi * (i - 1) * (j - 1) / n) + \cos(2 * \pi * (i - 1) * (j - 1) / n)$
Symmetric matrix arising in the Hartley transform.

k = -1 $Q(i,j) = \cos((i-1)*(j-1)*\pi/(n-1))$
Chebyshev Vandermonde-like matrix, based on extrema of $T(n-1)$.

k = -2 $Q(i,j) = \cos((i-1)*(j-1/2)*\pi/n)$
Chebyshev Vandermonde-like matrix, based on zeros of $T(n)$.

parter—Toeplitz matrix with singular values near pi

$C = \text{gallery}('parter', n)$ returns the matrix C such that $C(i,j) = 1/(i-j+0.5)$.

C is a Cauchy matrix and a Toeplitz matrix. Most of the singular values of C are very close to π .

pei—Pei matrix

$A = \text{gallery}('pei', n, al pha)$, where $al pha$ is a scalar, returns the symmetric matrix $al pha * eye(n) + ones(n)$. The default for $al pha$ is 1. The matrix is singular for $al pha$ equal to either 0 or -n.

poisson—Block tridiagonal matrix from Poisson's equation (sparse)

$A = \text{gallery}('poisson', n)$ returns the block tridiagonal (sparse) matrix of order n^2 resulting from discretizing Poisson's equation with the 5-point operator on an n -by- n mesh.

prolate—Symmetric, ill-conditioned Toeplitz matrix

$A = \text{gallery}('prolate', n, w)$ returns the n -by- n prolate matrix with parameter w . It is a symmetric Toeplitz matrix.

If $0 < w < 0.5$ then A is positive definite

- The eigenvalues of A are distinct, lie in $(0, 1)$, and tend to cluster around 0 and 1.
- The default value of w is 0.25.

randcolu — Random matrix with normalized cols and specified singular values

`A = gallery('randcolu', n)` is a random n-by-n matrix with columns of unit 2-norm, with random singular values whose squares are from a uniform distribution.

`A' *A` is a correlation matrix of the form produced by `gallery('randcorr', n)`.

`gallery('randcolu', x)` where `x` is an n-vector ($n > 1$), produces a random n-by-n matrix having singular values given by the vector `x`. The vector `x` must have nonnegative elements whose sum of squares is n .

`gallery('randcolu', x, m)` where `m >= n`, produces an m-by-n matrix.

`gallery('randcolu', x, m, k)` provides a further option:

`k = 0` `diag(x)` is initially subjected to a random two-sided orthogonal transformation, and then a sequence of Givens rotations is applied (default).

`k = 1` The initial transformation is omitted. This is much faster, but the resulting matrix may have zero entries.

For more information, see:

[1] Davies, P. I. and N. J. Higham, "Numerically Stable Generation of Correlation Matrices and Their Factors," *BIT*, Vol. 40, 2000, pp. 640-651.

randcorr — Random correlation matrix with specified eigenvalues

`gallery('randcorr', n)` is a random n-by-n correlation matrix with random eigenvalues from a uniform distribution. A correlation matrix is a symmetric positive semidefinite matrix with 1s on the diagonal (see `corrcoef`).

`gallery('randcorr', x)` produces a random correlation matrix having eigenvalues given by the vector `x`, where `length(x) > 1`. The vector `x` must have nonnegative elements summing to `length(x)`.

`gallery('randcorr', x, k)` provides a further option:

- | | |
|-------|---|
| k = 0 | The diagonal matrix of eigenvalues is initially subjected to a random orthogonal similarity transformation, and then a sequence of Givens rotations is applied (default). |
| k = 1 | The initial transformation is omitted. This is much faster, but the resulting matrix may have some zero entries. |

For more information, see:

[1] Bendel, R. B. and M. R. Mickey, "Population Correlation Matrices for Sampling Experiments," *Commun. Statist. Simulation Comput.*, B7, 1978, pp. 163-182.

[2] Davies, P. I. and N. J. Higham, "Numerically Stable Generation of Correlation Matrices and Their Factors," *BIT*, Vol. 40, 2000, pp. 640-651.

randhess—Random, orthogonal upper Hessenberg matrix

`H = gallery('randhess', n)` returns an n-by-n real, random, orthogonal upper Hessenberg matrix.

`H = gallery('randhess', x)` if x is an arbitrary, real, length n vector with n > 1, constructs H nonrandomly using the elements of x as parameters.

Matrix H is constructed via a product of n-1 Givens rotations.

rando—Random matrix composed of elements -1, 0 or 1

`A = gallery('rando', n, k)` returns a random n-by-n matrix with elements from one of the following discrete distributions:

- | | |
|-------|--|
| k = 1 | $A(i, j) = 0$ or 1 with equal probability (default). |
| k = 2 | $A(i, j) = -1$ or 1 with equal probability. |
| k = 3 | $A(i, j) = -1, 0$ or 1 with equal probability. |

Argument n may be a two-element vector, in which case the matrix is $n(1)$ -by- $n(2)$.

randsvd—Random matrix with preassigned singular values

`A = gallery('randsvd', n, kappa, mode, kl, ku)` returns a banded (multidiagonal) random matrix of order `n` with `cond(A) = kappa` and singular values from the distribution mode. If `n` is a two-element vector, `A` is `n(1)-by-n(2)`.

Arguments `kl` and `ku` specify the number of lower and upper off-diagonals, respectively, in `A`. If they are omitted, a full matrix is produced. If only `kl` is present, `ku` defaults to `kl`.

Distribution mode can be:

- 1 One large singular value.
 - 2 One small singular value.
 - 3 Geometrically distributed singular values (default).
 - 4 Arithmetically distributed singular values.
 - 5 Random singular values with uniformly distributed logarithm.
- < 0 If mode is -1, -2, -3, -4, or -5, then randsvd treats mode as `abs(mode)`, except that in the original matrix of singular values the order of the diagonal entries is reversed: small to large instead of large to small.

Condition number `kappa` defaults to `sqrt(1/eps)`. In the special case where `kappa < 0`, `A` is a random, full, symmetric, positive definite matrix with `cond(A) = -kappa` and eigenvalues distributed according to mode. Arguments `kl` and `ku`, if present, are ignored.

redheff—Redheffer's matrix of 1s and 0s

`A = gallery('redheff', n)` returns an `n`-by-`n` matrix of 0's and 1's defined by `A(i,j) = 1`, if `j = 1` or if `i` divides `j`, and `A(i,j) = 0` otherwise.

The Redheffer matrix has these properties:

- $(n - \text{floor}(\log_2(n))) - 1$ eigenvalues equal to 1
- A real eigenvalue (the spectral radius) approximately `sqrt(n)`
- A negative eigenvalue approximately `-sqrt(n)`

- The remaining eigenvalues are provably “small.”
- The Riemann hypothesis is true if and only if $\det(A) = O(n^{(1/2+\epsilon)})$ for every $\epsilon > 0$.

Barrett and Jarvis conjecture that “the small eigenvalues all lie inside the unit circle $\|Z\| = 1$,” and a proof of this conjecture, together with a proof that some eigenvalue tends to zero as n tends to infinity, would yield a new proof of the prime number theorem.

riemann—Matrix associated with the Riemann hypothesis

$A = \text{gallery}('riemann', n)$ returns an n -by- n matrix for which the Riemann hypothesis is true if and only if $\det(A) = O(n! n^{-1/2+\epsilon})$ for every $\epsilon > 0$.

The Riemann matrix is defined by:

$$A = B(2:n+1, 2:n+1)$$

where $B(i, j) = i - 1$ if i divides j , and $B(i, j) = -1$ otherwise.

The Riemann matrix has these properties:

- Each eigenvalue $e(i)$ satisfies $\|e(i)\| \leq m - 1/m$, where $m = n+1$.
- $i \leq e(i) \leq i+1$ with at most $m \cdot \sqrt{m}$ exceptions.
- All integers in the interval $(m/3, m/2]$ are eigenvalues.

ris—Symmetric Hankel matrix

$A = \text{gallery}('ris', n)$ returns a symmetric n -by- n Hankel matrix with elements

$$A(i, j) = 0.5 / (n - i - j + 1.5)$$

The eigenvalues of A cluster around $\pi/2$ and $-\pi/2$. This matrix was invented by F.N. Ris.

rosser—Classic symmetric eigenvalue test matrix

$A = \text{rosser}$ returns the Rosser matrix. This matrix was a challenge for many matrix eigenvalue algorithms. But the Francis QR algorithm, as perfected by

Wilkinson and implemented in MATLAB, has no trouble with it. The matrix is 8-by-8 with integer elements. It has:

- A double eigenvalue
- Three nearly equal eigenvalues
- Dominant eigenvalues of opposite sign
- A zero eigenvalue
- A small, nonzero eigenvalue

smoke—Complex matrix with a 'smoke ring' pseudospectrum

`A = gallery('smoke', n)` returns an n-by-n matrix with 1's on the superdiagonal, 1 in the (n, 1) position, and powers of roots of unity along the diagonal.

`A = gallery('smoke', n, 1)` returns the same except that element A(n, 1) is zero.

The eigenvalues of `smoke(n, 1)` are the nth roots of unity; those of `smoke(n)` are the nth roots of unity times $2^{(1/n)}$.

toeppd—Symmetric positive definite Toeplitz matrix

`A = gallery('toeppd', n, m, w, theta)` returns an n-by-n symmetric, positive semi-definite (SPD) Toeplitz matrix composed of the sum of m rank 2 (or, for certain theta, rank 1) SPD Toeplitz matrices. Specifically,

$$T = w(1)*T(theta(1)) + \dots + w(m)*T(theta(m))$$

where `T(theta(k))` has (i, j) element $\cos(2\pi * theta(k) * (i - j))$.

By default: `m = n`, `w = rand(m, 1)`, and `theta = rand(m, 1)`.

toeppen—Pentadiagonal Toeplitz matrix (sparse)

`P = gallery('toeppen', n, a, b, c, d, e)` returns the n-by-n sparse, pentadiagonal Toeplitz matrix with the diagonals: $P(3, 1) = a$, $P(2, 1) = b$, $P(1, 1) = c$, $P(1, 2) = d$, and $P(1, 3) = e$, where a, b, c, d, and e are scalars.

By default, $(a, b, c, d, e) = (1, -10, 0, 10, 1)$, yielding a matrix of Rutishauser. This matrix has eigenvalues lying approximately on the line segment $2\cos(2t) + 20i\sin(t)$.

tridiag—Tridiagonal matrix (sparse)

`A = gallery('tridiag', c, d, e)` returns the tridiagonal matrix with subdiagonal `c`, diagonal `d`, and superdiagonal `e`. Vectors `c` and `e` must have `length(d) - 1`.

`A = gallery('tridiag', n, c, d, e)`, where `c`, `d`, and `e` are all scalars, yields the Toeplitz tridiagonal matrix of order `n` with subdiagonal elements `c`, diagonal elements `d`, and superdiagonal elements `e`. This matrix has eigenvalues

$$d + 2\sqrt{c \cdot e} \cdot \cos(k \cdot \pi / (n+1))$$

where `k = 1:n`. (see [1].)

`A = gallery('tridiag', n)` is the same as

`A = gallery('tridiag', n, -1, 2, -1)`, which is a symmetric positive definite M-matrix (the negative of the second difference matrix).

triw—Upper triangular matrix discussed by Wilkinson and others

`A = gallery('triw', n, alpha, k)` returns the upper triangular matrix with ones on the diagonal and alphas on the first $k \geq 0$ superdiagonals.

Order `n` may be a 2-vector, in which case the matrix is $n(1)$ -by- $n(2)$ and upper trapezoidal.

Ostrowski ["On the Spectrum of a One-parametric Family of Matrices, *J. Reine Angew. Math.*, 1954] shows that

$$\text{cond}(\text{gallery('triw', n, 2)}) = \cot(\pi / (4 \cdot n))^2,$$

and, for large `abs(alpha)`, `cond(gallery('triw', n, alpha))` is approximately `abs(alpha)^n * sin(pi / (4 * n - 2))`.

Adding $-2^{(2-n)}$ to the $(n, 1)$ element makes `triw(n)` singular, as does adding $-2^{(1-n)}$ to all the elements in the first column.

vander—Vandermonde matrix

`A = gallery('vander', c)` returns the Vandermonde matrix whose second to last column is `c`. The j th column of a Vandermonde matrix is given by $A(:, j) = C^{(n-j)}$.

wathen—Finite element matrix (sparse, random entries)

`A = gallery('wathen', nx, ny)` returns a sparse, random, n -by- n finite element matrix where

$$n = 3*nx*ny + 2*nx + 2*ny + 1.$$

Matrix `A` is precisely the “consistent mass matrix” for a regular nx -by- ny grid of 8-node (serendipity) elements in two dimensions. `A` is symmetric, positive definite for any (positive) values of the “density,” `rho(nx, ny)`, which is chosen randomly in this routine.

`A = gallery('wathen', nx, ny, 1)` returns a diagonally scaled matrix such that

$$0.25 \leq \text{eig}(\text{inv}(D)*A) \leq 4.5$$

where `D = diag(diag(A))` for any positive integers `nx` and `ny` and any densities `rho(nx, ny)`.

wilk—Various matrices devised or discussed by Wilkinson

`[A, b] = gallery('wilk', n)` returns a different matrix or linear system depending on the value of `n`.

`n = 3` Upper triangular system $Ux=b$ illustrating inaccurate solution.

`n = 4` Lower triangular system $Lx=b$, ill-conditioned.

`n = 5` `hilb(6)(1:5, 2:6)*1.8144`. A symmetric positive definite matrix.

`n = 21` `W21+`, tridiagonal matrix. Eigenvalue problem.

See Also

`hadamard`, `hilb`, `invhilb`, `magic`, `wilkinson`

References

The MATLAB gallery of test matrices is based upon the work of Nicholas J. Higham at the Department of Mathematics, University of Manchester, Manchester, England. Additional detail on these matrices is documented in *The Test Matrix Toolbox for MATLAB* by N. J. Higham, September, 1995. This report is available via anonymous ftp from The MathWorks at `ftp://ftp.mathworks.com/pub/contrib/linAlg/testmatrix/testmatrix.ps` or on the Web at `ftp://ftp.ma.man.ac.uk/pub/narep` or `http://www.ma.man.ac.uk/MCCM/MCCM.html`. Further background can be found in the book *Accuracy and Stability of Numerical Algorithms*, Nicholas J. Higham, SIAM, 1996.

gamma, gammairc, gammaln

Purpose	Gamma functions	
Syntax	$Y = \text{gamma}(A)$	Gamma function
	$Y = \text{gammairc}(X, A)$	Incomplete gamma function
	$Y = \text{gammaln}(A)$	Logarithm of gamma function
Definition	The gamma function is defined by the integral:	
	$\Gamma(a) = \int_0^{\infty} e^{-t} t^{a-1} dt$	
	The gamma function interpolates the factorial function. For integer n:	
	$\text{gamma}(n+1) = n! = \text{prod}(1:n)$	
	The incomplete gamma function is:	
	$P(x, a) = \frac{1}{\Gamma(a)} \int_0^x e^{-t} t^{a-1} dt$	
Description	$Y = \text{gamma}(A)$ returns the gamma function at the elements of A. A must be real.	
	$Y = \text{gammairc}(X, A)$ returns the incomplete gamma function of corresponding elements of X and A. Arguments X and A must be real and the same size (or either can be scalar).	
	$Y = \text{gammaln}(A)$ returns the logarithm of the gamma function, $\text{gammaln}(A) = \log(\text{gamma}(A))$. The gammaln command avoids the underflow and overflow that may occur if it is computed directly using $\log(\text{gamma}(A))$.	
Algorithm	The computations of gamma and gammaln are based on algorithms outlined in [1]. Several different minimax rational approximations are used depending upon the value of A. Computation of the incomplete gamma function is based on the algorithm in [2].	

gamma, gammairc, gammaln

References

- [1] Cody, J., *An Overview of Software Development for Special Functions*, Lecture Notes in Mathematics, 506, Numerical Analysis Dundee, G. A. Watson (ed.), Springer Verlag, Berlin, 1976.
- [2] Abramowitz, M. and I.A. Stegun, *Handbook of Mathematical Functions*, National Bureau of Standards, Applied Math. Series #55, Dover Publications, 1965, sec. 6.5.

Purpose	Get current axes handle
Syntax	<code>h = gca</code>
Description	<p><code>h = gca</code> returns the handle to the current axes for the current figure. If no axes exists, MATLAB creates one and returns its handle. You can use the statement</p> <pre>get(gcf, 'CurrentAxes')</pre> <p>if you do not want MATLAB to create an axes if one does not already exist.</p> <p>The current axes is the target for graphics output when you create axes children. Graphics commands such as <code>plot</code>, <code>text</code>, and <code>surf</code> draw their results in the current axes. Changing the current figure also changes the current axes.</p>
See Also	<code>axes</code> , <code>cla</code> , <code>delete</code> , <code>gcf</code> , <code>gcbo</code> , <code>gco</code> , <code>hold</code> , <code> subplot</code> , <code>findobj</code> <code>figure CurrentAxes property</code>

gcbf

Purpose	Get handle of figure containing object whose callback is executing
Syntax	<code>fig = gcbf</code>
Description	<code>fig = gcbf</code> returns the handle of the figure that contains the object whose callback is currently executing. This object can be the figure itself, in which case, <code>gcbf</code> returns the figure's handle. When no callback is executing, <code>gcbf</code> returns the empty matrix, <code>[]</code> . The value returned by <code>gcbf</code> is identical to the figure output argument returned by <code>gcbo</code> .
See Also	<code>gcbo</code> , <code>gco</code> , <code>gcf</code> , <code>gca</code>

Purpose	Return the handle of the object whose callback is currently executing
Syntax	<pre>h = gcbo</pre> <pre>[h, figure] = gcbo</pre>
Description	<p><code>h = gcbo</code> returns the handle of the graphics object whose callback is executing.</p> <p><code>[h, figure] = gcbo</code> returns the handle of the current callback object and the handle of the figure containing this object.</p>
Remarks	<p>MATLAB stores the handle of the object whose callback is executing in the root <code>CallbackObject</code> property. If a callback interrupts another callback, MATLAB replaces the <code>CallbackObject</code> value with the handle of the object whose callback is interrupting. When that callback completes, MATLAB restores the handle of the object whose callback was interrupted.</p> <p>The root <code>CallbackObject</code> property is read-only, so its value is always valid at any time during callback execution. The root <code>CurrentFigure</code> property, and the <code>figure CurrentAxes</code> and <code>CurrentObject</code> properties (returned by <code>gcf</code>, <code>gca</code>, and <code>gco</code> respectively) are user settable, so they can change during the execution of a callback, especially if that callback is interrupted by another callback. Therefore, those functions are not reliable indicators of which object's callback is executing.</p> <p>When you write callback routines for the <code>CreateFcn</code> and <code>DeleteFcn</code> of any object and the <code>figure ResizeFcn</code>, you must use <code>gcbo</code> since those callbacks do not update the root's <code>CurrentFigure</code> property, or the figure's <code>CurrentObject</code> or <code>CurrentAxes</code> properties; they only update the root's <code>CallbackObject</code> property.</p> <p>When no callbacks are executing, <code>gcbo</code> returns <code>[]</code> (an empty matrix).</p>
See Also	<code>gca</code> , <code>gcf</code> , <code>gco</code> , <code>rootobject</code>

gcd

Purpose	Greatest common divisor
Syntax	$G = \text{gcd}(A, B)$ $[G, C, D] = \text{gcd}(A, B)$
Description	$G = \text{gcd}(A, B)$ returns an array containing the greatest common divisors of the corresponding elements of integer arrays A and B. By convention, $\text{gcd}(0, 0)$ returns a value of 0; all other inputs return positive integers for G. $[G, C, D] = \text{gcd}(A, B)$ returns both the greatest common divisor array G, and the arrays C and D, which satisfy the equation: $A(i) \cdot C(i) + B(i) \cdot D(i) = G(i)$. These are useful for solving Diophantine equations and computing elementary Hermite transformations.
Examples	The first example involves elementary Hermite transformations. For any two integers a and b there is a 2-by-2 matrix E with integer entries and determinant = 1 (<i>a unimodular matrix</i>) such that: $E * [a; b] = [g, 0]$, where g is the greatest common divisor of a and b as returned by the command $[g, c, d] = \text{gcd}(a, b)$. The matrix E equals: $\begin{matrix} c & d \\ -b/g & a/g \end{matrix}$ In the case where a = 2 and b = 4: $[g, c, d] = \text{gcd}(2, 4)$ $g = 2$ $c = 1$ $d = 0$

So that

$$\begin{array}{rcl} E = & & \\ & 1 & 0 \\ & -2 & 1 \end{array}$$

In the next example, we solve for x and y in the Diophantine equation
 $30x + 56y = 8$.

$$[g, c, d] = \text{gcd}(30, 56)$$

$$\begin{array}{rcl} g = & & \\ & 2 & \end{array}$$

$$\begin{array}{rcl} c = & & \\ & -13 & \end{array}$$

$$\begin{array}{rcl} d = & & \\ & 7 & \end{array}$$

By the definition, for scalars c and d :

$$30(-13) + 56(7) = 2,$$

Multiplying through by 8/2:

$$30(-13*4) + 56(7*4) = 8$$

Comparing this to the original equation, a solution can be read by inspection:

$$x = (-13*4) = -52; \quad y = (7*4) = 28$$

See Also

1 cm

References

[1] Knuth, Donald, *The Art of Computer Programming*, Vol. 2, Addison-Wesley: Reading MA, 1973. Section 4.5.2, Algorithm X.

gcf

Purpose	Get current figure handle
Syntax	<code>h = gcf</code>
Description	<code>h = gcf</code> returns the handle of the current figure. The current figure is the figure window in which graphics commands such as <code>plot</code> , <code>title</code> , and <code>surf</code> draw their results. If no figure exists, MATLAB creates one and returns its handle. You can use the statement <code>get(0, 'CurrentFigure')</code>
	if you do not want MATLAB to create a figure if one does not already exist.

See Also `axes`, `clf`, `close`, `delete`, `figure`, `gca`, `gcbo`, `gco`, `subplot`
`root CurrentFigure property`

Purpose	Return handle of current object
Syntax	<code>h = gco</code> <code>h = gco(figure_handle)</code>
Description	<code>h = gco</code> returns the handle of the current object. <code>h = gco(figure_handle)</code> returns the value of the current object for the figure specified by <code>figure_handle</code> .
Remarks	The current object is the last object clicked on, excluding uimenus. If the mouse click did not occur over a figure child object, the figure becomes the current object. MATLAB stores the handle of the current object in the figure's <code>CurrentObject</code> property. The <code>CurrentObject</code> of the <code>CurrentFigure</code> does not always indicate the object whose callback is being executed. Interruptions of callbacks by other callbacks can change the <code>CurrentObject</code> or even the <code>CurrentFigure</code> . Some callbacks, such as <code>CreateFcn</code> and <code>DeleteFcn</code> , and <code>uimenu Callback</code> intentionally do not update <code>CurrentFigure</code> or <code>CurrentObject</code> . <code>gcbo</code> provides the only completely reliable way to retrieve the handle to the object whose callback is executing, at any point in the callback function, regardless of the type of callback or of any previous interruptions.
Examples	This statement returns the handle to the current object in figure window 2: <code>h = gco(2)</code>
See Also	<code>gca</code> , <code>gcbo</code> , <code>gcf</code> The root object description

genpath

Purpose	Generate a path string
Syntax	<pre>genpath genpath directory p = genpath('directory')</pre>
Description	<p><code>genpath</code> returns a path string formed by recursively adding all the directories below <code>matlabroot/tool box</code>.</p> <p><code>genpath directory</code> returns a path string formed by recursively adding all the directories below <code>directory</code>.</p> <p><code>p = genpath('directory')</code> returns the path string to variable, <code>p</code>.</p>
Examples	<p>You generate a path that includes <code>matlabroot\tool box\images</code> and all directories below that with the following command:</p> <pre>p = genpath(fullfile(matlabroot, 'toolbox', 'images')) p = matlabroot\toolbox\images; matlabroot\toolbox\images\images; matlabroot\toolbox\images\images\ja; matlabroot\toolbox\images\images\ imdemos; matlabroot\toolbox\images\imdemos\ja;</pre> <p>You can also use <code>genpath</code> in conjunction with <code>addpath</code> to add subdirectories to the path from the command line. The following example adds the <code>\control</code> directory and its subdirectories to the current path.</p> <pre>% Display the current path path MATLABPATH K:\toolbox\matlab\general K:\toolbox\matlab\ops K:\toolbox\matlab\lang K:\toolbox\matlab\elmat K:\toolbox\matlab\elfun : : :</pre>

```
% Use GENPATH to add \control and its subdirectories  
addpath(genpath('K:\tool box\control'))
```

```
% Display the new path  
path
```

MATLABPATH

```
K:\tool box\control  
K:\tool box\control\ctrlutil  
K:\tool box\control\control  
K:\tool box\control\ctrlguis  
K:\tool box\control\ctrldemos  
K:\tool box\matlab\general  
K:\tool box\matlab\ops  
K:\tool box\matlab\lang  
K:\tool box\matlab\elmat  
K:\tool box\matlab\elfun  
:  
:  
:
```

See Also

path, addpath, rmpath

get

Purpose	Get object properties
Syntax	<pre>get(h) get(h, 'PropertyName') <m-by-n value cell array> = get(H, <property cell array> a = get(h) a = get(0, 'Factory') a = get(0, 'FactoryObjectTypePropertyName') a = get(h, 'Default') a = get(h, 'DefaultObjectTypePropertyName')</pre>
Description	<p>get(h) returns all properties and their current values of the graphics object identified by the handle h.</p> <p>get(h, 'PropertyName') returns the value of the property 'PropertyName' of the graphics object identified by h.</p> <p><m-by-n value cell array> = get(H, pn) returns <i>n</i> property values for <i>m</i> graphics objects in the <i>m</i>-by-<i>n</i> cell array, where <i>m</i> = length(H) and <i>n</i> is equal to the number of property names contained in pn.</p> <p>a = get(h) returns a structure whose field names are the object's property names and whose values are the current values of the corresponding properties. h must be a scalar. If you do not specify an output argument, MATLAB displays the information on the screen.</p> <p>a = get(0, 'Factory') returns the factory-defined values of all user-settable properties. a is a structure array whose field names are the object property names and whose field values are the values of the corresponding properties. If you do not specify an output argument, MATLAB displays the information on the screen.</p> <p>a = get(0, 'FactoryObjectTypePropertyName') returns the factory-defined value of the named property for the specified object type. The argument, <i>FactoryObjectTypePropertyName</i>, is the word Factory concatenated with the object type (e.g., Figure) and the property name (e.g., Color).</p> <p>FactoryFigureColor</p>

`a = get(h, 'Default')` returns all default values currently defined on object `h`. `a` is a structure array whose field names are the object property names and whose field values are the values of the corresponding properties. If you do not specify an output argument, MATLAB displays the information on the screen.

`a = get(h, 'DefaultObjTypePropertyName')` returns the factory-defined value of the named property for the specified object type. The argument, `DefaultObjTypePropertyName`, is the word `Default` concatenated with the object type (e.g., `Figure`) and the property name (e.g., `Color`).

`DefaultFigureColor` or

Examples

You can obtain the default value of the `LineWidth` property for line graphics objects defined on the root level with the statement:

```
get(0, 'DefaultLineWidth')
ans =
    0.5000
```

To query a set of properties on all axes children define a cell array of property names:

```
props = {'HandleVisibility', 'Interruptible';
         'SelectionHighlight', 'Type'};
output = get(get(gca, 'Children'), props);
```

The variable `output` is a cell array of dimension `length(get(gca, 'Children'))`-by-4.

For example, type

```
patch; surface; text; line
output = get(get(gca, 'Children'), props)
output =
    'on'      'on'      'on'      'line'
    'on'      'off'     'on'      'text'
    'on'      'on'      'on'      'surface'
    'on'      'on'      'on'      'patch'
```

See Also

`findobj`, `gca`, `gcf`, `gco`, `set`

[Handle Graphics Properties](#)

get (activex)

Purpose	Retrieve a property value from an interface or get a list of properties.
Syntax	<code>v = get (a [, 'propertyname' [, arg1, arg2, ...]])</code>
Arguments	<p><code>a</code> An ActiveX object previously returned from <code>actxcontrol</code>, <code>actxserver</code>, <code>get</code>, or <code>invoke</code>.</p> <p><code>propertyname</code> A string that is the name of the property value to be retrieved.</p> <p><code>arg1, ..., argn</code> Arguments, if any, required by the property being retrieved. Properties are similar to methods in that it is possible for a property to have arguments.</p>
Returns	The value of the property or a list of properties (if you use the form <code>get(a)</code>). The meaning and type of this value is dependent upon the specific property being retrieved. The object's documentation should describe the specific meaning of the return value. See "Converting Data" in <i>MATLAB External Interfaces</i> for a description of how MATLAB converts ActiveX data types.
Description	Retrieve a property value from an interface.

Note You can use the return value of `actxcontrol` as an argument to the `get` function to get a list of properties of the control and methods that can be invoked.

Example	<p>Retrieve a single, property value:</p> <pre>% get the string value of the 'Label' property s = get (a, 'Label');</pre> <p>Retrieve a list of properties:</p> <pre>get (a)</pre> <pre>AutoAlign = [-1] AutoAngle = [-1] AutoAngleConfine = [0]</pre>
----------------	--

```
AutoOffset = [-1]
.
.
.
SelectionOffsetY = [0]
SelectionRadius = [0.8]
Selections = [4]
Value = [0]
```

get (serial)

Purpose	Return serial port object properties
Syntax	<pre>get(obj) out = get(obj) out = get(obj, 'PropertyName')</pre>
Arguments	<p>obj A serial port object or an array of serial port objects.</p> <p>'PropertyName' A property name or a cell array of property names.</p> <p>out A single property value, a structure of property values, or a cell array of property values.</p>
Description	<p><code>get(obj)</code> returns all property names and their current values to the command line for <code>obj</code>.</p> <p><code>out = get(obj)</code> returns the structure <code>out</code> where each field name is the name of a property of <code>obj</code>, and each field contains the value of that property.</p> <p><code>out = get(obj, 'PropertyName')</code> returns the value <code>out</code> of the property specified by <code>PropertyName</code> for <code>obj</code>. If <code>PropertyName</code> is replaced by a 1-by-n or n-by-1 cell array of strings containing property names, then <code>get</code> returns a 1-by-n cell array of values to <code>out</code>. If <code>obj</code> is an array of serial port objects, then <code>out</code> will be a m-by-n cell array of property values where m is equal to the length of <code>obj</code> and n is equal to the number of properties specified.</p>
Remarks	<p>Refer to “Displaying Property Names and Property Values” for a list of serial port object properties that you can return with <code>get</code>.</p> <p>When you specify a property name, you can do so without regard to case, and you can make use of property name completion. For example, if <code>s</code> is a serial port object, then these commands are all valid.</p> <pre>out = get(s, 'BaudRate'); out = get(s, 'baudrate'); out = get(s, 'BAUD');</pre> <p>If you use the <code>help</code> command to display help for <code>get</code>, then you need to supply the pathname shown below.</p> <pre>help serial/get</pre>

Example

This example illustrates some of the ways you can use get to return property values for the serial port object s.

```
s = serial('COM1');
out1 = get(s);
out2 = get(s, {'BaudRate', 'DataBits'});
get(s, 'Parity')
ans =
none
```

See Also

Functions

set

getappdata

Purpose	Get value of application-defined data
Syntax	<code>val ue = getappdata(h, name)</code> <code>val ues = getappdata(h)</code>
Description	<code>val ue = getappdata(h, name)</code> gets the value of the application-defined data with the name specified by name, in the object with the handle h. If the application-defined data does not exist, MATLAB returns an empty matrix in <code>val ue</code> . <code>val ue = getappdata(h)</code> returns all application-defined data for the object with handle h.
See Also	<code>setappdata</code> , <code>rmapappdata</code> , <code>isappdata</code>

Purpose Get environment variable

Syntax

```
getenv 'name'  
N = getenv('name')
```

Description `getenv 'name'` searches the underlying operating system's environment list for a string of the form `name=valu`e, where `name` is the input string. If found, MATLAB returns the string, `valu`e. If the specified name cannot be found, an empty matrix is returned.

`N = getenv('name')` returns `valu`e to the variable, `N`.

Examples

```
os = getenv('OS')  
  
os =  
Wi ndows_NT
```

See Also `computer`, `pwd`, `ver`, `path`

getfield

Purpose	Get field of structure array
Syntax	<pre>f = getfield(s, 'field') f = getfield(s, {i,j}, 'field', {k})</pre>
Description	<p><code>f = getfield(s, 'field')</code>, where <code>s</code> is a 1-by-1 structure, returns the contents of the specified field. This is equivalent to the syntax <code>f = s.field</code>.</p> <p>If <code>s</code> is a structure having dimensions greater than 1-by-1, <code>getfield</code> returns the first of all output values requested in the call. That is, for structure array <code>s(m,n)</code>, <code>getfield</code> returns <code>f = s(1,1).field</code>.</p> <p><code>f = getfield(s, {i,j}, 'field', {k})</code> returns the contents of the specified field. This is equivalent to the syntax <code>f = s(i,j).field(k)</code>. All subscripts must be passed as cell arrays—that is, they must be enclosed in curly braces (similar to <code>{i,j}</code> and <code>{k}</code> above). Pass field references as strings.</p>
Examples	<p>Given the structure</p> <pre>mystr(1, 1).name = 'alice'; mystr(1, 1).ID = 0; mystr(2, 1).name = 'gertrude'; mystr(2, 1).ID = 1</pre> <p>Then the command <code>f = getfield(mystr, {2, 1}, 'name')</code> yields</p> <pre>f = gertrude</pre> <p>To list the contents of all name (or other) fields, embed <code>getfield</code> in a loop.</p> <pre>for k = 1:2 name{k} = getfield(mystr, {k, 1}, 'name'); end name name = 'alice' 'gertrude'</pre>

The following example starts out by creating a structure using the standard structure syntax. It then reads the fields of the structure using `getfield` with variable and quoted field names and additional subscripting arguments.

```
class = 5;      student = 'John_Doe';
grades(class).John_Doe.Math(10, 21:30) = ...
[85, 89, 76, 93, 85, 91, 68, 84, 95, 73];
```

Use `getfield` to access the structure fields.

```
getfield(grades, {class}, student, 'Math', {10, 21:30})
```

```
ans =
```

```
85    89    76    93    85    91    68    84    95    73
```

See Also

`setfield`, `rmfield`, `fieldnames`

getframe

Purpose	Get movie frame
Syntax	<pre>F = getframe F = getframe(h) F = getframe(h, rect) [X, Map] = getframe(...)</pre>
Description	<p><code>getframe</code> returns a movie frame. The frame is a snapshot (pixmap) of the current axes or figure.</p> <p><code>F = getframe</code> gets a frame from the current axes.</p> <p><code>F = getframe(h)</code> gets a frame from the figure or axes identified by the handle <code>h</code>.</p> <p><code>F = getframe(h, rect)</code> specifies a rectangular area from which to copy the pixmap. <code>rect</code> is relative to the lower-left corner of the figure or axes <code>h</code>, in pixel units. <code>rect</code> is a four-element vector in the form <code>[left bottom width height]</code>, where <code>width</code> and <code>height</code> define the dimensions of the rectangle.</p> <p><code>F = getframe(...)</code> returns a movie frame, which is a structure having two fields:</p> <ul style="list-style-type: none">• <code>cdata</code> – The image data stored as a matrix of <code>uint8</code> values. The dimensions of <code>F.cdata</code> are <code>height-by-width-by-3</code>.• <code>colormap</code> – The colormap stored as an <code>n-by-3</code> matrix of doubles. <code>F.colormap</code> is empty on true color systems. <p>To capture an image, use this approach:</p> <pre>F = getframe(gcf); image(F.cdata) colormap(F.colormap)</pre> <p><code>[X, Map] = getframe(...)</code> returns the frame as an indexed image matrix <code>X</code> and a colormap <code>Map</code>. This version is obsolete and is supported only for compatibility with earlier version of MATLAB. Since indexed images cannot always capture true color displays, you should use the single output argument form of <code>getframe</code>. To write code that is compatible with earlier version of</p>

MATLAB and that can take advantage of true color support, use the following approach:

```
F = getframe(gcf);
[X, Map] = frame2im(f);
imshow(X, Map)
```

Remarks

Usually, `getframe` is used in a for loop to assemble an array of movie frames for playback using `movie`. For example,

```
for j = 1:n
    plotting commands
    F(j) = getframe;
end
movie(F)
```

To create movies that are compatible with earlier versions of MATLAB (before Release 11/MATLAB 5.3) use this approach:

```
M = movie(n);
for j = 1:n
    plotting commands
    M(:,j) = getframe;
end
movie(M)
```

Capture Regions

Note that `F = getframe;` returns the contents of the current axes, exclusive of the axis labels, title, or tick labels. `F = getframe(gcf);` captures the entire interior of the current figure window. To capture the figure window menu, use the form `F = getframe(h, rect)` with a rectangle sized to include the menu.

Examples

Make the peaks function vibrate.

```
Z = peaks; surf(Z)
axis tight
set(gca, 'nextplot', 'replacechildren');
for j = 1:20
    surf(sin(2*pi*j/20)*Z, Z)
    F(j) = getframe;
end
```

getframe

```
movie(F, 20) % Play the movie twenty times
```

See Also

[frame2im](#), [image](#), [im2frame](#), [movie](#), [movien](#)

Purpose	Input data using the mouse
Syntax	$[x, y] = \text{ginput}(n)$ $[x, y] = \text{ginput}$ $[x, y, button] = \text{ginput}(\dots)$
Description	<code>ginput</code> enables you to select points from the figure using the mouse or arrow keys for cursor positioning. The figure must have focus before <code>ginput</code> receives input. $[x, y] = \text{ginput}(n)$ enables you to select n points from the current axes and returns the x - and y -coordinates in the column vectors x and y , respectively. You can press the Return key to terminate the input before entering n points. $[x, y] = \text{ginput}$ gathers an unlimited number of points until you press the Return key. $[x, y, button] = \text{ginput}(\dots)$ returns the x -coordinates, the y -coordinates, and the button or key designation. <code>button</code> is a vector of integers indicating which mouse buttons you pressed (1 for left, 2 for middle, 3 for right), or ASCII numbers indicating which keys on the keyboard you pressed.
Remarks	If you select points from multiple axes, the results you get are relative to those axes coordinates systems.
Examples	Pick 10 two-dimensional points from the figure window. $[x, y] = \text{ginput}(10)$ Position the cursor with the mouse (or the arrow keys on terminals without a mouse, such as Tektronix emulators). Enter data points by pressing a mouse button or a key on the keyboard. To terminate input before entering 10 points, press the Return key.
See Also	<code>gtext</code>

global

Purpose	Define a global variable
Syntax	<code>global X Y Z</code>
Description	<code>global X Y Z</code> defines X, Y, and Z as global in scope. Ordinarily, each MATLAB function, defined by an M-file, has its own local variables, which are separate from those of other functions, and from those of the base workspace. However, if several functions, and possibly the base workspace, all declare a particular name as global, they all share a single copy of that variable. Any assignment to that variable, in any function, is available to all the functions declaring it global. If the global variable does not exist the first time you issue the <code>global</code> statement, it is initialized to the empty matrix. If a variable with the same name as the global variable already exists in the current workspace, MATLAB issues a warning and changes the value of that variable to match the global.
Remarks	Use <code>clear global variable</code> to clear a global variable from the global workspace. Use <code>clear variable</code> to clear the global link from the current workspace without affecting the value of the global. To use a global within a callback, declare the global, use it, then clear the global link from the workspace. This avoids declaring the global after it has been referenced. For example,
	<pre>ui control ('style', 'pushbutton', 'CallBack', ... 'global MY_GLOBAL, disp(MY_GLOBAL), MY_GLOBAL = MY_GLOBAL+1, clear MY_GLOBAL',... 'string', 'count')</pre>
	There is no function form of the global command (i.e., you cannot use parentheses and quote the variable names).
Examples	Here is the code for the functions <code>tic</code> and <code>toc</code> (some comments abridged). These functions manipulate a stopwatch-like timer. The global variable <code>TICTOC</code> is shared by the two functions, but it is invisible in the base workspace or in any other functions that do not declare it.
	<pre>function tic</pre>

```
%      TIC Start a stopwatch timer.  
%      TIC; any stuff; TOC  
%      prints the time required.  
%      See also: TOC, CLOCK.  
global TICTOC  
TICTOC = clock;  
  
function t = toc  
%      TOC Read the stopwatch timer.  
%      TOC prints the elapsed time since TIC was used.  
%      t = TOC; saves elapsed time in t, does not print.  
%      See also: TIC, ETIME.  
global TICTOC  
if nargin < 1  
    elapsed_time = etime(clock, TICTOC)  
else  
    t = etime(clock, TICTOC);  
end
```

See Also

clear, isglobal, who

gmres

Purpose	Generalized Minimum Residual method (with restarts)
Syntax	<pre>x = gmres(A, b) gmres(A, b, restart) gmres(A, b, restart, tol) gmres(A, b, restart, tol, maxit) gmres(A, b, restart, tol, maxit, M) gmres(A, b, restart, tol, maxit, M1, M2) gmres(A, b, restart, tol, maxit, M1, M2, x0) gmres(afun, b, restart, tol, maxit, m1fun, m2fun, x0, p1, p2, ...) [x, flag] = gmres(A, b, ...) [x, flag, relres] = gmres(A, b, ...) [x, flag, relres, iter] = gmres(A, b, ...) [x, flag, relres, iter, resvec] = gmres(A, b, ...)</pre>
Description	<p><code>x = gmres(A, b)</code> attempts to solve the system of linear equations $A^*x = b$ for <code>x</code>. The n-by-n coefficient matrix <code>A</code> must be square and the column vector <code>b</code> must have length n. <code>A</code> can be a function <code>afun</code> such that <code>afun(x)</code> returns A^*x. For this syntax, <code>gmres</code> does not restart; the maximum number of iterations is <code>min(n, 10)</code>.</p> <p>If <code>gmres</code> converges, a message to that effect is displayed. If <code>gmres</code> fails to converge after the maximum number of iterations or halts for any reason, a warning message is printed displaying the relative residual $\text{norm}(b - A^*x) / \text{norm}(b)$ and the iteration number at which the method stopped or failed.</p> <p><code>gmres(A, b, restart)</code> restarts the method every <code>restart</code> inner iterations. The maximum number of outer iterations is <code>min(n/restart, 10)</code>. The maximum number of total iterations is <code>restart * min(n/restart, 10)</code>. If <code>restart</code> is <code>n</code> or <code>[]</code>, then <code>gmres</code> does not restart and the maximum number of total iterations is <code>min(n, 10)</code>.</p> <p><code>gmres(A, b, restart, tol)</code> specifies the tolerance of the method. If <code>tol</code> is <code>[]</code>, then <code>gmres</code> uses the default, <code>1e-6</code>.</p> <p><code>gmres(A, b, restart, tol, maxit)</code> specifies the maximum number of outer iterations, i.e., the total number of iterations does not exceed <code>restart * maxit</code>. If <code>maxit</code> is <code>[]</code> then <code>gmres</code> uses the default, <code>min(n/restart, 10)</code>. If <code>restart</code> is <code>n</code></p>

or [], then the maximum number of total iterations is `maxit` (instead of `restart * maxit`).

`gmres(A, b, restart, tol, maxit, M)` and
`gmres(A, b, restart, tol, maxit, M1, M2)` use preconditioner `M` or `M = M1 * M2` and effectively solve the system $\text{inv}(M)^* A^* x = \text{inv}(M)^* b$ for `x`. If `M` is [] then `gmres` applies no preconditioner. `M` can be a function that returns `M\cdot x`.

`gmres(A, b, restart, tol, maxit, M1, M2, x0)` specifies the first initial guess. If `x0` is [], then `gmres` uses the default, an all-zero vector.

`gmres(afun, b, restart, tol, maxit, m1fun, m2fun, x0, p1, p2, ...)` passes parameters to functions `afun(x, p1, p2, ...)`, `m1fun(x, p1, p2, ...)`, and `m2fun(x, p1, p2, ...)`.

`[x, flag] = gmres(A, b, ...)` also returns a convergence flag:

`flag = 0` `gmres` converged to the desired tolerance `tol` within `maxit` outer iterations.

`flag = 1` `gmres` iterated `maxit` times but did not converge.

`flag = 2` Preconditioner `M` was ill-conditioned.

`flag = 3` `gmres` stagnated. (Two consecutive iterates were the same.)

Whenever `flag` is not 0, the solution `x` returned is that with minimal norm residual computed over all the iterations. No messages are displayed if the `flag` output is specified.

`[x, flag, relres] = gmres(A, b, ...)` also returns the relative residual $\text{norm}(b - A^* x) / \text{norm}(b)$. If `flag` is 0, `relres <= tol`.

`[x, flag, relres, iter] = gmres(A, b, ...)` also returns both the outer and inner iteration numbers at which `x` was computed, where
 $0 \leq \text{iter}(1) \leq \text{maxit}$ and $0 \leq \text{iter}(2) \leq \text{restart}$.

`[x, flag, relres, iter, resvec] = gmres(A, b, ...)` also returns a vector of the residual norms at each inner iteration, including $\text{norm}(b - A^* x_0)$.

gmres

Examples

Example 1.

```
A = gallery('wilk', 21);
b = sum(A, 2);
tol = 1e-12;
maxit = 15;
M1 = diag([10:-1:1 1 1:10]);

x = gmres(A, b, 10, tol, maxit, M1, [], []);
gmres(10) converged at iteration 2(10) to a solution with relative
residual 1.9e-013
```

Alternatively, use this matrix-vector product function

```
function y = afun(x, n)
y = [0;
      x(1:n-1)' + [((n-1)/2:-1:0)';
      (1:(n-1)/2)'] .* x + [x(2:n);
      0];
```

and this preconditioner backsolve function

```
function y = mfun(r, n)
y = r ./ [((n-1)/2:-1:1)'; 1; (1:(n-1)/2)'];
```

as inputs to gmres

```
x1 = gmres(@afun, b, 10, tol, maxit, @mfun, [], [], 21);
```

Note that both afun and mfun must accept the gmres extra input n=21.

Example 2.

```
load west0479
A = west0479
b = sum(A, 2)
[x, flag] = gmres(A, b, 5)
```


flag is 1 because gmres does not converge to the default tolerance 1e-6 within the default 10 outer iterations.

```
[L1, U1] = luinc(A, 1e-5);
[x1, flag1] = gmres(A, b, 5, 1e-6, 5, L1, U1);
```

`f1 ag1` is 2 because the upper triangular `U1` has a zero on its diagonal, and `gmres` fails in the first iteration when it tries to solve a system such as `U1*y = r` for `y` using backslash.

```
[L2, U2] = luinc(A, 1e- 6);
tol = 1e- 15;
[x4, flag4, relres4, iter4, resvec4] = gmres(A, b, 4, tol, 5, L2, U2);
[x6, flag6, relres6, iter6, resvec6] = gmres(A, b, 6, tol, 3, L2, U2);
[x8, flag8, relres8, iter8, resvec8] = gmres(A, b, 8, tol, 3, L2, U2);
```

`flag4`, `flag6`, and `flag8` are all 0 because `gmres` converged when restarted at iterations 4, 6, and 8 while preconditioned by the incomplete LU factorization with a drop tolerance of `1e- 6`. This is verified by the plots of outer iteration number against relative residual. A combined plot of all three clearly shows the restarting at iterations 4 and 6. The total number of iterations computed may be more for lower values of restart, but the number of length `n` vectors stored is fewer, and the amount of work done in the method decreases proportionally.



See Also

`bicg`, `bicgstab`, `cgs`, `lqr`, `luinc`, `minres`, `pcg`, `qmr`, `symmlq`
`@ (function handle)`, `\ (backslash)`


References

- [1] Barrett, R., M. Berry, T. F. Chan, et al., *Templates for the Solution of Linear Systems: Building Blocks for Iterative Methods*, SIAM, Philadelphia, 1994.
- [2] Saad, Youcef and Martin H. Schultz, "GMRES: A generalized minimal residual algorithm for solving nonsymmetric linear systems", *SIAM J. Sci. Stat. Comput.*, July 1986, Vol. 7, No. 3, pp. 856-869.

Purpose	Plot set of nodes using an adjacency matrix
Synopsis	<code>gplot(A, Coordinates)</code> <code>gplot(A, Coordinates, LineSpec)</code>
Description	The <code>gplot</code> function graphs a set of coordinates using an adjacency matrix. <code>gplot(A, Coordinates)</code> plots a graph of the nodes defined in <code>Coordinates</code> according to the n -by- n adjacency matrix <code>A</code> , where n is the number of nodes. <code>Coordinates</code> is an n -by-2 or an n -by-3 matrix, where n is the number of nodes and each coordinate pair or triple represents one node.
	<code>gplot(A, Coordinates, LineSpec)</code> plots the nodes using the line type, marker symbol, and color specified by <code>LineSpec</code> .
Remarks	For two-dimensional data, <code>Coordinates(i, :) = [x(i) y(i)]</code> denotes node i , and <code>Coordinates(j, :) = [x(j) y(j)]</code> denotes node j . If node i and node j are joined, <code>A(i,j)</code> or <code>A(j,i)</code> are nonzero; otherwise, <code>A(i,j)</code> and <code>A(j,i)</code> are zero.
Examples	To draw half of a Bucky ball with asterisks at each node: <code>k = 1:30;</code> <code>[B, XY] = bucky;</code> <code>gplot(B(k, k), XY(k, :), '-*')</code>

gplot

axis square



See Also

[LineSpec](#), [sparse](#), [spy](#)

Purpose	Numerical gradient
Syntax	$\text{FX} = \text{gradient}(F)$ $[\text{FX}, \text{FY}] = \text{gradient}(F)$ $[\text{Fx}, \text{Fy}, \text{Fz}, \dots] = \text{gradient}(F)$ $[\dots] = \text{gradient}(F, h)$ $[\dots] = \text{gradient}(F, h1, h2, \dots)$
Definition	The <i>gradient</i> of a function of two variables, $F(x, y)$, is defined as
	$\nabla F = \frac{\partial F}{\partial x} \hat{i} + \frac{\partial F}{\partial y} \hat{j}$
	and can be thought of as a collection of vectors pointing in the direction of increasing values of F . In MATLAB, numerical gradients (differences) can be computed for functions with any number of variables. For a function of N variables, $F(x, y, z, \dots)$,
	$\nabla F = \frac{\partial F}{\partial x} \hat{i} + \frac{\partial F}{\partial y} \hat{j} + \frac{\partial F}{\partial z} \hat{k} + \dots$
Description	<p>$\text{FX} = \text{gradient}(F)$ where F is a vector returns the one-dimensional numerical gradient of F. FX corresponds to $\partial F / \partial x$, the differences in the x direction.</p> <p>$[\text{FX}, \text{FY}] = \text{gradient}(F)$ where F is a matrix returns the x and y components of the two-dimensional numerical gradient. FX corresponds to $\partial F / \partial x$, the differences in the x (column) direction. FY corresponds to $\partial F / \partial y$, the differences in the y (row) direction. The spacing between points in each direction is assumed to be one.</p> <p>$[\text{FX}, \text{FY}, \text{FZ}, \dots] = \text{gradient}(F)$ where F has N dimensions returns the N components of the gradient of F. There are two ways to control the spacing between values in F:</p> <ul style="list-style-type: none"> • A single spacing value, h, specifies the spacing between points in every direction. • N spacing values ($h1, h2, \dots$) specifies the spacing for each dimension. Scalar spacing parameters specify a constant spacing for each dimension. Vector parameters specify the coordinates of the values along corresponding

gradient

dimensions of F. In this case, the length of the vector must match the size of the corresponding dimension.

[. . .] = gradient (F, h) where h is a scalar uses h as the spacing between points in each direction.


[. . .] = gradient (F, h1, h2, . . .) with N spacing parameters specifies the spacing for each dimension of F.

Examples

The statements

```
v = -2:0.2:2;  
[x, y] = meshgrid(v);  
z = x .* exp(-x.^2 - y.^2);  
[px, py] = gradient(z, .2, .2);  
contour(v, v, z), hold on, quiver(px, py), hold off
```

produce



Given,

```
F(:,:,1) = magic(3); F(:,:,2) = pascal(3);  
gradient(F) takes dx = dy = dz = 1.
```

[PX, PY, PZ] = gradient(F, 0.2, 0.1, 0.2) takes dx = 0.2, dy = 0.1, and dz = 0.2.

See Also

del2, diff

graymon

Purpose	Set default figure properties for grayscale monitors
Syntax	graymon
Description	graymon sets defaults for graphics properties to produce more legible displays for grayscale monitors.
See Also	axes, figure

Purpose	Grid lines for two- and three-dimensional plots
Syntax	<code>grid on</code> <code>grid off</code> <code>grid minor</code> <code>grid</code> <code>grid(axes_handle, ...)</code>
Description	The <code>grid</code> function turns the current axes' grid lines on and off. <code>grid on</code> adds major grid lines to the current axes. <code>grid off</code> removes major and minor grid lines from the current axes. <code>grid</code> toggles the major grid visibility state. <code>grid(axes_handle, ...)</code> uses the axes specified by <code>axes_handle</code> instead of the current axes.
Algorithm	<code>grid</code> sets the <code>XGrid</code> , <code>YGrid</code> , and <code>ZGrid</code> properties of the axes. <code>grid minor</code> sets the <code>XGridMinor</code> , <code>YGridMinor</code> , and <code>ZGridMinor</code> properties of the axes. You can set the grid lines for just one axis using the <code>set</code> command and the <code>individual</code> property. For example,
	<pre>set(axes_handle, 'XGrid', 'on')</pre> turns on only x-axis grid lines.
See Also	<code>axes</code> , <code>set</code> The properties of axes objects.

griddata

Purpose	Data gridding								
Syntax	<pre>ZI = griddata(x, y, z, XI, YI) [XI, YI, ZI] = griddata(x, y, z, xi, yi) [...] = griddata(..., method)</pre>								
Description	<p><code>ZI = griddata(x, y, z, XI, YI)</code> fits a surface of the form $z = f(x, y)$ to the data in the (usually) nonuniformly spaced vectors (x, y, z). <code>griddata</code> interpolates this surface at the points specified by (XI, YI) to produce <code>ZI</code>. The surface always passes through the data points. <code>XI</code> and <code>YI</code> usually form a uniform grid (as produced by <code>meshgrid</code>).</p> <p><code>XI</code> can be a row vector, in which case it specifies a matrix with constant columns. Similarly, <code>YI</code> can be a column vector, and it specifies a matrix with constant rows.</p> <p><code>[XI, YI, ZI] = griddata(x, y, z, xi, yi)</code> returns the interpolated matrix <code>ZI</code> as above, and also returns the matrices <code>XI</code> and <code>YI</code> formed from row vector <code>xi</code> and column vector <code>yi</code>. These latter are the same as the matrices returned by <code>meshgrid</code>.</p> <p><code>[...] = griddata(..., method)</code> uses the specified interpolation method:</p> <table><tr><td>'linear'</td><td>Triangle-based linear interpolation (default)</td></tr><tr><td>'cubic'</td><td>Triangle-based cubic interpolation</td></tr><tr><td>'nearest'</td><td>Nearest neighbor interpolation</td></tr><tr><td>'v4'</td><td>MATLAB 4 <code>griddata</code> method</td></tr></table> <p>The <code>method</code> defines the type of surface fit to the data. The '<code>cubic</code>' and '<code>v4</code>' methods produce smooth surfaces while '<code>linear</code>' and '<code>nearest</code>' have discontinuities in the first and zero'th derivatives, respectively. All the methods except '<code>v4</code>' are based on a Delaunay triangulation of the data.</p>	'linear'	Triangle-based linear interpolation (default)	'cubic'	Triangle-based cubic interpolation	'nearest'	Nearest neighbor interpolation	'v4'	MATLAB 4 <code>griddata</code> method
'linear'	Triangle-based linear interpolation (default)								
'cubic'	Triangle-based cubic interpolation								
'nearest'	Nearest neighbor interpolation								
'v4'	MATLAB 4 <code>griddata</code> method								

Note Occasionally, `griddata` may return points on or very near the convex hull of the data as Nans. This is because roundoff in the computations

sometimes makes it difficult to determine if a point near the boundary is in the convex hull.

Remarks

XI and YI can be matrices, in which case griddata returns the values for the corresponding points (XI(i,j), YI(i,j)). Alternatively, you can pass in the row and column vectors xi and yi, respectively. In this case, griddata interprets these vectors as if they were matrices produced by the command meshgrid(xi,yi).

Algorithm

The griddata(. . . , 'v4') command uses the method documented in [1]. The other methods are based on Delaunay triangulation (see delaunay).

Examples

Sample a function at 100 random points between ± 2.0 :

```
rand('seed', 0)
x = rand(100, 1) * 4 - 2; y = rand(100, 1) * 4 - 2;
z = x.*exp(-x.^2-y.^2);
```


x, y, and z are now vectors containing nonuniformly sampled data. Define a regular grid, and grid the data to it:

```
ti = -2:.25:2;
[XI, YI] = meshgrid(ti, ti);
ZI = griddata(x, y, z, XI, YI);
```

Plot the gridded data along with the nonuniform data points used to generate it:

```
mesh(XI, YI, ZI), hold
plot3(x, y, z, 'o'), hold off
```

griddata



See Also

`del a unay`, `griddat a3`, `griddat an`, `interp2`, `meshgrid`

References

[1] Sandwell, David T., "Biharmonic Spline Interpolation of GEOS-3 and SEASAT Altimeter Data", *Geophysical Research Letters*, 2, 139-142, 1987.

[2] Watson, David E., *Contouring: A Guide to the Analysis and Display of Spatial Data*, Tarrytown, NY: Pergamon (Elsevier Science, Inc.): 1992.

Purpose	Data gridding and hypersurface fitting for 3-D data				
Syntax	<pre>w = griddata3(x, y, z, v, xi, yi, zi) w = griddata3(. . . , 'method')</pre>				
Description	<p><code>w = griddata3(x, y, z, v, xi, yi, zi)</code> fits a hypersurface of the form $w = f(x, y, z)$ to the data in the (usually) nonuniformly spaced vectors <code>(x, y, z, v)</code>. <code>griddata3</code> interpolates this hypersurface at the points specified by <code>(xi, yi, zi)</code> to produce <code>w</code>. <code>w</code> is the same size as <code>xi</code>, <code>yi</code>, and <code>zi</code>.</p> <p><code>(xi, yi, zi)</code> is usually a uniform grid (as produced by <code>meshgrid</code>) and is where <code>griddata3</code> gets its name.</p> <p><code>w = griddata3(. . . , 'method')</code> defines the type of surface that is fit to the data, where '<code>method</code>' is either:</p> <table> <tr> <td>'linear'</td> <td>Tesselation-based linear interpolation (default)</td> </tr> <tr> <td>'nearest'</td> <td>Nearest neighbor interpolation</td> </tr> </table>	'linear'	Tesselation-based linear interpolation (default)	'nearest'	Nearest neighbor interpolation
'linear'	Tesselation-based linear interpolation (default)				
'nearest'	Nearest neighbor interpolation				

Note All the methods are based on a Delaunay triangulation of the data that uses `qhull` [2]. For information about `qhull`, see <http://www.geom.umn.edu/software/qhull/>. For copyright information, see <http://www.geom.umn.edu/software/downl oad/COPYING.html>.

See Also	<code>delaunayn</code> , <code>griddata</code> , <code>griddatan</code> , <code>meshgrid</code>
Reference	<p>[1] Barber, C. B., D.P. Dobkin, and H.T. Huhdanpaa, "The Quickhull Algorithm for Convex Hulls," <i>ACM Transactions on Mathematical Software</i>, Vol. 22, No. 4, Dec. 1996, p. 469-483. Available in HTML format at http://www.acm.org/pubs/citations/journals/toms/1996-22-4/p469-barber/ and in PostScript format at ftp://geom.umn.edu/pub/software/qhull-96.ps.</p> <p>[2] National Science and Technology Research Center for Computation and Visualization of Geometric Structures (The Geometry Center), University of Minnesota. 1993.</p>

griddatan

Purpose	Data gridding and hypersurface fitting (dimension ≥ 2)
Syntax	<pre>yi = griddatan(X, y, xi) yi = griddatan(..., 'method')</pre>
Description	<p><code>yi = griddatan(X, y, xi)</code> fits a hyper-surface of the form $y = f(X)$ to the data in the (usually) nonuniformly-spaced vectors (X, y). <code>griddatan</code> interpolates this hyper-surface at the points specified by <code>xi</code> to produce <code>yi</code>. <code>xi</code> can be nonuniform.</p> <p><code>X</code> is of dimension m-by-n, representing m points in n-D space. <code>y</code> is of dimension m-by-1, representing m values of the hyper-surface $f(X)$. <code>xi</code> is a vector of size p-by-n, representing p points in the n-D space whose surface value is to be fitted. <code>yi</code> is a vector of length p approximating the values $f(xi)$. The hypersurface always goes through the data points (X, y). <code>xi</code> is usually a uniform grid (as produced by <code>meshgrid</code>).</p> <p><code>[...] = griddatan(..., 'method')</code> defines the type of surface fit to the data, where '<code>method</code>' is one of:</p> <ul style="list-style-type: none">'linear' Tessellation-based linear interpolation (default)'nearest' Nearest neighbor interpolation <p>All the methods are based on a Delaunay tessellation of the data.</p>
Note	<p><code>griddatan</code> calls <code>delaunayn</code>, which is based on <code>qhull1</code> [2]. For information about <code>qhull1</code>, see http://www.geom.umn.edu/software/qhull1/. For copyright information, see http://www.geom.umn.edu/software/downl/COPYING.html.</p>
See Also	<code>delaunayn</code> , <code>griddata</code> , <code>griddata3</code> , <code>meshgrid</code>
Reference	[1] Barber, C. B., D.P. Dobkin, and H.T. Huhtanpaa, "The Quickhull Algorithm for Convex Hulls," <i>ACM Transactions on Mathematical Software</i> , Vol. 22, No. 4, Dec. 1996, p. 469-483. Available in HTML format at http://www.acm.org/pubs/

ci tati ons/j ournal s/toms/1996- 22- 4/p469- barber/ and in PostScript format
at ftp: //geom. umn. edu/pub/software/qhull - 96. ps.

[2] National Science and Technology Research Center for Computation and
Visualization of Geometric Structures (The Geometry Center), University of
Minnesota. 1993.

gsvd

Purpose	Generalized singular value decomposition
Syntax	$[U, V, X, C, S] = \text{gsvd}(A, B)$ $[U, V, X, C, S] = \text{gsvd}(A, B, 0)$ $\text{sigma} = \text{gsvd}(A, B)$
Description	$[U, V, X, C, S] = \text{gsvd}(A, B)$ returns unitary matrices U and V , a (usually) square matrix X , and nonnegative diagonal matrices C and S so that $A = U * C * X'$ $B = V * S * X'$ $C' * C + S' * S = I$ <p>A and B must have the same number of columns, but may have different numbers of rows. If A is m-by-p and B is n-by-p, then U is m-by-m, V is n-by-n and X is p-by-q where $q = \min(m, n, p)$.</p> <p>$\text{sigma} = \text{gsvd}(A, B)$ returns the vector of generalized singular values, $\text{sqrt}(\text{diag}(C' * C) ./ \text{diag}(S' * S))$.</p> <p>The nonzero elements of S are always on its main diagonal. If $m \geq p$ the nonzero elements of C are also on its main diagonal. But if $m < p$, the nonzero diagonal of C is $\text{diag}(C, p-m)$. This allows the diagonal elements to be ordered so that the generalized singular values are nondecreasing.</p> <p>$\text{gsvd}(A, B, 0)$, with three input arguments and either m or $n \geq p$, produces the “economy-sized” decomposition where the resulting U and V have at most p columns, and C and S have at most p rows. The generalized singular values are $\text{diag}(C) ./ \text{diag}(S)$.</p> <p>When B is square and nonsingular, the generalized singular values, $\text{gsvd}(A, B)$, are equal to the ordinary singular values, $\text{svd}(A/B)$, but they are sorted in the opposite order. Their reciprocals are $\text{gsvd}(B, A)$.</p> <p>In this formulation of the gsvd, no assumptions are made about the individual ranks of A or B. The matrix X has full rank if and only if the matrix $[A; B]$ has full rank. In fact, $\text{svd}(X)$ and $\text{cond}(X)$ are equal to $\text{svd}([A; B])$ and $\text{cond}([A; B])$. Other formulations, eg. G. Golub and C. Van Loan [1], require that $\text{nul}(A)$ and $\text{nul}(B)$ do not overlap and replace X by $\text{inv}(X)$ or $\text{inv}(X')$.</p> <p>Note, however, that when $\text{nul}(A)$ and $\text{nul}(B)$ do overlap, the nonzero elements of C and S are not uniquely determined.</p>

Examples**Example 1.** The matrices have at least as many rows as columns.

A = reshape(1: 15, 5, 3)

B = magic(3)

A =

1	6	11
2	7	12
3	8	13
4	9	14
5	10	15

B =

8	1	6
3	5	7
4	9	2

The statement

[U, V, X, C, S] = gsvd(A, B)

produces a 5-by-5 orthogonal U, a 3-by-3 orthogonal V, a 3-by-3 nonsingular X,

X =

2. 8284	- 9. 3761	- 6. 9346
- 5. 6569	- 8. 3071	- 18. 3301
2. 8284	- 7. 2381	- 29. 7256

and

C =

0. 0000	0	0
0	0. 3155	0
0	0	0. 9807
0	0	0
0	0	0

S =

1. 0000	0	0
0	0. 9489	0
0	0	0. 1957

Since A is rank deficient, the first diagonal element of C is zero.

gsvd

The economy sized decomposition,

$$[U, V, X, C, S] = \text{gsvd}(A, B, 0)$$

produces a 5-by-3 matrix U and a 3-by-3 matrix C.

U =

$$\begin{matrix} 0.5700 & -0.6457 & -0.4279 \\ -0.7455 & -0.3296 & -0.4375 \\ -0.1702 & -0.0135 & -0.4470 \\ 0.2966 & 0.3026 & -0.4566 \\ 0.0490 & 0.6187 & -0.4661 \end{matrix}$$

C =

$$\begin{matrix} 0.0000 & 0 & 0 \\ 0 & 0.3155 & 0 \\ 0 & 0 & 0.9807 \end{matrix}$$

The other three matrices, V, X, and S are the same as those obtained with the full decomposition.

The generalized singular values are the ratios of the diagonal elements of C and S.

$$\text{sigma} = \text{gsvd}(A, B)$$

$$\begin{matrix} \text{sigma} = \\ 0.0000 \\ 0.3325 \\ 5.0123 \end{matrix}$$

These values are a reordering of the ordinary singular values

$$\text{svd}(A/B)$$

$$\begin{matrix} \text{ans} = \\ 5.0123 \\ 0.3325 \\ 0.0000 \end{matrix}$$

Example 2. The matrices have at least as many columns as rows.

$$A = \text{reshape}(1:15, 3, 5)$$

$$B = \text{magic}(5)$$

A =

1	4	7	10	13
2	5	8	11	14
3	6	9	12	15

B =

17	24	1	8	15
23	5	7	14	16
4	6	13	20	22
10	12	19	21	3
11	18	25	2	9

The statement

[U, V, X, C, S] = gsvd(A, B)

produces a 3-by-3 orthogonal U, a 5-by-5 orthogonal V, a 5-by-5 nonsingular X and

C =

0	0	0. 0000	0	0
0	0	0	0. 0439	0
0	0	0	0	0. 7432

S =

1. 0000	0	0	0	0
0	1. 0000	0	0	0
0	0	1. 0000	0	0
0	0	0	0. 9990	0
0	0	0	0	0. 6690

In this situation, the nonzero diagonal of C is $\text{diag}(C, 2)$. The generalized singular values include three zeros.

sigma = gsvd(A, B)

gsvd

```
sigma =
    0
    0
    0. 0000
    0. 0439
    1. 1109
```

Reversing the roles of A and B reciprocates these values, producing two infinities.

```
gsvd(B, A)
ans =
    1. 0e+016 *
        0. 0000
        0. 0000
        4. 4126
        Inf
        Inf
```

Algorithm

The generalized singular value decomposition uses the C-S decomposition described in [1], as well as the built-in svd and qr functions. The C-S decomposition is implemented in a subfunction in the gsvd M-file.

Diagnostics

The only warning or error message produced by gsvd itself occurs when the two input arguments do not have the same number of columns.

See Also

qr, svd

References

[1] Golub, Gene H. and Charles Van Loan, *Matrix Computations*, Third Edition, Johns Hopkins University Press, Baltimore, 1996

Purpose	Mouse placement of text in two-dimensional view
Syntax	<code>gtext('string')</code> <code>h = gtext('string')</code>
Description	<p><code>gtext('string')</code> displays a text string in the current figure window after you select a location with the mouse.</p> <p><code>gtext('string')</code> waits for you to press a mouse button or keyboard key while the pointer is within a figure window. Pressing a mouse button or any key places '<i>string</i>' on the plot at the selected location.</p> <p><code>h = gtext('string')</code> returns the handle to a text graphics object after you place '<i>string</i>' on the plot at the selected location.</p>
Remarks	As you move the pointer into a figure window, the pointer becomes a crosshair to indicate that <code>gtext</code> is waiting for you to select a location. <code>gtext</code> uses the functions <code>ginput</code> and <code>text</code> .
Examples	Place a label on the current plot: <code>gtext('Note this divergence!')</code>
See Also	<code>ginput</code> , <code>text</code>

guidata

Purpose	Store or retrieve application data
Syntax	<pre>gui data(obj ect_handl e, data) data = gui data(obj ect_handl e)</pre>
Description	<p><code>gui data(obj ect_handl e, data)</code> stores the variable <code>data</code> in the figure's application data. If <code>obj ect_handl e</code> is not a figure handle, then the object's parent figure is used. <code>data</code> can be any MATLAB variable, but is typically a structure, which enables you to add new fields as required.</p> <p>Note that there can be only one variable stored in a figure's application data at any time. Subsequent calls to <code>gui data(obj ect_handl e, data)</code> overwrite the previously created version of <code>data</code>. See the Examples section for information on how to use this function.</p> <p><code>data = gui data(obj ect_handl e)</code> returns previously stored data, or an empty matrix if nothing has been stored.</p> <p><code>gui dat a</code> provides application developers with a convenient interface to a figure's application data:</p> <ul style="list-style-type: none">• You do not need to create and maintain a hard-coded property name for the application data throughout your source code.• You can access the data from within a subfunction callback routine using the component's handle (which is returned by <code>gcb</code>), without needing to find the figure's handle. <p><code>gui dat a</code> is particularly useful in conjunction with <code>gui handl es</code>, which creates a structure in the figure's application data containing the handles of all the components in a GUI.</p>
Examples	<p>In this example, <code>gui data</code> is used to save a structure on a GUI figure's application data from within the initialization section of the application M-file. This structure is initially created by <code>gui handl es</code> and then used to save additional data as well.</p> <pre>data = gui handl es(figure_handl e); % create structure of handl es data.number0fErrors = 0; % add some additional data gui data(figure_handl e, data) % save the structure</pre>

You can recall the data from within a subfunction callback routine and then save the structure again:

```
data = guidata(gcbo); % get the structure in the subfunction  
data.numberOfErrors = data.numberOfErrors + 1;  
guidata(gcbo, data) % save the changes to the structure
```

See Also

[gui](#), [de](#), [gui handl es](#), [getappdata](#), [setappdata](#)

guide

Purpose	Start the GUI Layout Editor
Syntax	<pre>gui de gui de('filename.fig') gui de(figure_handles)</pre>
Description	<p>gui de displays the GUI Layout Editor open to a new untitled FIG-file.</p> <p>gui de('filename.fig') opens the FIG-file named filename.fig. You can specify the path to a file not on your MATLAB path.</p> <p>gui de('figure_handles') opens FIG-files in the Layout Editor for each existing figure listed in figure_handles. MATLAB copies the contents of each figure into the FIG-file, with the exception of axes children (image, light, line, patch, rectangle, surface, and text objects), which are not copied.</p>
See Also	<p>inspect</p> <p>Creating GUIs</p>

Purpose	Create a structure of handles
Syntax	<code>handles = guihandles(object_handles)</code> <code>handles = guihandles</code>
Description	<code>handles = guihandles(object_handles)</code> returns a structure containing the handles of the objects in a figure, using the value of their Tag properties as the fieldnames, with the following caveats: <ul style="list-style-type: none">• Objects are excluded if their Tag properties are empty, or are not legal variable names.• If several objects have the same Tag, that field in the structure contains a vector of handles.• Objects with hidden handles are included in the structure.
See Also	<code>guidata</code> , <code>guide</code> , <code>getappdata</code> , <code>setappdata</code>

hadamard

Purpose	Hadamard matrix																
Syntax	$H = \text{hadamard}(n)$																
Description	$H = \text{hadamard}(n)$ returns the Hadamard matrix of order n .																
Definition	Hadamard matrices are matrices of 1's and -1's whose columns are orthogonal, $H^T * H = n*I$ where $[n n] = \text{size}(H)$ and $I = \text{eye}(n,n)$. They have applications in several different areas, including combinatorics, signal processing, and numerical analysis, [1], [2]. An n -by- n Hadamard matrix with $n > 2$ exists only if $\text{rem}(n, 4) = 0$. This function handles only the cases where n , $n/12$, or $n/20$ is a power of 2.																
Examples	The command <code>hadamard(4)</code> produces the 4-by-4 matrix: <table style="margin-left: auto; margin-right: auto;"><tr><td>1</td><td>1</td><td>1</td><td>1</td></tr><tr><td>1</td><td>-1</td><td>1</td><td>-1</td></tr><tr><td>1</td><td>1</td><td>-1</td><td>-1</td></tr><tr><td>1</td><td>-1</td><td>-1</td><td>1</td></tr></table>	1	1	1	1	1	-1	1	-1	1	1	-1	-1	1	-1	-1	1
1	1	1	1														
1	-1	1	-1														
1	1	-1	-1														
1	-1	-1	1														
See Also	<code>compan</code> , <code>hankel</code> , <code>toeplitz</code>																
References	[1] Ryser, H. J., <i>Combinatorial Mathematics</i> , John Wiley and Sons, 1963. [2] Pratt, W. K., <i>Digital Signal Processing</i> , John Wiley and Sons, 1978.																

Purpose	Hankel matrix												
Syntax	$H = \text{hankel}(c)$ $H = \text{hankel}(c, r)$												
Description	$H = \text{hankel}(c)$ returns the square Hankel matrix whose first column is c and whose elements are zero below the first anti-diagonal. $H = \text{hankel}(c, r)$ returns a Hankel matrix whose first column is c and whose last row is r . If the last element of c differs from the first element of r , the last element of c prevails.												
Definition	A Hankel matrix is a matrix that is symmetric and constant across the anti-diagonals, and has elements $h(i, j) = p(i+j-1)$, where vector $p = [c \ r(2: \text{end})]$ completely determines the Hankel matrix.												
Examples	A Hankel matrix with anti-diagonal disagreement is $c = 1: 3; r = 7: 10;$ $h = \text{hankel}(c, r)$ $h =$ <table style="margin-left: 200px;"><tr><td>1</td><td>2</td><td>3</td><td>8</td></tr><tr><td>2</td><td>3</td><td>8</td><td>9</td></tr><tr><td>3</td><td>8</td><td>9</td><td>10</td></tr></table> $p = [1 \ 2 \ 3 \ 8 \ 9 \ 10]$	1	2	3	8	2	3	8	9	3	8	9	10
1	2	3	8										
2	3	8	9										
3	8	9	10										
See Also	hadamard , toeplitz												

hdf

Purpose	HDF interface
Syntax	<code>hdf*(functstr, param1, param2, . . .)</code>
Description	MATLAB provides a set of functions that enable you to access the HDF library developed and supported by the National Center for Supercomputing Applications (NCSA). MATLAB supports all or a portion of these HDF interfaces: SD, V, VS, AN, DRF8, DF24, H, HE, and HD. To use these functions you must be familiar with the HDF library. Documentation for the library is available on the NCSA HDF Web page at http://hdf.ncsa.uiuc.edu . MATLAB additionally provides extensive command line help for each of the provided functions.
This table lists the interface-specific HDF functions in MATLAB.	
Function	Interface
<code>hdfan</code>	Multifile annotation
<code>hdfdf24</code>	24-bit raster image
<code>hdfdfr8</code>	8-bit raster image
<code>hdfgd</code>	HDF-EOS GD interface
<code>hdfh</code>	HDF H interface
<code>hdfhd</code>	HDF HD interface
<code>hdfhe</code>	HDF HE interface
<code>hdfml</code>	Gateway utilities
<code>hdfpt</code>	HDF-EOS PT interface
<code>hdfsd</code>	Multifile scientific data set
<code>hdfsw</code>	HDF-EOS SW interface
<code>hdfv</code>	Vgroup
<code>hdfvf</code>	Vdata VF functions

<code>hdfvh</code>	Vdata VH functions
<code>hdfvs</code>	Vdata VS functions

See Also

`imfinfo`, `imread`, `imwrite`, `int8`, `int16`, `int32`, `single`, `uint8`, `uint16`, `uint32`

hdfinfo

Purpose	Return information about an HDF or HDF-EOS file
Syntax	<code>S = hdfinfo(filename)</code> <code>S = hdfinfo(filename, mode)</code>
Description	<code>S = hdfinfo(filename)</code> returns a structure, S, whose fields contain information about the contents of an HDF or HDF-EOS file. <code>filename</code> is a string that specifies the name of the HDF file. <code>S = hdfinfo(filename, mode)</code> reads the file as an HDF file, if <code>mode</code> is ' <code>hdf</code> ' , or as an HDF-EOS file, if <code>mode</code> is ' <code>eos</code> '. If <code>mode</code> is ' <code>eos</code> ' , only HDF-EOS data objects are queried. To retrieve information on the entire contents of a file containing both HDF and HDF-EOS objects, <code>mode</code> must be ' <code>hdf</code> ' .

Note `hdfinfo` can be used on version 4.x HDF files or version 2.x HDF-EOS files.

The set of fields in the returned structure, S, depends on the individual file. Fields that may be present in the S structure are shown in the following table.

HDF Object Fields

Mode	Fieldname	Description	Return Type
HDF	Attributes	Attributes of the data set	Structure array
	Description	Annotation description	Cell array
	Filename	Name of the file	String
	Label	Annotation label	Cell array
	Raster8	Description of 8-bit raster images	Structure array
	Raster24	Description of 24-bit raster images	Structure array
	SDS	Description of scientific data sets	Structure array
	Vdata	Description of Vdata sets	Structure array
	Vgroup	Description of Vgroups	Structure array
EOS	Filename	Name of the file	String
	Grid	Grid data	Structure array
	Point	Point data	Structure array
	Swath	Swath data	Structure array

Those fields in the table above that contain structure arrays are further described in the tables shown below.

Fields Common to Returned Structure Arrays

Structure arrays returned by hdfinfo contain some common fields. These are shown in the table below. Not all structure arrays will contain all of these fields.

Common Fields

Fieldname	Description	Data Type
Attributes	Data set attributes. Contains fields Name and Value	Structure array
Description	Annotation description	Cell array
Filename	Name of the file	String
Label	Annotation label	Cell array
Name	Name of the data set	String
Rank	Number of dimensions of the data set	Double
Ref	Data set reference number	Double
Type	Type of HDF or HDF-EOS object	String

Fields Specific to Certain Structures

Structure arrays returned by hdfinfo also contain fields that are unique to each structure. These are shown in the tables below.

Fields of the Attribute Structure

Fieldname	Description	Data Type
Name	Attribute name	String
Value	Attribute value or description	Numeric or string

Fields of the Raster8 and Raster24 Structures

Fieldname	Description	Data Type
HasPalette	1 (true) if the image has an associated palette, otherwise 0 (false). (8-bit only)	Logical
Height	Height of the image, in pixels	Number
Interlace	Interlace mode of the image (24-bit only)	String
Name	Name of the image	String
Width	Width of the image, in pixels	Number

Fields of the SDS Structure

Fieldname	Description	Data Type
DataType	Data precision	String
Dims	Dimensions of the data set. Contains fields: Name, DataType, Size, Scale, and Attributes. Scale is an array of numbers to place along the dimension and demarcate intervals in the data set	Structure array
Index	Index of the SDS	Number

Fields of the Vdata Structure

Fieldname	Description	Data Type
DataAttributes	Attributes of the entire data set. Contains fields: Name and Value	Structure array
Class	Class name of the data set	String
Fields	Fields of the Vdata. Contains fields: Name and Attributes	Structure array

Fields of the Vdata Structure

Fieldname	Description	Data Type
NumRecords	Number of data set records.	Double
IsAttribute	1 (true) if Vdata is an attribute, otherwise 0 (false).	Logical

Fields of the Vgroup Structure

Fieldname	Description	Data Type
Class	Class name of the data set.	String
Raster8	Description of the 8-bit raster image.	Structure array
Raster24	Description of the 24-bit raster image.	Structure array
SDS	Description of the Scientific Data sets.	Structure array
Tag	Tag of this Vgroup.	Number
Vdata	Description of the Vdata sets.	Structure array
Vgroup	Description of the Vgroups.	Structure array

Fields of the Grid Structure

Fieldname	Description	Data Type
Columns	Number of columns in the grid.	Number
DataFields	Description of the data fields in each Grid field of the grid. Contains fields: Name, Rank, Dims, NumberType, FillValue, and TileDims.	Structure array
LowerRight	Lower right corner location, in meters.	Number
OriginCode	Origin code for the grid.	Number
PixRegCode	Pixel registration code.	Number

Fields of the Grid Structure

Fieldname	Description	Data Type
Projection	Projection code, zone code, sphere code, and projection parameters of the grid. Contains fields: Proj Code, ZoneCode, SphereCode, and Proj Param.	Structure
Rows	Number of rows in the grid.	Number
UpperLeft	Upper left corner location, in meters.	Number

Fields of the Point Structure

Fieldname	Description	Data Type
Level	Description of each level of the point. Contains fields: Name, NumRecords, FieldNames, DataType, and Index.	Structure

Fields of the Swath Structure

Fieldname	Description	Data Type
DataFields	Data fields in the swath. Contains fields: Name, Rank, Dims, NumberType, and FillValue.	Structure array
GeolocationFields	Geolocation fields in the swath. Contains fields: Name, Rank, Dims, NumberType, and FillValue.	Structure array
IdxMapInfo	Relationship between indexed elements of the geolocation mapping. Contains fields: Map, and Size.	Structure
MapInfo	Relationship between data and geolocation fields. Contains fields: Map, Offset, and Increment.	Structure

Examples

To retrieve information about the file, example. hdf

```
fileinfo = hdfinfo('example.hdf')

fileinfo =
    Filename: 'example.hdf'
        SDS: [1x1 struct]
        Vdata: [1x1 struct]
```

And to retrieve information from this about the scientific data set in example.hdf

```
sds_info = fileinfo.SDS

sds_info =
    Filename: 'example.hdf'
        Type: 'Scientific Data Set'
        Name: 'Example SDS'
        Rank: 2
        DataType: 'int16'
        Attributes: []
        Dims: [2x1 struct]
        Label: {}
        Description: {}
        Index: 0
```

See Also

[hdfread](#), [hdf](#)

Purpose	Extract data from an HDF or HDF-EOS file
Syntax	<pre>data = hdfread(filename, dataset) data = hdfread(hinfo) data = hdfread(..., param1, value1, param2, value2, ...) [data, map] = hdfread(...)</pre>
Description	<p>hdfread reads data from a data set in an HDF or HDF-EOS file. If the name of the data set is known, then hdfread searches the file for the data. If it is not known, use hdfinfo first, to obtain a structure describing the contents of the file. The information returned by hdfinfo contains structures describing the data sets contained in the file. You can extract one of these structures and pass it directly to hdfread.</p> <p><code>data = hdfread(filename, dataset)</code> returns all data from the file, <code>filename</code>, for the data set, <code>dataset</code>.</p> <p><code>data = hdfread(hinfo)</code> returns all data for the particular data set described by <code>hinfo</code>. <code>hinfo</code> is a structure extracted from the output structure of the <code>hdfinfo</code> function.</p> <p><code>data = hdfread(..., param1, value1, param2, value2, ...)</code> returns subsets of the data according to the specified parameter and value pairs. See the tables below to find the valid parameters and values for different data sets.</p> <p><code>[data, map] = hdfread(...)</code> returns the image data and the colormap for an 8-bit raster image.</p>
Arguments	<p>Note hdfread can be used on version 4.x HDF files or version 2.x HDF-EOS files.</p> <hr/> <p>The following tables show the valid parameters and values to be used with the third hdfread syntax shown above. There is one table for each type of data set. Parameters footnoted as <i>required</i> must be used to read data stored in that type of data set. Parameters footnoted as <i>exclusive</i> may not be used with any other subsetting parameter, except for required parameters.</p>

hdfread

When a parameter requires multiple values, the values must be stored in a cell array. For example, the 'Index' parameter requires three values: start, stride, and edge. Enclose these values in curly braces as a cell array.

```
hdfread(dataset_name, 'Index', {start, stride, edge})
```

All values that are indices are 1-based.

HDF Data

When using hdfread on HDF files, you can extract subsets of the data in SDS or Vdata data sets, as shown in the tables below.

Parameters and Values for SDS Data Sets

Parameter	Value	Description
'Index'	start	Array specifying the location in the data set to begin reading. Each number in start must be smaller than its corresponding dimension. Default value is 1, which indicates the first element of each dimension.
	stride	Array specifying the interval between the values to read. Default value is an interval of 1.
	edge	Array specifying the length of each dimension to read. Default value is an array containing the lengths of the corresponding dimensions.

SDS Syntax Example

```
hdfread(sds_dataset, 'Index', {start, stride, edge})
```

Parameters and Values for Vdata Data Sets

Parameter	Value	Description
'Fields'	fieldname	String naming the data set field to be read from. For multiple fieldnames, use a comma-separated list.
'FirstRecord'	records	One-based number specifying the first record from which to begin reading.
'NumRecords'	reccount	Number specifying the total number of records to read.

Vdata Syntax Example

```
hdfread(vdata_dataset, 'FirstRecord', 400, 'NumRecords', 50)
```

HDF-EOS Data

When using hdfread on HDF-EOS files, you can extract subsets the data in Grid, Point, or Swath data sets, as shown in the tables below.

Parameters and Values for Grid Data Sets

Parameter	Value	Description
'Box'	longitude	Two-element vector specifying longitude coordinates that define a region.
	latitude	Two-element vector specifying latitude coordinates that define a region.
'Fields' ¹	fieldname	String naming the data set field to be read from. You can specify only one fieldname for a Grid data set.
'Index' ²	start	Array specifying the location in the data set to begin reading. Each number in start must be smaller than its corresponding dimension. Default value is 1, which indicates the first element of each dimension.
	stride	Array specifying the interval between the values to read. Default value is an interval of 1.
	edge	Array specifying the length of each dimension to read. Default value is an array containing the lengths of the corresponding dimensions.
'Interpolate' ²	longitude	N-length vector specifying the longitude points for bilinear interpolation.
	latitude	N-length vector specifying the latitude points for bilinear interpolation.

hdfread

Parameters and Values for Grid Data Sets

Parameter	Value	Description
'Pixel's' ²	longitude	N-length vector specifying the longitude coordinates that define a region. This region will be converted into pixel rows and columns with the origin in the upper left-hand corner of the grid. This is the pixel equivalent of reading a 'Box' region.
	latitude	N-length vector specifying the latitude coordinates that define a region. See longitude, above.
'Tile' ²	coordinates	Vector specifying the tile coordinates to read.
'Time'	start	Number specifying the start of a period of time.
	stop	Number specifying the end of a period of time.
'Vertical' ³	dimension	String specifying either a dimension name or field name to subset the data by.
	range	Two-element vector specifying the minimum and maximum range for the subset. If dimension is a dimension name, then range specifies the range of elements to extract. If dimension is a field name, then range specifies the range of values to extract.

1. 'Fields' is a required parameter.
2. 'Index', 'Interpolate', 'Pixels', and 'Tile' are exclusive parameters.
3. 'Vertical' subsetting may be used alone or in conjunction with 'Box' or 'Time'. To subset a region along multiple dimensions, vertical subsetting may be used up to 8 times in one call to hdfread.

Grid Syntax Example:

```
hdfread(grid_dataset, 'Fields', fieldname, ...
'Vertical', {dimension, [min, max]})
```

Parameters and Values for Point Data Sets

Parameter	Value	Description
'Box'	longitude	Two-element vector specifying the longitude region.
	latitude	Two-element vector specifying the latitude region.
'Fields' ¹	fieldnames	String naming one or more data set fields to be read from. For multiple fieldnames, use a comma-separated list.
'Level' ¹	level	One-based number specifying which level to read from in a HDF-EOS Point data set.
'RecordNumbers'	records	Vector specifying the record numbers to read.
'Time'	start	Number specifying the start of a period of time.
	stop	Number specifying the end of a period of time.

1. 'Fields' and 'Level' are required parameters.

Point Syntax Example:

```
hdfread(point_dataset, 'Fields', {field1, field2}, ...
'Level', level, 'RecordNumbers', [1:50, 200:250])
```

hdfread

Parameters and Values for Swath Data Sets

Parameter	Value	Description
' Box'	longitude	Two-element vector specifying the longitude region.
	latitude	Two-element vector specifying the latitude region.
	mode	String defining the criterion for the inclusion of a cross track in a region. The cross track is within a region if its midpoint is within the box (<code>mode=' midpoint'</code>), either endpoint is within the box (<code>mode=' endpoint'</code>), or any point is within the box (<code>mode=' anypoint'</code>). mode is only valid for Swath data sets.
' ExtMode'	mode	String specifying whether geolocation fields and data fields must be in the same swath (<code>mode=' internal'</code>), or may be in different swaths (<code>mode=' external'</code>). mode is only used when extracting a time period or a region.
' Fields' ¹	fieldname	String naming the data set field to be read from. You can specify only one fieldname for a Swath data set.
' Index' ²	start	Array specifying the location in the data set to begin reading. Each number in start must be smaller than its corresponding dimension. Default value is 1, which indicates the first element of each dimension.
	stride	Array specifying the interval between the values to read. Default value is an interval of 1.
	edge	Array specifying the length of each dimension to read. Default value is an array containing the lengths of the corresponding dimensions.

Parameters and Values for Swath Data Sets

Parameter	Value	Description
'Time' ²	start	Number specifying the start of a period of time.
	stop	Number specifying the end of a period of time.
	mode	String defining the criterion for the inclusion of a cross track in a region. The cross track is within a region if its midpoint is within the box (mode='midpoint'), either endpoint is within the box (mode='endpoint'), or any point is within the box (mode='anypoint'). mode is only valid for Swath data sets.
'Vertical' ³	dimension	String specifying either a dimension name or field name to subset the data by.
	range	Two-element vector specifying the minimum and maximum range for the subset. If dimension is a dimension name, then range specifies the range of elements to extract. If dimension is a field name, then range specifies the range of values to extract.

1. 'Fields' is a required parameter.
2. 'Index' and 'Time' are exclusive parameters.
3. 'Vertical' subsetting may be used alone or in conjunction with 'Box' or 'Time'. To subset a region along multiple dimensions, vertical subsetting may be used up to 8 times in one call to hdfread.

Swath Syntax Example

```
hdfread(swath_dataset, 'Fields', fidname, ...
        'Time', {start, stop, 'midpoint'})
```

Examples

Example 1

When you know the name of the data set, you can refer to the data set by name in the hdfread command. To read a data set named 'Example SDS', use

```
data = hdfread('example.hdf', 'Example SDS');
```

Example 2

When you don't know the name of the data set, use hdfinfo first to retrieve information on the data set.

```
fileinfo = hdfinfo('example.hdf');
```

```
sds_info = fileinfo.SDS;
```

You can check the size of the information returned as follows.

```
sds_info.Dims.Size  
ans =  
    16  
ans =  
    5
```

Read a subset of the data returned from hdfinfo. This example specifies a starting index of [3 3], a interval of 1 between values ([] meaning the default value of 1), and a length of 10 rows and 2 columns.

```
data = hdfread(sds_info, 'Index', {[3 3], [], [10 2]});
```

```
data(:, 1)  
ans =  
    7  
    8  
    9  
   10  
   11  
   12  
   13  
   14  
   15  
   16
```

```
data(:, 2)  
ans =  
    8  
    9  
   10  
   11
```

```
12
13
14
15
16
17
```

Example 3

This example retrieves information from example.hdf first, and then reads two fields of the data, `Idx` and `Temp`.

```
info = hdfinfo('example.hdf');

data = hdfread(info, Vdata, ...
    'Fields', {'Idx', 'Temp'})

data =
    [1x10 int16]
    [1x10 int16]

index = data{1, 1};
temp = data{2, 1};

temp(1:6)
ans =
    0     12      3      5     10     -1
```

See Also

`hdfinfo`, `hdf`

help

Purpose	Display help for MATLAB functions in Command Window
Syntax	<code>help</code> <code>help /</code> <code>help function</code> <code>help tool box/</code> <code>help tool box/function</code> <code>help syntax</code>
Description	<p><code>help</code> lists all primary help topics in the Command Window. Each main help topic corresponds to a directory name on MATLAB's search path.</p> <p><code>help /</code> lists all of the operators and special characters, along with their descriptions.</p> <p><code>help function</code> displays M-file help, which is a brief description and the syntax for <code>function</code>, in the Command Window. If <code>function</code> is overloaded, <code>help</code> displays the M-file help for the first <code>function</code> found on the search path, and lists the overloaded functions.</p> <p><code>help tool box/</code> displays the contents file for the specified directory named <code>tool box</code>. It is not necessary to give the full pathname of the directory; the last component, or the last several components, is sufficient.</p> <p><code>help tool box/function</code> displays the M-file help for <code>function</code> that belongs to the <code>tool box</code> directory.</p> <p><code>help syntax</code> displays M-file help describing the syntax used in MATLAB commands and functions.</p>

Note M-file help displayed in the Command Window uses all uppercase characters for the function and variable names to make them stand out from the rest of the text. When typing function names, however, use lowercase characters. Some functions for interfacing to Java do use mixed case; the M-file help accurately reflects that and you should use mixed case when typing them.

Remarks**Creating Online Help for Your Own M-Files**

MATLAB's help system, like MATLAB itself, is highly extensible. You can write help descriptions for your own M-files and toolboxes using the same self-documenting method that MATLAB's M-files and toolboxes use.

The `help` function lists all help topics by displaying the first line (the H1 line) of the contents files in each directory on MATLAB's search path. The contents files are the M-files named `Contents.m` within each directory.

Typing `help topic`, where `topic` is a directory name, displays the comment lines in the `Contents.m` file located in that directory. If a contents file does not exist, `help` displays the H1 lines of all the files in the directory.

Typing `help topic`, where `topic` is a function name, displays help for the function by listing the first contiguous comment lines in the M-file `topic.m`.

Create self-documenting online help for your own M-files by entering text on one or more contiguous comment lines, beginning with the second line of the file (first line if it is a script). For example, an abridged version of the M-file `angle.m` provided with MATLAB could contain

```
function p = angle(h)
% ANGLE Polar angle.
% ANGLE(H) returns the phase angles, in radians, of a matrix
% with complex elements. Use ABS for the magnitudes.
p = atan2(imag(h), real(h));
```

When you execute `help angle`, lines 2, 3, and 4 display. These lines are the first block of contiguous comment lines. The help system ignores comment lines that appear later in an M-file, after any executable statements or after a blank line.

The first comment line in any M-file (the H1 line) is special. It should contain the function name and a brief description of the function. The `lookfor` function searches and displays this line, and `help` displays these lines in directories that do not contain a `Contents.m` file.

Creating Contents Files for Your Own M-File Directories

A `Contents.m` file is provided for each M-file directory included with the MATLAB software. If you create directories in which to store your own M-files, you should create `Contents.m` files for them too. To do so, simply follow the format used in an existing `Contents.m` file.

help

Examples

Typing

`help datafun`

displays help for the `datafun` directory.

Typing

`help fft`

displays help for the `fft` function.

To prevent long descriptions from scrolling off the screen before you have time to read them, enter `more on`, and then enter the `help` function.


See Also

`doc`, `helpbrowser`, `helpwin`, `lookfor`, `more`, `partialpath`, `path`, `what`, `which`

Purpose	Display the MATLAB Help browser, providing access to extensive online help
Graphical Interface	As an alternative to the <code>helpbrowser</code> function, select Help from the View menu or click the help  button on the toolbar in the MATLAB desktop.
Syntax	<code>helpbrowser</code>
Description	<code>helpbrowser</code> displays the Help browser, providing direct access to a comprehensive library of online help, including reference pages and manuals. If the Help browser was previously opened in the current session, it shows the last page viewed; otherwise it shows the Begin Here page. For details, see "Using the Help Browser" in the "Getting Help" chapter of <i>Using MATLAB</i> .

Tabs in Help Navigator pane provide different ways to find documentation.

View documentation in the display pane.



See Also

`doc`, `docopt`, `help`, `helpdesk`, `helpwin`, `lookfor`, `web`


helpdesk

Purpose	Display Help browser
Syntax	hel pdesk
Description	hel pdesk displays the Help browser and shows the “Begin Here” page. In previous releases, hel pdesk displayed the Help Desk, which was the precursor to the Help browser. In a future release, the hel pdesk function will be phased out – use the hel pbrowser function instead.
See Also	hel pbrowser

Purpose	Create a help dialog box
Syntax	<pre>hel pdl g hel pdl g(' hel pstring') hel pdl g(' hel pstring' , ' dl gname') h = hel pdl g(. . .)</pre>
Description	<p>hel pdl g creates a help dialog box or brings the named help dialog box to the front.</p> <p>hel pdl g displays a dialog box named ' Help Dialog' containing the string ' This is the default help string.'</p> <p>hel pdl g(' hel pstring') displays a dialog box named 'Help Dialog' containing the string specified by ' hel pstring'.</p> <p>hel pdl g(' hel pstring' , ' dl gname') displays a dialog box named ' dl gname' containing the string ' hel pstring'.</p> <p>h = hel pdl g(. . .) returns the handle of the dialog box.</p>
Remarks	MATLAB wraps the text in ' hel pstring' to fit the width of the dialog box. The dialog box remains on your screen until you press the OK button or the Return key. After pressing the button, the help dialog box disappears.
Examples	The statement,

```
hel pdl g(' Choose 10 points from the figure' , ' Point Selection');
```

displays this dialog box:



helpdlg

See Also

[dialog](#), [errordlg](#), [questdlg](#), [warndlg](#)

Purpose	Display M-file help, with access to M-file help for all functions
Syntax	<code>hel pwi n</code> <code>hel pwi n topic</code>
Description	<code>hel pwi n</code> lists topics for groups of functions in the Help browser. It shows brief descriptions of the topics and provides links to access M-file help for the functions. You cannot follow links in the <code>hel pwi n</code> list of functions if MATLAB is busy (for example, running a program).
	<code>hel pwi n topic</code> displays help information for the topic in the Help browser. If <code>topic</code> is a directory, it displays all functions in the directory. If <code>topic</code> is a function, it displays M-file help for that function. From the page, you can access a list of directories (the Default Topics link) as well as the reference page help for the function (the Go to online doc link). You cannot follow links in the <code>hel pwi n</code> list of functions if MATLAB is busy (for example, running a program).
Examples	<p>Typing</p> <pre>hel pwi n datafun</pre> <p>displays the functions in the <code>datafun</code> directory and a brief description of each.</p> <p>Typing</p> <pre>hel pwi n fft</pre> <p>displays the M-file help for the <code>fft</code> function in the Help browser.</p>
See Also	<code>doc</code> , <code>docopt</code> , <code>hel p</code> , <code>hel pbrowser</code> , <code>lookfor</code> , <code>web</code>

hess

Purpose	Hessenberg form of a matrix						
Syntax	$[P, H] = \text{hess}(A)$ $H = \text{hess}(A)$						
Description	$H = \text{hess}(A)$ finds H , the Hessenberg form of matrix A . $[P, H] = \text{hess}(A)$ produces a Hessenberg matrix H and a unitary matrix P so that $A = P^*H^*P'$ and $P'^*P = \text{eye}(\text{size}(A))$.						
Definition	A Hessenberg matrix is zero below the first subdiagonal. If the matrix is symmetric or Hermitian, the form is tridiagonal. This matrix has the same eigenvalues as the original, but less computation is needed to reveal them.						
Examples	H is a 3-by-3 eigenvalue test matrix:						
	$H = \begin{matrix} & & \\ -149 & -50 & -154 \\ 537 & 180 & 546 \\ -27 & -9 & -25 \end{matrix}$						
	Its Hessenberg form introduces a single zero in the (3,1) position:						
	$\text{hess}(H) = \begin{matrix} & & \\ -149.0000 & 42.2037 & -156.3165 \\ -537.6783 & 152.5511 & -554.9272 \\ 0 & 0.0728 & 2.4489 \end{matrix}$						
Algorithm	hess uses LAPACK routines to compute the Hessenberg form of a matrix:						
	<table border="1"><thead><tr><th>Matrix A</th><th>Routine</th></tr></thead><tbody><tr><td>Real symmetric</td><td>DSYTRD DSYTRD, DORGTR, (with output P)</td></tr><tr><td>Real nonsymmetric</td><td>DGEHRD DGEHRD, DORGHR (with output P)</td></tr></tbody></table>	Matrix A	Routine	Real symmetric	DSYTRD DSYTRD, DORGTR, (with output P)	Real nonsymmetric	DGEHRD DGEHRD, DORGHR (with output P)
Matrix A	Routine						
Real symmetric	DSYTRD DSYTRD, DORGTR, (with output P)						
Real nonsymmetric	DGEHRD DGEHRD, DORGHR (with output P)						

Matrix A	Routine
Complex Hermitian	ZHETRD ZHETRD, ZUNGTR (with output P)
Complex non-Hermitian	ZGEHRD ZGEHRD, ZUNGHR (with output P)

See Also eig, qz, schur

References [1] Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling, A. McKenney, and D. Sorensen, *LAPACK User's Guide* (http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999.

hex2dec

Purpose	Hexadecimal to decimal number conversion
Syntax	<code>d = hex2dec('hex_value')</code>
Description	<code>d = hex2dec('hex_value')</code> converts <i>hex_value</i> to its floating-point integer representation. The argument <i>hex_value</i> is a hexadecimal integer stored in a MATLAB string. The value of <i>hex_value</i> must be smaller than hexadecimal 10,000,000,000,000.
	If <i>hex_value</i> is a character array, each row is interpreted as a hexadecimal string.
Examples	<pre>hex2dec('3ff') ans = 1023</pre>
	For a character array S <pre>S = OFF 2DE 123 hex2dec(S) ans = 255 734 291</pre>
See Also	<code>dec2hex</code> , <code>format</code> , <code>hex2num</code> , <code>sprintf</code>

Purpose	Hexadecimal to double number conversion
Syntax	<code>f = hex2num('hex_value')</code>
Description	<code>f = hex2num('hex_value')</code> converts <i>hex_value</i> to the IEEE double-precision floating-point number it represents. NaN, Inf, and denormalized numbers are all handled correctly. Fewer than 16 characters are padded on the right with zeros.
Examples	<pre>f = hex2num('400921fb54442d18') f = 3.14159265358979</pre>
See Also	<code>format</code> , <code>hex2dec</code> , <code>sprintf</code>

hgload

Purpose	Loads Handle Graphics object from a file
Syntax	<pre>h = hgload('filename') h = hgload('filename', 'all')</pre>
Description	<p><code>h = hgload('filename')</code> loads a handle graphics object and its children if any from the file specified by <code>filename</code>. If <code>filename</code> contains no extension, then MATLAB adds the ".fig" extension.</p> <p><code>h = hgload('filename', 'all')</code> overrides the default behavior, which does not reload non-serializable objects saved in the file. These objects include the default toolbars and default menus.</p> <p>Non-serializable objects are normally not reloaded because they are loaded from different files at figure creation time. This allows revisions of the default menus and toolbars to occur without affecting existing fig-files. Passing the string <code>all</code> to <code>hgload</code> insures that any non-serializable objects contained in the file are also reloaded.</p> <p>Note that by default, <code>hgsave</code> excludes non- serializable objects from the fig-file unless you use the <code>all</code> flag.</p>
See Also	<code>hgsave</code> , <code>open</code>

Purpose	Saves a Handle Graphics object hierarchy to a file
Syntax	<code>hgsave('filename')</code> <code>hgsave(h, 'filename')</code> <code>hgsave('filename', 'all')</code>
Description	<code>hgsave('filename')</code> saves the current figure to a file named <code>filename</code> . <code>hgsave(h, 'filename')</code> saves the objects identified by the array of handles <code>h</code> to a file named <code>filename</code> . If you do not specify an extension for <code>filename</code> , then MATLAB adds the extension ".fig". If <code>h</code> is a vector, none of the handles in <code>h</code> may be ancestors or descendants of any other handles in <code>h</code> . <code>hgsave('filename', 'all')</code> overrides the default behavior, which does not save non-serializable objects. Non-serializable objects include the default toolbars and default menus. This allows revisions of the default menus and toolbars to occur without affecting existing FIG-files and also reduces the size of FIG-files. Passing the string <code>all</code> to <code>hgsave</code> insures that non-serializable objects are also saved. Note: the default behavior of <code>hload</code> is to ignore non-serializable objects in the file at load time. This behavior can be overwritten using the <code>all</code> argument with <code>hload</code> .
See Also	<code>hload</code> , <code>open</code>

hidden

Purpose	Remove hidden lines from a mesh plot
Syntax	<code>hidden on</code> <code>hidden off</code> <code>hidden</code>
Description	Hidden line removal draws only those lines that are not obscured by other objects in the field of view. <code>hidden on</code> turns on hidden line removal for the current graph so lines in the back of a mesh are hidden by those in front. This is the default behavior. <code>hidden off</code> turns off hidden line removal for the current graph. <code>hidden</code> toggles the hidden line removal state.
Algorithm	<code>hidden on</code> sets the <code>FaceCol</code> or <code>property</code> of a surface graphics object to the background <code>Col</code> or of the axes (or of the figure if <code>axes Col</code> or is none).
Examples	Set hidden line removal off and on while displaying the <code>peaks</code> function. <code>mesh(peaks)</code> <code>hidden off</code> <code>hidden on</code>
See Also	<code>shading</code> , <code>mesh</code> The surface properties <code>FaceCol</code> or and <code>EdgeCol</code> or

Purpose	Hilbert matrix
Syntax	<code>H = hilb(n)</code>
Description	<code>H = hilb(n)</code> returns the Hilbert matrix of order n .
Definition	The Hilbert matrix is a notable example of a poorly conditioned matrix [1]. The elements of the Hilbert matrices are $H(i, j) = 1/(i + j - 1)$.
Examples	Even the fourth-order Hilbert matrix shows signs of poor conditioning. <code>cond(hilb(4)) =</code> 1. 5514e+04
<hr/>	
Note	See the M-file for a good example of efficient MATLAB programming where conventional for loops are replaced by vectorized statements.
<hr/>	
See Also	<code>invhilb</code>
References	[1] Forsythe, G. E. and C. B. Moler, <i>Computer Solution of Linear Algebraic Systems</i> , Prentice-Hall, 1967, Chapter 19.

hist


Purpose	Histogram plot
Syntax	<pre>n = hist(Y) n = hist(Y, x) n = hist(Y, nbins) [n, xout] = hist(...)</pre>
Description	<p>A histogram shows the distribution of data values.</p> <p><code>n = hist(Y)</code> bins the elements in vector <code>Y</code> into 10 equally spaced containers and returns the number of elements in each container as a row vector. If <code>Y</code> is an m-by-p matrix, <code>hist</code> treats the columns of <code>Y</code> as vectors and returns a 10-by-p matrix <code>n</code>. Each column of <code>n</code> contains the results for the corresponding column of <code>Y</code>.</p> <p><code>n = hist(Y, x)</code> where <code>x</code> is a vector, returns the distribution of <code>Y</code> among <code>length(x)</code> bins with centers specified by <code>x</code>. For example, if <code>x</code> is a 5-element vector, <code>hist</code> distributes the elements of <code>Y</code> into five bins centered on the <code>x</code>-axis at the elements in <code>x</code>. Note: use <code>histc</code> if it is more natural to specify bin edges instead of centers.</p> <p><code>n = hist(Y, nbins)</code> where <code>nbins</code> is a scalar, uses <code>nbins</code> number of bins.</p> <p><code>[n, xout] = hist(...)</code> returns vectors <code>n</code> and <code>xout</code> containing the frequency counts and the bin locations. You can use <code>bar(xout, n)</code> to plot the histogram.</p> <p><code>hist(...)</code> without output arguments, <code>hist</code> produces a histogram plot of the output described above. <code>hist</code> distributes the bins along the <code>x</code>-axis between the minimum and maximum values of <code>Y</code>.</p>
Remarks	<p>All elements in vector <code>Y</code> or in one column of matrix <code>Y</code> are grouped according to their numeric range. Each group is shown as one bin.</p> <p>The histogram's <code>x</code>-axis reflects the range of values in <code>Y</code>. The histogram's <code>y</code>-axis shows the number of elements that fall within the groups; therefore, the <code>y</code>-axis ranges from 0 to the greatest number of elements deposited in any bin.</p> <p>The histogram is created with a patch graphics object. If you want to change the color of the graph, you can set patch properties. See the "Example" section</p>

for more information. By default, the graph color is controlled by the current colormap, which maps the bin color to the first color in the colormap.

Examples

Generate a bell-curve histogram from Gaussian data.

```
x = -2.9:0.1:2.9;  
y = randn(10000, 1);  
hist(y, x)
```




Change the color of the graph so that the bins are red and the edges of the bins are white.

```
h = findobj(gca, 'Type', 'patch');
```

hist

```
set(h, 'FaceColor', 'r', 'EdgeColor', 'w')
```



See Also

[bar](#), [ColorSpec](#), [histc](#), [patch](#), [stairs](#)

Purpose	Histogram count
Syntax	$n = \text{histc}(x, \text{edges})$ $n = \text{histc}(x, \text{edges}, \text{dim})$ $[n, \text{bin}] = \text{histc}(\dots)$
Description	<p>$n = \text{histc}(x, \text{edges})$ counts the number of values in vector x that fall between the elements in the edges vector (which must contain monotonically non-decreasing values). n is a $\text{lengh}(\text{edges})$ vector containing these counts.</p> <p>$n(k)$ counts the value $x(i)$ if $\text{edges}(k) \leq x(i) < \text{edges}(k+1)$. The last bin counts any values of x that match $\text{edges}(\text{end})$. Values outside the values in edges are not counted. Use $-\text{inf}$ and inf in edges to include all non-NaN values.</p> <p>For matrices, $\text{histc}(x, \text{edges})$ returns a matrix of column histogram counts. For N-D arrays, $\text{histc}(x, \text{edges})$ operates along the first non-singleton dimension.</p> <p>$n = \text{histc}(x, \text{edges}, \text{dim})$ operates along the dimension dim.</p> <p>$[n, \text{bin}] = \text{histc}(\dots)$ also returns an index matrix bin. If x is a vector, $n(k) = \text{sum}(\text{bin} == k)$. bin is zero for out of range values. If x is an M-by-N matrix, then,</p> <pre>for j=1:N, n(k,j) = sum(bin(:,j)==k); end</pre> <p>To plot the histogram, use the <code>bar</code> command.</p>
See Also	<code>hist</code>

hold

Purpose	Hold current graph in the figure
Syntax	<code>hold on</code> <code>hold off</code> <code>hold</code>
Description	<p>The <code>hold</code> function determines whether new graphics objects are added to the graph or replace objects in the graph.</p> <p><code>hold on</code> retains the current plot and certain axes properties so that subsequent graphing commands add to the existing graph.</p> <p><code>hold off</code> resets axes properties to their defaults before drawing new plots. <code>hold off</code> is the default.</p> <p><code>hold</code> toggles the hold state between adding to the graph and replacing the graph.</p>
Remarks	<p>Test the hold state using the <code>ishold</code> function.</p> <p>Although the hold state is on, some axes properties change to accommodate additional graphics objects. For example, the axes' limits increase when the data requires them to do so.</p> <p>The <code>hold</code> function sets the <code>NextPlot</code> property of the current figure and the current axes. If several axes objects exist in a figure window, each axes has its own hold state. <code>hold</code> also creates an axes if one does not exist.</p> <p><code>hold on</code> sets the <code>NextPlot</code> property of the current figure and axes to <code>add</code>.</p> <p><code>hold off</code> sets the <code>NextPlot</code> property of the current axes to <code>replace</code>.</p> <p><code>hold</code> toggles the <code>NextPlot</code> property between the <code>add</code> and <code>replace</code> states.</p>
See Also	<code>axis</code> , <code>cla</code> , <code>ishold</code> , <code>newplot</code> The <code>NextPlot</code> property of axes and figure graphics objects.

Purpose	Move the cursor to the upper left corner of the Command Window
Syntax	<code>home</code>
Description	<code>home</code> moves the cursor to the upper-left corner of the Command Window and clears the screen. You can use the scroll bar to see the history of previous functions.
Examples	Use <code>home</code> in an M-file to return the cursor to the upper-left corner of the screen.
See Also	<code>clc</code>

horzcat

Purpose	Horizontal concatenation																																
Syntax	<code>C = horzcat(A1, A2, ...)</code>																																
Description	<code>C = horzcat(A1, A2, ...)</code> horizontally concatenates matrices A1, A2, and so on. All matrices in the argument list must have the same number of rows. horzcat concatenates N-dimensional arrays along the second dimension. The first and remaining dimensions must match. MATLAB calls <code>C = horzcat(A1, A2, ...)</code> for the syntax <code>C = [A1 A2 ...]</code> when any of A1, A2, etc. is an object.																																
Examples	Create a 3-by-5 matrix, A, and a 3-by-3 matrix, B. Then horizontally concatenate A and B. <code>A = magic(5); % Create 3-by-5 matrix, A A(4:5,:) = []</code> <code>A =</code> <table><tr><td>17</td><td>24</td><td>1</td><td>8</td><td>15</td></tr><tr><td>23</td><td>5</td><td>7</td><td>14</td><td>16</td></tr><tr><td>4</td><td>6</td><td>13</td><td>20</td><td>22</td></tr></table> <code>B = magic(3)*100 % Create 3-by-3 matrix, B</code> <code>B =</code> <table><tr><td>800</td><td>100</td><td>600</td></tr><tr><td>300</td><td>500</td><td>700</td></tr><tr><td>400</td><td>900</td><td>200</td></tr></table> <code>C = horzcat(A, B) % Horizontally concatenate A and B</code> <code>C =</code> <table><tr><td>17</td><td>24</td><td>1</td><td>8</td><td>15</td><td>800</td><td>100</td><td>600</td></tr></table>	17	24	1	8	15	23	5	7	14	16	4	6	13	20	22	800	100	600	300	500	700	400	900	200	17	24	1	8	15	800	100	600
17	24	1	8	15																													
23	5	7	14	16																													
4	6	13	20	22																													
800	100	600																															
300	500	700																															
400	900	200																															
17	24	1	8	15	800	100	600																										

23	5	7	14	16	300	500	700
4	6	13	20	22	400	900	200

See Also

vertcat, cat

hsv2rgb

Purpose	Convert HSV colormap to RGB colormap
Syntax	<code>M = hsv2rgb(H)</code>
Description	<code>M = hsv2rgb(H)</code> converts a hue-saturation-value (HSV) colormap to a red-green-blue (RGB) colormap. H is an m -by-3 matrix, where m is the number of colors in the colormap. The columns of H represent hue, saturation, and value, respectively. M is an m -by-3 matrix. Its columns are intensities of red, green, and blue, respectively.
	<code>rgb_image = hsv2rgb(hsv_image)</code> converts the HSV image (3-D array) to the equivalent RGB image RGB (3-D array).
Remarks	As $H(:, 1)$ varies from 0 to 1, the resulting color varies from red through yellow, green, cyan, blue, and magenta, and returns to red. When $H(:, 2)$ is 0, the colors are unsaturated (i.e., shades of gray). When $H(:, 2)$ is 1, the colors are fully saturated (i.e., they contain no white component). As $H(:, 3)$ varies from 0 to 1, the brightness increases. The MATLAB hsv colormap uses <code>hsv2rgb([hue saturation value])</code> where hue is a linear ramp from 0 to 1, and saturation and value are all 1's.
See Also	<code>brighten</code> , <code>colormap</code> , <code>rgb2hsv</code>

Purpose	Imaginary unit
Syntax	i a+bi x+i *y
Description	As the basic imaginary unit <code>sqrt(-1)</code> , i is used to enter complex numbers. Since i is a function, it can be overridden and used as a variable. This permits you to use i as an index in for loops, etc. If desired, use the character i without a multiplication sign as a suffix in forming a complex numerical constant. You can also use the character j as the imaginary unit.
Examples	<code>Z = 2+3i</code> <code>Z = x+i *y</code> <code>Z = r*exp(i *theta)</code>
See Also	<code>conj</code> , <code>i mag</code> , <code>j</code> , <code>real</code>

if

Purpose	Conditionally execute statements
Syntax	<pre>if expression statements end</pre>
Description	MATLAB evaluates the <i>expression</i> and, if the evaluation yields a logical true or nonzero result, executes one or more MATLAB commands denoted here as <i>statements</i> . When nesting <i>if</i> s, each <i>if</i> must be paired with a matching <i>end</i> . When using <i>elseif</i> and/or <i>else</i> within an <i>if</i> statement, the general form of the statement is
	<pre>if expression1 statements1 elseif expression2 statements2 else statements3 end</pre>
Arguments	expression <i>expression</i> is a MATLAB expression, usually consisting of variables or smaller expressions joined by relational operators (e.g., <code>count < limit</code>), or logical functions (e.g., <code>isreal(A)</code>). Simple expressions can be combined by logical operators (<code>&</code> , <code> </code> , <code>~</code>) into compound expressions such as the following. MATLAB evaluates compound expressions from left to right, adhering to operator precedence rules. <code>(count < limit) & ((height - offset) >= 0)</code>
	statements <i>statements</i> is one or more MATLAB statements to be executed only if the <i>expression</i> is true or nonzero.

Remarks**Nonscalar Expressions**

If the evaluated expression yields a nonscalar value, then every element of this value must be true or nonzero for the entire expression to be considered true. For example, the statement, `if (A < B)` is true only if each element of matrix A is less than its corresponding element in matrix B. See Example 2, below.

Partial Evaluation of the expression Argument

Within the context of an `if` or `while` expression, MATLAB does not necessarily evaluate all parts of a logical expression. In some cases it is possible, and often advantageous, to determine whether an expression is true or false through only partial evaluation.

For example, if A equals zero in statement 1 below, then the expression evaluates to false, regardless of the value of B. In this case, there is no need to evaluate B and MATLAB does not do so. In statement 2, if A is nonzero, then the expression is true, regardless of B. Again, MATLAB does not evaluate the latter part of the expression.

1) `if (A & B)`

2) `if (A | B)`

You can use this property to your advantage to cause MATLAB to evaluate a part of an expression only if a preceding part evaluates to the desired state. Here are some examples.

```
while (b ~= 0) & (a/b > 18.5)
if exist('myfun.m') & (myfun(x) >= y)
if iscell(A) & all(cellfun('isreal', A))
```

Examples**Example 1 - Simple `if` Statement**

In this example, if both of the conditions are satisfied, then the student passes the course.

```
if ((attendance >= 0.90) & (grade_average >= 60))
    pass = 1;
end;
```

Example 2 - Nonscalar Expression

Given matrices A and B

if

$$\begin{array}{cc} A = & B = \\ \begin{array}{cc} 1 & 0 \\ 2 & 3 \end{array} & \begin{array}{cc} 1 & 1 \\ 3 & 4 \end{array} \end{array}$$

Expression	Evaluates As	Because
$A < B$	false	$A(1, 1)$ is not less than $B(1, 1)$.
$A < (B + 1)$	true	Every element of A is less than that same element of B with 1 added.
$A & B$	false	$A(1, 2) \& B(1, 2)$ is false.
$B < 5$	true	Every element of B is less than 5.

See Also

[else](#), [elseif](#), [end](#), [for](#), [while](#), [switch](#), [break](#), [return](#), [relational_operators](#), [logical_operators](#)

Purpose	Inverse one-dimensional fast Fourier transform
Syntax	$y = \text{ifft}(X)$ $y = \text{ifft}(X, n)$ $y = \text{ifft}(X, [], dim)$ $y = \text{ifft}(X, n, dim)$
Description	<p>$y = \text{ifft}(X)$ returns the inverse discrete Fourier transform (DFT) of vector X, computed with a fast Fourier transform (FFT) algorithm.</p> <p>If X is a matrix, ifft returns the inverse DFT of each column of the matrix.</p> <p>If X is a multidimensional array, ifft operates on the first non-singleton dimension.</p> <p>$y = \text{ifft}(X, n)$ returns the n-point inverse DFT of vector X.</p> <p>$y = \text{ifft}(X, [], dim)$ and $y = \text{ifft}(X, n, dim)$ return the inverse DFT of X across the dimension dim.</p> <p>For any X, $\text{ifft}(\text{fft}(X))$ equals X to within roundoff error. If X is real, $\text{ifft}(\text{fft}(X))$ may have small imaginary parts.</p>
Algorithm	The algorithm for $\text{ifft}(X)$ is the same as the algorithm for $\text{fft}(X)$, except for a sign change and a scale factor of $n = \text{length}(X)$. As for fft , the execution time for ifft depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.
See Also	fft , ifft2 , ifftn , ifftshift dftmtx and freqz , in the Signal Processing Toolbox

ifft2

Purpose	Inverse two-dimensional fast Fourier transform
Syntax	$Y = \text{ifft2}(X)$ $Y = \text{ifft2}(X, m, n)$
Description	$Y = \text{ifft2}(X)$ returns the two-dimensional inverse discrete Fourier transform (DFT) of X , computed with a fast Fourier transform (FFT) algorithm. The result Y is the same size as X . $Y = \text{ifft2}(X, m, n)$ returns the m -by- n inverse fast Fourier transform of matrix X . For any X , $\text{ifft2}(\text{fft2}(X))$ equals X to within roundoff error. If X is real, $\text{ifft2}(\text{fft2}(X))$ may have small imaginary parts.
Algorithm	The algorithm for $\text{ifft2}(X)$ is the same as the algorithm for $\text{fft2}(X)$, except for a sign change and scale factors of $[m, n] = \text{size}(X)$. The execution time for ifft2 depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.
See Also	dftmtx and freqz in the Signal Processing Toolbox, and: fft2 , fftshift , ifft , ifftn , ifftshift

Purpose	Inverse multidimensional fast Fourier transform
Syntax	$Y = \text{ifftn}(X)$ $Y = \text{ifftn}(X, \text{size})$
Description	$Y = \text{ifftn}(X)$ returns the n-dimensional inverse discrete Fourier transform (DFT) of X , computed with a multidimensional fast Fourier transform (FFT) algorithm. The result Y is the same size as X . $Y = \text{ifftn}(X, \text{size})$ pads X with zeros, or truncates X , to create a multidimensional array of size size before performing the inverse transform. The size of the result Y is size .
Remarks	For any X , $\text{ifftn}(\text{fft}(X))$ equals X within roundoff error. If X is real, $\text{ifftn}(\text{fft}(X))$ may have small imaginary parts.
Algorithm	$\text{ifftn}(X)$ is equivalent to <pre>Y = X; for p = 1:length(size(X)) Y = ifft(Y, [], p); end</pre> This computes in-place the one-dimensional inverse DFT along each dimension of X . The execution time for ifftn depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.
See Also	fft , ifft , ifft2 , ifftshift

ifftshift

Purpose	Inverse FFT shift
Syntax	<code>ifftshift(X)</code> <code>ifftshift(X, dim)</code>
Description	<code>ifftshift(X)</code> undoes the results of <code>fftshift</code> . If X is a vector, <code>ifftshift(X)</code> swaps the left and right halves of X . For matrices, <code>ifftshift(X)</code> swaps the first quadrant with the third and the second quadrant with the fourth. If X is a multidimensional array, <code>ifftshift(X)</code> swaps “half-spaces” of X along each dimension. <code>ifftshift(X, dim)</code> applies the <code>ifftshift</code> operation along the dimension dim .
See Also	<code>fft</code> , <code>fft2</code> , <code>fftn</code> , <code>fftshift</code>

Purpose Convert indexed image into movie format

Syntax

```
f = im2frame(X, map)
f = im2frame(X)
```

Description `f = im2frame(X, map)` converts the indexed image `X` and associated colormap `map` into a movie frame `f`. If `X` is a truecolor (m-by-n-by-3) image, then `map` is optional and has no affect.

Typical usage:

```
M(1) = im2frame(X1, map);
M(2) = im2frame(X2, map);
...
M(n) = im2frame(Xn, map);
movie(M)
```

`f = im2frame(X)` converts the indexed image `X` into a movie frame `f` using the current colormap if `X` contains an indexed image.

See Also `frame2im`, `movie`, `capture`

imag

Purpose Imaginary part of a complex number

Syntax $Y = \text{imag}(Z)$

Description $Y = \text{imag}(Z)$ returns the imaginary part of the elements of array Z.

Examples $\text{imag}(2+3i)$

ans =

3

See Also conj , i , j , real

Purpose	Display image object
Syntax	<pre>image(C) image(x, y, C) image(..., 'PropertyName', PropertyValue, ...) image('PropertyName', PropertyValue, ...) Formal syntax - PN/PV only handle = image(...)</pre>
Description	<p>image creates an image graphics object by interpreting each element in a matrix as an index into the figure's colormap or directly as RGB values, depending on the data specified.</p> <p>The image function has two forms:</p> <ul style="list-style-type: none"> • A high-level function that calls newplot to determine where to draw the graphics objects and sets the following axes properties: XLim and YLim to enclose the image Layer to top to place the image in front of the tick marks and grid lines YDir to reverse View to [0 90] • A low-level function that adds the image to the current axes without calling newplot. The low-level function argument list can contain only property name/property value pairs. <p>You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see set and get for examples of how to specify these data types).</p> <p>image(C) displays matrix C as an image. Each element of C specifies the color of a rectangular segment in the image.</p> <p>image(x, y, C) where x and y are two-element vectors, specifies the range of the x- and y-axis labels, but produces the same image as image(C). This can be useful, for example, if you want the axis tick labels to correspond to real physical dimensions represented by the image.</p>

`image(x, y, C, 'PropertyName', PropertyValue, ...)` is a high-level function that also specifies property name/property value pairs. This syntax calls `newplot` before drawing the image.

`image('PropertyName', PropertyValue, ...)` is the low-level syntax of the `image` function. It specifies only property name/property value pairs as input arguments.

`handle = image(...)` returns the handle of the image object it creates. You can obtain the handle with all forms of the `image` function.

Remarks

image data can be either indexed or true color. An indexed image stores colors as an array of indices into the figure colormap. A true color image does not use a colormap; instead, the color values for each pixel are stored directly as RGB triplets. In MATLAB, the `CData` property of a truecolor image object is a three-dimensional (m -by- n -by-3) array. This array consists of three m -by- n matrices (representing the red, green, and blue color planes) concatenated along the third dimension.

The `imread` function reads image data into MATLAB arrays from graphics files in various standard formats, such as TIFF. You can write MATLAB image data to graphics files using the `imwrite` function. `imread` and `imwrite` both support a variety of graphics file formats and compression schemes.

When you read image data into MATLAB using `imread`, the data is usually stored as an array of 8-bit integers. However, `imread` also supports reading 16-bit-per-pixel data from TIFF and PNG files. These are more efficient storage method than the double-precision (64-bit) floating-point numbers that MATLAB typically uses. However, it is necessary for MATLAB to interpret

8-bit and 16-bit image data differently from 64-bit data. This table summarizes these differences.

Image Type	Double-precision Data (double array)	8-bit Data (uint8 array) 16-bit Data (uint16 array)
indexed (colormap)	Image is stored as a two-dimensional (m-by-n) array of integers in the range [1, length(colormap)]; colormap is an m-by-3 array of floating-point values in the range [0, 1]	Image is stored as a two-dimensional (m-by-n) array of integers in the range [0, 255] (uint8) or [0, 65535] (uint16); colormap is an m-by-3 array of floating-point values in the range [0, 1]
truecolor (RGB)	Image is stored as a three-dimensional (m-by-n-by-3) array of floating-point values in the range [0, 1]	Image is stored as a three-dimensional (m-by-n-by-3) array of integers in the range [0, 255] (uint8) or [0, 65535] (uint16)

Indexed Images

In an indexed image of class double, the value 1 points to the first row in the colormap, the value 2 points to the second row, and so on. In a uint8 or uint16 indexed image, there is an offset; the value 0 points to the first row in the colormap, the value 1 points to the second row, and so on.

If you want to convert a uint8 or uint16 indexed image to double, you need to add 1 to the result. For example,

```
X64 = double(X8) + 1;
```

or

```
X64 = double(X16) + 1;
```

To convert from double to uint8 or uint16, you need to first subtract 1, and then use round to ensure all the values are integers.

```
X8 = uint8(round(X64 - 1));
```

or

```
X16 = uint16(round(X64 - 1));
```

The order of the operations must be as shown in these examples, because you cannot perform mathematical operations on `uint8` or `uint16` arrays.

When you write an indexed image using `imwrite`, MATLAB automatically converts the values if necessary.

Colormaps

Colormaps in MATLAB are always m-by-3 arrays of double-precision floating-point numbers in the range [0, 1]. In most graphics file formats, colormaps are stored as integers, but MATLAB does not support colormaps with integer values. `imread` and `imwrite` automatically convert colormap values when reading and writing files.

True Color Images

In a truecolor image of class `double`, the data values are floating-point numbers in the range [0, 1]. In a truecolor image of class `uint8`, the data values are integers in the range [0, 255] and for truecolor image of class `uint16` the data values are integers in the range [0, 65535]

If you want to convert a truecolor image from one data type to the other, you must rescale the data. For example, this statement converts a `uint8` truecolor image to `double`,

```
RGB64 = double(RGB8)/255;
```

or for `uint16` images,

```
RGB64 = double(RGB16)/65535;
```

This statement converts a `double` truecolor image to `uint8`.

```
RGB8 = uint8(round(RGB64*255));
```


or for `uint16` images,

```
RGB16 = uint16(round(RGB64*65535));
```

The order of the operations must be as shown in these examples, because you cannot perform mathematical operations on `uint8` or `uint16` arrays.

When you write a truecolor image using `imwrite`, MATLAB automatically converts the values if necessary.

Object Hierarchy



Setting Default Properties

You can set default image properties on the axes, figure, and root levels.

```

set(0, 'DefaultImageProperty', PropertyValue...)
set(gcf, 'DefaultImageProperty', PropertyValue...)
set(gca, 'DefaultImageProperty', PropertyValue...)
  
```

Where *Property* is the name of the image property and *PropertyValue* is the value you are specifying. Use `set` and `get` to access image properties.

The following table lists all image properties and provides a brief description of each. The property name links take you to an expanded description of the properties.

Property Name	Property Description	Property Value
Data Defining the Object		
CData	The image data	Values: matrix or m-by-n-by-3 array Default: enter image; axis image ij and see
CDataMapping	Specify the mapping of data to colormap	Values: scaled, direct Default: direct

image

Property Name	Property Description	Property Value
XData	Control placement of image along <i>x</i> -axis	Values: [min max] Default: [1 size(CData, 2)]
YData	Control placement of image along <i>y</i> -axis	Values: [min max] Default: [1 size(CData, 1)]
Specifying Transparency		
AlphaData	Transparency data	m-by-n matrix of double or uint8 Default: 1 (opaque)
AlphaDataMapping	Transparency mapping method	none, direct, scaled Default: none
Controlling the Appearance		
Clipping	Clipping to axes rectangle	Values: on, off Default: on
EraseMode	Method of drawing and erasing the image (useful for animation)	Values: normal, none, xor, background Default: normal
SelectionHighlight	Highlight image when selected (Selected property set to on)	Values: on, off Default: on
Visible	Make the image visible or invisible	Values: on, off Default: on
Controlling Access to Objects		
HandleVisibility	Determines if and when the line's handle is visible to other functions	Values: on, callback, off Default: on
HitTest	Determine if image can become the current object (see the figure CurrentObject property)	Values: on, off Default: on
General Information About the Image		
Children	Image objects have no children	Values: [] (empty matrix)

Property Name	Property Description	Property Value
Parent	The parent of an image object is always an axes object	Value: axes handle
Selected	Indicate whether image is in a "selected" state.	Values: on, off Default: on
Tag	User-specified label	Value: any string Default: '' (empty string)
Type	The type of graphics object (read only)	Value: the string 'image'
UserData	User-specified data	Value: any matrix Default: [] (empty matrix)

Properties Related to Callback Routine Execution

BusyAction	Specify how to handle callback routine interruption	Values: cancel, queue Default: queue
ButtonDownFcn	Define a callback routine that executes when a mouse button is pressed on over the image	Values: string Default: empty string
CreateFcn	Define a callback routine that executes when an image is created	Values: string Default: empty string
DeleteFcn	Define a callback routine that executes when the image is deleted (via close or delete)	Values: string Default: empty string
Interruptible	Determine if callback routine can be interrupted	Values: on, off Default: on (can be interrupted)
UIContextMenu	Associate a context menu with the image	Values: handle of a uicontextmenu

Image Properties

Image Properties

This section lists property names along with the types of values each property accepts.

AlphaData m-by-n matrix of double or uint8

The transparency data. A matrix of non-NaN values specifying the transparency of each element in the image data. The AlphaData can be of class double or uint8.

MATLAB determines the transparency in one of three ways:

- Using the elements of AlphaData as transparency values (AlphaDataMapping set to none, the default).
- Using the elements of AlphaData as indices into the current alphamap (AlphaDataMapping set to direct).
- Scaling the elements of AlphaData to range between the minimum and maximum values of the axes Alim property (AlphaDataMapping set to scaled).

AlphaDataMapping {none} | direct | scaled

Transparency mapping method. This property determines how MATLAB interprets indexed alpha data. It can be any of the following:

- none - The transparency values of AlphaData are between 0 and 1 or are clamped to this range (the default).
- scaled - Transform the AlphaData to span the portion of the alphamap indicated by the axes Alim property, linearly mapping data values to alpha values.
- direct - Use the AlphaData as indices directly into the alphamap. When not scaled, the data are usually integer values ranging from 1 to length(alphamap). MATLAB maps values less than 1 to the first alpha value in the alphamap, and values greater than length(alphamap) to the last alpha value in the alphamap. Values with a decimal portion are fixed to the nearest, lower integer. If AlphaData is an array uint8 integers, then the indexing begins at 0 (i.e., MATLAB maps a value of 0 to the first alpha value in the alphamap).

BusyAction cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback

routines. If there is a callback routine executing, subsequently invoked callback routes always attempt to interrupt it. If the `Interruptible` property of the object whose callback is executing is set to `on` (the default), then interruption occurs at the next point where the event queue is processed. If the `Interruptible` property is `off`, the `BusyAction` property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are:

- `cancel` – discard the event that attempted to execute a second callback routine.
- `queue` – queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn string

Button press callback routine. A callback routine that executes whenever you press a mouse button while the pointer is over the image object. Define this routine as a string that is a valid MATLAB expression or the name of an M-file. The expression executes in the MATLAB workspace.

CData matrix or m-by-n-by-3 array

The image data. A matrix of values specifying the color of each rectangular area defining the image. `image(C)` assigns the values of `C` to `CData`. MATLAB determines the coloring of the image in one of three ways:

- Using the elements of `CData` as indices into the current colormap (the default)
- Scaling the elements of `CData` to range between the values `min(get(gca, 'CLim'))` and `max(get(gca, 'CLim'))` (`CDataMapping` set to `scaled`)
- Interpreting the elements of `CData` directly as RGB values (true color specification)

Note that the behavior of NaNs in `CData` is not defined. See the `ImageAlphaData` property for information on using transparency with images.

A true color specification for `CData` requires an m-by-n-by-3 array of RGB values. The first page contains the red component, the second page the green component, and the third page the blue component of each element in the


Image Properties

image. RGB values range from 0 to 1. The following picture illustrates the relative dimensions of CData for the two color models.

Indexed Colors

	CData	


True Colors



If CData has only one row or column, the height or width respectively is always one data unit and is centered about the first YData or XData element respectively. For example, using a 4-by-1 matrix of random data,

```
C = rand(4, 1);
image(C, 'CDataMapping', 'scaled')
axis image
```

produces:



CDataMapping scaled | {direct}

Direct or scaled indexed colors. This property determines whether MATLAB interprets the values in CData as indices into the figure colormap (the default) or scales the values according to the values of the axes `CLim` property.

When `CDataMapping` is `direct`, the values of `CData` should be in the range 1 to `length(get(gcf, 'Colormap'))`. If you use true color specification for `CData`, this property has no effect.

Children handles

The empty matrix; image objects have no children.

Clipping on | off

Clipping mode. By default, MATLAB clips images to the axes rectangle. If you set `Clipping` to `off`, the image can display outside the axes rectangle. For example, if you create an image, set `hold` to `on`, freeze axis scaling (`axis manual`), and then create a larger image, it extends beyond the axis limits.

Image Properties

CreateFcn string

Callback routine executed during object creation. This property defines a callback routine that executes when MATLAB creates an image object. You must define this property as a default value for images. For example, the statement,

```
set(0, 'DefaultImageCreateFcn', 'axis image')
```

defines a default value on the root level that sets the aspect ratio and the axis limits so the image has square pixels. MATLAB executes this routine after setting all image properties. Setting this property on an existing image object has no effect.

The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

DeleteFcn string

Delete image callback routine. A callback routine that executes when you delete the image object (i.e., when you issue a delete command or clear the axes or figure containing the image). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

EraseMode {normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase image objects. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects redraw is necessary to improve performance and obtain the desired effect.

- normal (the default) — Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none – Do not erase the image when it is moved or changed. While the object is still visible on the screen after erasing with EraseMode none, you cannot print it because MATLAB stores no information about its former location.

- xor – Draw and erase the image by performing an exclusive OR (XOR) with the color of the screen beneath it. This mode does not damage the color of the objects beneath the image. However, the image's color depends on the color of whatever is beneath it on the display.
- background – Erase the image by drawing it in the axes' background Col or, or the figure background Col or if the axes Col or is set to none. This damages objects that are behind the erased image, but images are always properly colored.

Printing with Non-normal Erase Modes. MATLAB always prints figures as if the EraseMode of all objects is normal . This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB may mathematically combine layers of colors (e.g., XORing a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

You can use the MATLAB `getframe` command or other screen capture application to create an image of a figure containing non-normal mode objects.

HandleVisibility {on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when HandleVisibility is on.

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

Image Properties

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes `get`, `findobj`, `gca`, `gcf`, `gco`, `newplot`, `cla`, `clf`, and `close`.

When a handle's visibility is restricted using `callback` or `off`, the object's handle does not appear in its parent's `Children` property, figures do not appear in the root's `CurrentFigure` property, objects do not appear in the root's `CallbackObject` property or in the figure's `CurrentObject` property, and axes do not appear in their parent's `CurrentAxes` property.

You can set the root `ShowHiddenHandles` property to `on` to make all handles visible, regardless of their `HandleVisibility` settings (this does not affect the values of the `HandleVisibility` properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

HitTest {`on`} | `off`

Selectable by mouse click. `HitTest` determines if the image can become the current object (as returned by the `gco` command and the figure `CurrentObject` property) as a result of a mouse click on the image. If `HitTest` is `off`, clicking on the image selects the object below it (which maybe the axes containing it).

Interruptible {`on`} | `off`

Callback routine interruption mode. The `Interruptible` property controls whether an image callback routine can be interrupted by subsequently invoked callback routines. Only callback routines defined for the `ButtonDownFcn` are affected by the `Interruptible` property. MATLAB checks for events that can interrupt a callback routine only when it encounters a `drawnow`, `figure`, `getframe`, or `pause` command in the routine.

Parent handle of parent axes

Image's parent. The handle of the image object's parent axes. You can move an image object to another axes by changing this property to the new axes handle.

Selected `on` | {`off`}

Is object selected? When this property is `on`, MATLAB displays selection handles if the `SelectionHighlight` property is also `on`. You can, for example,

define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight {on} | off

Objects highlight when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles.

Tag string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Type string (read only)

Type of graphics object. This property contains a string that identifies the class of graphics object. For image objects, Type is always 'image'.

UIContextMenu handle of a uicontextmenu object

Associate a context menu with the image. Assign this property the handle of a uicontextmenu object created in the same figure as the image. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the image.

UserData matrix

User specified data. This property can be any data you want to associate with the image object. The image does not use this property, but you can access it using set and get.

Visible {on} | off

Image visibility. By default, image objects are visible. Setting this property to off prevents the image from being displayed. However, the object still exists and you can set and query its properties.

XData [1 size(CData, 2)] by default

Control placement of image along x-axis. A vector specifying the locations of the centers of the elements CData(1, 1) and CData(m, n), where CData has a size of m-by-n. Element CData(1, 1) is centered over the coordinate defined by the first

Image Properties

elements in XData and YData. Element CData(m, n) is centered over the coordinate defined by the last elements in XData and YData. The centers of the remaining elements of CData are evenly distributed between those two points.

The width of each CData element is determined by the expression:

$$(XData(2) - XData(1)) / (\text{size}(CData, 2) - 1)$$

You can also specify a single value for XData. In this case, image centers the first element at this coordinate and centers each following element one unit apart.

YData [1 size(CData, 1)] by default

Control placement of image along y-axis. A vector specifying the locations of the centers of the elements CData(1, 1) and CData(m, n), where CData has a size of m-by-n. Element CData(1, 1) is centered over the coordinate defined by the first elements in XData and YData. Element CData(m, n) is centered over the coordinate defined by the last elements in XData and YData. The centers of the remaining elements of CData are evenly distributed between those two points.

The height of each CData element is determined by the expression:

$$(YData(2) - YData(1)) / (\text{size}(CData, 1) - 1)$$

You can also specify a single value for YData. In this case, image centers the first element at this coordinate and centers each following elements one unit apart.


See Also

colormap, imfinfo, imread, imwrite, pcolor, newplot, surface

Displaying Bit-Mapped Images in Graphics.

Purpose	Scale data and display an image object
Syntax	<code>imagesc(C)</code> <code>imagesc(x, y, C)</code> <code>imagesc(..., clims)</code> <code>h = imagesc(...)</code>
Description	The <code>imagesc</code> function scales image data to the full range of the current colormap and displays the image. (See Examples for an illustration.)
	<code>imagesc(C)</code> displays <code>C</code> as an image. Each element of <code>C</code> corresponds to a rectangular area in the image. The values of the elements of <code>C</code> are indices into the current colormap that determine the color of each patch.
	<code>imagesc(x, y, C)</code> displays <code>C</code> as an image and specifies the bounds of the <i>x</i> - and <i>y</i> -axis with vectors <code>x</code> and <code>y</code> .
	<code>imagesc(..., clims)</code> normalizes the values in <code>C</code> to the range specified by <code>clims</code> and displays <code>C</code> as an image. <code>clims</code> is a two-element vector that limits the range of data values in <code>C</code> . These values map to the full range of values in the current colormap.
	<code>h = imagesc(...)</code> returns the handle for an image graphics object.
Remarks	<code>x</code> and <code>y</code> do not affect the elements in <code>C</code> ; they only affect the annotation of the axes. If <code>length(x) > 2</code> or <code>length(y) > 2</code> , <code>imagesc</code> ignores all except the first and last elements of the respective vector.
Algorithm	<code>imagesc</code> creates an image with <code>CDataMapping</code> set to <code>scaled</code> , and sets the axes <code>CLim</code> property to the value passed in <code>clims</code> .
Examples	If the size of the current colormap is 81-by-3, the statements <code>clims = [10 60]</code> <code>imagesc(C, clims)</code> map the data values in <code>C</code> to the colormap as shown in this illustration.

imagedesc





In this example, the left image maps to the gray colormap using the statements

```
load clown  
imagesc(X)  
colormap(gray)
```

The right image has values between 10 and 60 scaled to the full range of the gray colormap using the statements

```
load clown  
clims = [10 60];  
imagesc(X, clims)  
colormap(gray)
```



See Also

`image`, `colorbar`

imfinfo

Purpose	Information about graphics file
Syntax	<pre>info = imfinfo(filename, fmt)</pre> <pre>info = imfinfo(filename)</pre>
Description	<pre>info = imfinfo(filename, fmt)</pre> returns a structure whose fields contain information about an image in a graphics file. <code>filename</code> is a string that specifies the name of the graphics file, and <code>fmt</code> is a string that specifies the format of the file. The file must be in the current directory or in a directory on the MATLAB path. If <code>imfinfo</code> cannot find a file named <code>filename</code> , it looks for a file named <code>filename.</code> <code>fmt</code> .

This table lists the possible values for `fmt`.

Format	File Type
'bmp'	Windows Bitmap (BMP)
'cur'	Windows Cursor resources (CUR)
'hdf'	Hierarchical Data Format (HDF)
'ico'	Windows Icon resources (ICO)
'jpg' or 'jpeg'	Joint Photographic Experts Group (JPEG)
'pcx'	Windows Paintbrush (PCX)
'png'	Portable Network Graphics (PNG)
'tif' or 'tiff'	Tagged Image File Format (TIFF)
'xwd'	X Windows Dump (XWD)

If `filename` is a TIFF or HDF file containing more than one image, `info` is a structure array with one element (i.e., an individual structure) for each image in the file. For example, `info(3)` would contain information about the third image in the file.

The set of fields in `info` depends on the individual file and its format. However, the first nine fields are always the same. This table lists these fields and describes their values.

Field	Value
<code>filename</code>	A string containing the name of the file; if the file is not in the current directory, the string contains the full pathname of the file
<code>fileModDate</code>	A string containing the date when the file was last modified
<code>fileSize</code>	An integer indicating the size of the file in bytes
<code>format</code>	A string containing the file format, as specified by <code>fmt</code> ; for JPEG and TIFF files, the three-letter variant is returned
<code>formatVersion</code>	A string or number describing the version of the format
<code>width</code>	An integer indicating the width of the image in pixels
<code>height</code>	An integer indicating the height of the image in pixels
<code>bitDepth</code>	An integer indicating the number of bits per pixel
<code>colorType</code>	A string indicating the type of image; either ' <code>truecolor</code> ' for a truecolor RGB image, ' <code>grayscale</code> ' for a grayscale intensity image, or ' <code>indexed</code> ' for an indexed image

`info = imfinfo(filename)` attempts to infer the format of the file from its contents.

Example

```
info = imfinfo('canoe.tif')
```

```
info =
```

```
Filename: 'canoe.tif'
```

```
FileModDate: '25-Oct-1996 22:10:39'  
FileSize: 69708  
Format: 'tif'  
FormatVersion: []  
Width: 346  
Height: 207  
BitDepth: 8  
ColorType: 'indexed'  
FormatSignature: [73 73 42 0]  
ByteOrder: 'little-endian'  
NewSubfileType: 0  
BitsPerSample: 8  
Compression: 'PackBits'  
PhotometricInterpretation: 'RGB Palette'  
StripOffsets: [ 9x1 double]  
SamplesPerPixel: 1  
RowsPerStrip: 23  
StripByteCounts: [ 9x1 double]  
XResolution: 72  
YResolution: 72  
ResolutionUnit: 'Inch'  
Colormap: [256x3 double]  
PlanarConfiguration: 'Chunky'  
TileWidth: []  
TileLength: []  
TileOffsets: []  
TileByteCounts: []  
Orientation: 1  
FillOrder: 1  
GrayResponseUnit: 0.0100  
MaxSampleValue: 255  
MinSampleValue: 0  
Thresholding: 1
```

See Also

`imread`, `imwrite`

Purpose	Add a package or class to the current Java import list for the MATLAB command environment or for the calling function
Syntax	<pre>import package_name.* import class_name import cls_or_pkg_name1 cls_or_pkg_name2... import L = import</pre>
Description	<p><code>import package_name.*</code> adds all the classes in <code>package_name</code> to the current import list. Note that <code>package_name</code> must be followed by <code>.*</code>.</p> <p><code>import class_name</code> adds a single class to the current import list. Note that <code>class_name</code> must be fully qualified (that is, it must include the package name).</p> <p><code>import cls_or_pkg_name1 cls_or_pkg_name2...</code> adds all named classes and packages to the current import list. Note that each class name must be fully qualified, and each package name must be followed by <code>.*</code>.</p> <p><code>import</code> with no input arguments displays the current import list, without adding to it.</p> <p><code>L = import</code> with no input arguments returns a cell array of strings containing the current import list, without adding to it.</p> <p>The <code>import</code> command operates exclusively on the import list of the function from which it is invoked. When invoked at the command prompt, <code>import</code> uses the import list for the MATLAB command environment. If <code>import</code> is used in a script invoked from a function, it affects the import list of the function. If <code>import</code> is used in a script that is invoked from the command prompt, it affects the import list for the command environment.</p> <p>The import list of a function is persistent across calls to that function and is only cleared when the function is cleared.</p> <p>To clear the current import list, use the following command.</p> <pre>clear import</pre> <p>This command may only be invoked at the command prompt. Attempting to use <code>clear import</code> within a function results in an error.</p>

import

Remarks

The only reason for using `import` is to allow your code to refer to each imported class with the immediate class name only, rather than with the fully qualified class name. `import` is particularly useful in streamlining calls to constructors, where most references to Java classes occur.

Examples

This example shows importing and using the single class, `java.lang.String`, and two complete packages, `java.util` and `java.awt`.

```
import java.lang.String
import java.util.* java.awt.*
f = Frame;           % Create java.awt.Frame object
s = String('hello'); % Create java.lang.String object
methods Enumeration % List java.util.Enumeration methods
```

See Also

`clear`

Purpose	Load data from disk file.
Syntax	<pre>importdata('filename') A = importdata('filename') importdata('filename', 'delimiter')</pre>
Description	<p><code>importdata('filename')</code> loads data from <code>filename</code> into the workspace.</p> <p><code>A = importdata('filename')</code> loads data from <code>filename</code> into <code>A</code>.</p> <p><code>A = importdata('filename', 'delimiter')</code> loads data from <code>filename</code> using delimiter as the column separator (if text). Use '<code>\t</code>' for tab.</p>
Remarks	<p><code>importdata</code> looks at the file extension to determine which helper function to use. If it can recognize the file extension, <code>importdata</code> calls the appropriate helper function, specifying the maximum number of output arguments. If it cannot recognize the file extension, <code>importdata</code> calls <code>info</code> to determine which helper function to use. If no helper function is defined for this file extension, <code>importdata</code> treats the file as delimited text. <code>importdata</code> removes from the result empty outputs returned from the helper function.</p>
Examples	<pre>s = importdata('ding.wav') s = data: [11554x1 double] fs: 22050</pre>
See Also	<code>load</code>

imread

Purpose	Read image from graphics files
Syntax	<pre>A = imread(filename, fmt) [X, map] = imread(filename, fmt) [...] = imread(filename) [...] = imread(..., idx) (CUR, ICO, and TIFF only) [...] = imread(..., ref) (HDF only) [...] = imread(..., 'BackgroundColor', BG) (PNG only) [A, map, alpha] = imread(...) (PNG only)</pre>
Description	<p><code>A = imread(filename, <i>fmt</i>)</code> reads a grayscale or truecolor image named <code>filename</code> into <code>A</code>. If the file contains a grayscale intensity image, <code>A</code> is a two-dimensional array. If the file contains a truecolor (RGB) image, <code>A</code> is a three-dimensional (m-by-n-by-3) array.</p> <p><code>[X, map] = imread(filename, <i>fmt</i>)</code> reads the indexed image in <code>filename</code> into <code>X</code> and its associated colormap into <code>map</code>. The colormap values are rescaled to the range [0,1]. <code>A</code> and <code>map</code> are two-dimensional arrays.</p> <p><code>[...] = imread(filename)</code> attempts to infer the format of the file from its content.</p> <p><code>filename</code> is a string that specifies the name of the graphics file, and <code>fmt</code> is a string that specifies the format of the file. If the file is not in the current directory or in a directory in the MATLAB path, specify the full pathname for a location on your system. If <code>imread</code> cannot find a file named <code>filename</code>, it looks for a file named <code>filename.<i>fmt</i></code>. If you do not specify a string for <code>fmt</code>, the toolbox will try to discern the format of the file by checking the file header.</p>
	This table lists the possible values for <code>fmt</code> .
Format	File Type
'bmp'	Windows Bitmap (BMP)
'cur'	Windows Cursor resources (CUR)
'hdf'	Hierarchical Data Format (HDF)
'ico'	Windows Icon resources (ICO)

Format	File Type
'j pg' or 'j peg'	Joint Photographic Experts Group (JPEG)
'pcx'	Windows Paintbrush (PCX)
'png'	Portable Network Graphics (PNG)
'tif' or 'tiff'	Tagged Image File Format (TIFF)
'xwd'	X Windows Dump (XWD)

Special Case Syntax:

TIFF-Specific Syntax

[. . .] = imread(. . . , i dx) reads in one image from a multi-image TIFF file. i dx is an integer value that specifies the order in which the image appears in the file. For example, if i dx is 3, imread reads the third image in the file. If you omit this argument, imread reads the first image in the file.

PNG-Specific Syntax

The discussion in this section is only relevant to PNG files that contain transparent pixels. A PNG file does not necessarily contain transparency data. Transparent pixels, when they exist, will be identified by one of two components: a *transparency chunk* or an *alpha channel*. (A PNG file can only have one of these components, not both.)

The transparency chunk identifies which pixel values will be treated as transparent, e.g., if the value in the transparency chunk of an 8-bit image is 0.5020, all pixels in the image with the color 0.5020 can be displayed as transparent. An alpha channel is an array with the same number of pixels as are in the image, which indicates the transparency status of each corresponding pixel in the image (transparent or nontransparent).

Another potential PNG component related to transparency is the *background color chunk*, which (if present) defines a color value that can be used behind all transparent pixels. This section identifies the default behavior of the toolbox for reading PNG images that contain either a transparency chunk or an alpha channel, and describes how you can override it.

Case 1. You do not ask to output the alpha channel and do not specify a background color to use. For example,

```
[A, map] = imread(filename);  
A = imread(filename);
```

If the PNG file contains a background color chunk, the transparent pixels will be composited against the specified background color.

If the PNG file does not contain a background color chunk, the transparent pixels will be composited against 0 for grayscale (black), 1 for indexed (first color in map), or [0 0 0] for RGB (black).

Case 2. You do not ask to output the alpha channel but you specify the background color parameter in your call. For example,

```
[...] = imread(..., 'BackgroundColor', bg);
```

The transparent pixels will be composited against the specified color. The form of bg depends on whether the file contains an indexed, intensity (grayscale), or RGB image. If the input image is indexed, bg should be an integer in the range [1, P] where P is the colormap length. If the input image is intensity, bg should be an integer in the range [0,1]. If the input image is RGB, bg should be a three-element vector whose values are in the range [0,1].

There is one exception to the toolbox's behavior of using your background color. If you set background to 'none' no compositing will be performed. For example,

```
[...] = imread(..., 'Back', 'none');
```

Note If you specify a background color, you *cannot* output the alpha channel.

Case 3. You ask to get the alpha channel as an output variable. For example,

```
[A, map, al pha] = imread(filename);  
[A, map, al pha] = imread(filename, fmt);
```

No compositing is performed; the alpha channel will be stored separately from the image (not merged into the image as in cases 1 and 2). This form of imread returns the alpha channel if one is present, and also returns the image and any associated colormap. If there is no alpha channel, al pha returns []. If there is no colormap, or the image is grayscale or truecolor, map may be empty.

HDF-Specific Syntax

[...] = imread(..., ref) reads in one image from a multi-image HDF file. ref is an integer value that specifies the reference number used to identify the image. For example, if ref is 12, imread reads the image whose reference number is 12. (Note that in an HDF file the reference numbers do not necessarily correspond to the order of the images in the file. You can use imfinfo to match up image order with reference number.) If you omit this argument, imread reads the first image in the file.

CUR- and ICO-Specific Syntax

[...] = imread(..., idx) reads in one image from a multi-image icon or cursor file. idx is an integer value that specifies the order that the image appears in the file. For example, if idx is 3, imread reads the third image in the file. If you omit this argument, imread reads the first image in the file.

[A, map, alpha] = imread(...) returns the AND mask for the resource, which can be used to determine the transparency information. For cursor files, this mask may contain the only useful data.

Note By default, Microsoft Windows cursors are 32-by-32 pixels. MATLAB pointers must be 16-by-16. You will probably need to scale your image. If you have the Image Processing Toolbox, you can use the imresize function.

Format Support

This table summarizes the types of images that imread can read.

Format	Variants
BMP	1-bit, 4-bit, 8-bit, and 24-bit uncompressed images; 4-bit and 8-bit run-length encoded (RLE) images
CUR	1-bit, 4-bit, and 8-bit uncompressed images
HDF	8-bit raster image datasets, with or without associated colormap; 24-bit raster image datasets
ICO	1-bit, 4-bit, and 8-bit uncompressed images

imread

Format	Variants
JPEG	Any baseline JPEG image (8 or 24-bit); JPEG images with some commonly used extensions
PCX	1-bit, 8-bit, and 24-bit images
PNG	Any PNG image, including 1-bit, 2-bit, 4-bit, 8-bit, and 16-bit grayscale images; 8-bit and 16-bit indexed images; 24-bit and 48-bit RGB images
TIFF	Any baseline TIFF image, including 1-bit, 8-bit, and 24-bit uncompressed images; 1-bit, 8-bit, 16-bit, and 24-bit images with packbits compression; 1-bit images with CCITT compression; also 16-bit grayscale, 16-bit indexed, and 48-bit RGB images.
XWD	1-bit and 8-bit ZPixmaps; XYBitmaps; 1-bit XYPixmaps

Class Support In most of the image file formats supported by `imread`, pixels are stored using eight or fewer bits per color plane. When reading such a file, the class of the output (`A` or `X`) is `uint8`. `imread` also supports reading 16-bit-per-pixel data from TIFF and PNG files; for such image files, the class of the output (`A` or `X`) is `uint16`. Note that for indexed images, `imread` always reads the colormap into an array of class `double`, even though the image array itself may be of class `uint8` or `uint16`.

Remarks `imread` is a function in MATLAB.

Examples This example reads the sixth image in a TIFF file.

```
[X, map] = imread('flowers.tif', 6);
```

This example reads the fourth image in an HDF file.

```
iinfo = imfinfo('skull.hdf');  
[X, map] = imread('skull.hdf', iinfo(4).Reference);
```

This example reads a 24-bit PNG image and sets any of its fully transparent (alpha channel) pixels to red.

```
bg = [255 0 0];
```

```
A = imread('image.png', 'BackgroundColor', bg);
```

This example returns the alpha channel (if any) of a PNG image.

```
[A, map, al pha] = imread('image.png');
```

This example reads an ICO image, applies a transparency mask, and then displays the image.

```
[a, b, c] = imread('myicon.ico');
% Augment colormap for background color (white).
b2 = [b; 1 1 1];
% Create new image for display.
d = ones(size(a)) * (length(b2) - 1);
% Use the AND mask to mix the background and
% foreground data on the new image
d(c == 0) = a(c == 0);
% Display new image
imshow(uint8(d), b2)
```

See Also

[double](#), [fread](#), [imfinfo](#), [imwrite](#), [uint8](#), [uint16](#)

imwrite

Purpose	Write image to graphics file
Syntax	<pre>imwrite(A, filename, <i>fmt</i>) imwrite(X, map, filename, <i>fmt</i>) imwrite(..., filename) imwrite(..., Param1, Val 1, Param2, Val 2...)</pre>
Description	<p><code>imwrite(A, filename, <i>fmt</i>)</code> writes the image in <code>A</code> to <code>filename</code> in the format specified by <code>fmt</code>. <code>A</code> can be either a grayscale image (M-by-N) or a truecolor image (M-by-N-by-3). If <code>A</code> is of class <code>uint8</code> or <code>uint16</code>, <code>imwrite</code> writes the actual values in the array to the file. If <code>A</code> is of class <code>double</code>, <code>imwrite</code> rescales the values in the array before writing, using <code>uint8(round(255*A))</code>. This operation converts the floating-point numbers in the range [0,1] to 8-bit integers in the range [0,255].</p> <p><code>imwrite(X, map, filename, <i>fmt</i>)</code> writes the indexed image in <code>X</code> and its associated colormap <code>map</code> to <code>filename</code> in the format specified by <code>fmt</code>. If <code>X</code> is of class <code>uint8</code> or <code>uint16</code>, <code>imwrite</code> writes the actual values in the array to the file. If <code>X</code> is of class <code>double</code>, <code>imwrite</code> offsets the values in the array before writing using <code>uint8(X-1)</code>. (See note below for an exception.) <code>map</code> must be a valid MATLAB colormap of class <code>double</code>; <code>imwrite</code> rescales the values in <code>map</code> using <code>uint8(round(255*map))</code>. Note that most image file formats do not support colormaps with more than 256 entries.</p>

Note If the image is `double`, and you specify `PNG` as the output format and a bit depth of 16 bpp, the values in the array will be offset using `uint16(X-1)`.

`imwrite(..., filename)` writes the image to `filename`, inferring the format to use from the filename's extension. The extension must be one of the legal values for `fmt`.

`imwrite(..., Param1, Val 1, Param2, Val 2...)` specifies parameters that control various characteristics of the output file. Parameter settings can currently be made for `HDF`, `PNG`, `JPEG`, and `TIFF` files. For example, if you are writing a `JPEG` file, you can set the “quality” of the `JPEG` compression. For the lists of parameters available for each format, see the tables below.

`filename` is a string that specifies the name of the output file, and `fmt` is a string that specifies the format of the file.

This table lists the possible values for `fmt`.

Format	File Type
' <code>bmp</code> '	Windows Bitmap (BMP)
' <code>hdf</code> '	Hierarchical Data Format (HDF)
' <code>j pg</code> ' or ' <code>j peg</code> '	Joint Photographic Experts Group (JPEG)
' <code>pcx</code> '	Windows Paintbrush (PCX)
' <code>png</code> '	Portable Network Graphics (PNG)
' <code>tif</code> ' or ' <code>tiff</code> '	Tagged Image File Format (TIFF)
' <code>xwd</code> '	X Windows Dump (XWD)

This table describes the available parameters for HDF files.

Parameter	Values	Default
' <code>Compression</code> '	One of these strings: 'none' (the default), 'rl e', 'j peg'. 'rl e' is valid only for grayscale and indexed images. 'j peg' is valid only for grayscale and RGB images.	'rl e'
' <code>Quality</code> '	A number between 0 and 100; this parameter applies only if ' <code>Compression</code> ' is ' <code>j peg</code> '. Higher numbers mean higher <i>quality</i> (less image degradation due to compression), but the resulting file size is larger.	75
' <code>WriteMode</code> '	One of these strings: 'overwrite' (the default), or 'append'.	'overwrite'

imwrite

This table describes the available parameters for JPEG files.

Parameter	Values	Default
'Quality'	A number between 0 and 100; higher numbers mean higher <i>quality</i> (less image degradation due to compression), but the resulting file size is larger.	75

This table describes the available parameters for TIFF files.

Parameter	Values	Default
'Compression'	One of these strings: 'none', 'packbits', 'ccitt', 'fax3', or 'fax4'. The 'ccitt', 'fax3', and 'fax4' compression schemes are valid for binary images only.	'ccitt' for binary images; 'packbits' for nonbinary images
'Description'	Any string; fills in the ImageDescription field returned by <code>imfinfo</code> .	empty
'Resolution'	A two-element vector containing the XResolution and YResolution, or a scalar indicating both resolutions.	72
'WriteMode'	One of these strings: 'overwrite' or 'append'	'overwrite'

This table describes the available parameters for PNG files.

Parameter	Values	Default
'Author'	A string	Empty
'Description'	A string	Empty
'Copyright'	A string	Empty
'CreationTime'	A string	Empty
'Software'	A string	Empty
'Disclaimer'	A string	Empty

Parameter	Values	Default
'Warning'	A string	Empty
'Source'	A string	Empty
'Comment'	A string	Empty
'InterlaceType'	Either 'none' or 'adam7'	'none'
'BitDepth'	A scalar value indicating desired bit depth. For grayscale images this can be 1, 2, 4, 8, or 16. For grayscale images with an alpha channel this can be 8 or 16. For indexed images this can be 1, 2, 4, or 8. For truecolor images with or without an alpha channel this can be 8 or 16.	8 bits per pixel if image is double or uint8 16 bits per pixel if image is uint16 1 bit per pixel if image is logical
'Transparency'	<p>This value is used to indicate transparency information only when no alpha channel is used. Set to the value that indicates which pixels should be considered transparent. (If the image uses a colormap, this value will represent an index number to the colormap.)</p> <p>For indexed images: a Q- element vector in the range [0,1] where Q is no larger than the colormap length and each value indicates the transparency associated with the corresponding colormap entry. In most cases, Q=1.</p> <p>For grayscale images: a scalar in the range [0,1]. The value indicates the grayscale color to be considered transparent.</p> <p>For truecolor images: a three-element vector in the range [0,1]. The value indicates the truecolor color to be considered transparent.</p> <p>You cannot specify 'Transparency' and 'Alpha' at the same time.</p>	Empty

imwrite

Parameter	Values	Default
'Background'	The value specifies background color to be used when compositing transparent pixels. For indexed images: an integer in the range [1,P], where P is the colormap length. For grayscale images: a scalar in the range [0,1]. For truecolor images: a three-element vector in the range [0,1].	Empty
'Gamma'	A nonnegative scalar indicating the file gamma	Empty
'Chromaticities'	An eight-element vector [wx wy rx ry gx gy bx by] that specifies the reference white point and the primary chromaticities	Empty
'XResolution'	A scalar indicating the number of pixels/unit in the horizontal direction	Empty
'YResolution'	A scalar indicating the number of pixels/unit in the vertical direction	Empty
'ResolutionUnit'	Either 'unknown' or 'meter'	Empty
'Alpha'	A matrix specifying the transparency of each pixel individually. The row and column dimensions must be the same as the data array; they can be uint8, uint16, or double, in which case the values should be in the range [0,1].	Empty
'SignificantBits'	A scalar or vector indicating how many bits in the data array should be regarded as significant; values must be in the range [1,BitDepth]. For indexed images: a three-element vector. For grayscale images: a scalar. For grayscale images with an alpha channel: a two-element vector. For truecolor images: a three-element vector. For truecolor images with an alpha channel: a four-element vector	Empty

In addition to these PNG parameters, you can use any parameter name that satisfies the PNG specification for keywords, including only printable characters, 80 characters or fewer, and no leading or trailing spaces. The value corresponding to these user-specified parameters must be a string that contains no control characters other than linefeed.

Format Support

This table summarizes the types of images that `imwrite` can write.

Format	Variants
BMP	8-bit uncompressed images with associated colormap; 24-bit uncompressed images
HDF	8-bit raster image datasets, with or without associated colormap, 24-bit raster image datasets; uncompressed or with RLE or JPEG compression.
JPEG	Baseline JPEG images (8 or 24-bit). Note: Indexed images are converted to RGB before writing out JPEG files, because the JPEG format does not support indexed images.
PCX	8-bit images
PNG	1-bit, 2-bit, 4-bit, 8-bit, and 16-bit grayscale images; 8-bit and 16-bit grayscale images with alpha channels; 1-bit, 2-bit, 4-bit, and 8-bit indexed images; 24-bit and 48-bit truecolor images with or without alpha channels
TIFF	Baseline TIFF images, including 1-bit, 8-bit, and 24-bit uncompressed images; 1-bit, 8-bit, and 24-bit images with packbits compression; 1-bit images with CCITT 1D, Group 3, and Group 4 compression.
XWD	8-bit ZPixmaps

Class Support

Most of the supported image file formats store `uint8` data. PNG and TIFF additionally support `uint16` data. For grayscale and RGB images, if the data array is `double`, the assumed dynamic range is [0,1]. The data array is automatically scaled by 255 before being written out as `uint8`. If the data array is `uint8` or `uint16` (PNG and TIFF only), then it is written out without scaling as `uint8` or `uint16`, respectively.

Note If a logical double or uint8 is written to a PNG or TIFF file, it is assumed to be a binary image and will be written with a bit depth of 1.

For indexed images, if the index array is double, then the indices are first converted to zero-based indices by subtracting 1 from each element, and then they are written out as uint8. If the index array is uint8 or uint16 (PNG and TIFF only), then it is written out without modification as uint8 or uint16, respectively. When writing PNG files, you can override this behavior with the 'BitDepth' parameter; see the PNG table in this `imwrite` reference for details.

Remarks

`imwrite` is a function in MATLAB.

Example

This example appends an indexed image `X` and its colormap `map` to an existing uncompressed multipage HDF file named `flowers.hdf`.

```
imwrite(X, map, 'flowers.hdf', 'Compressi on', 'none', ...
'WriteMode', 'append')
```

See Also

`fwrite`, `imfinfo`, `imread`

Purpose	Convert an indexed image to an RGB image
Syntax	<code>RGB = ind2rgb(X, map)</code>
Description	<code>RGB = ind2rgb(X, map)</code> converts the matrix <code>X</code> and corresponding colormap <code>map</code> to RGB (truecolor) format.
Class Support	<code>X</code> can be of class <code>uint8</code> , <code>uint16</code> , or <code>double</code> . <code>RGB</code> is an <code>m</code> -by- <code>n</code> -3 array of class <code>double</code> .
See Also	<code>image</code>

ind2sub

Purpose	Subscripts from linear index
Syntax	$[I, J] = \text{ind2sub}(size, IND)$ $[I_1, I_2, I_3, \dots, I_n] = \text{ind2sub}(size, IND)$
Description	The <code>ind2sub</code> command determines the equivalent subscript values corresponding to a single index into an array.
	$[I, J] = \text{ind2sub}(size, IND)$ returns the arrays I and J containing the equivalent row and column subscripts corresponding to the index matrix IND for a matrix of size $size$.
	For matrices, $[I, J] = \text{ind2sub}(size(A), \text{find}(A>5))$ returns the same values as $[I, J] = \text{find}(A>5)$.
	$[I_1, I_2, I_3, \dots, I_n] = \text{ind2sub}(size, IND)$ returns n subscript arrays I_1, I_2, \dots, I_n containing the equivalent multidimensional array subscripts equivalent to IND for an array of size $size$.
Examples	The mapping from linear indexes to subscript equivalents for a 2-by-2-by-2 array is
See Also	<code>sub2ind</code> , <code>find</code>

Purpose	Infinity
Syntax	<code>inf</code>
Description	<code>Inf</code> returns the IEEE arithmetic representation for positive infinity. Infinity results from operations like division by zero and overflow, which lead to results too large to represent as conventional floating-point values.
Examples	<code>1/0</code> , <code>1. e1000</code> , <code>2^1000</code> , and <code>exp(1000)</code> all produce <code>Inf</code> . <code>log(0)</code> produces <code>-Inf</code> . <code>Inf - Inf</code> and <code>Inf / Inf</code> both produce <code>NaN</code> (Not-a-Number).
See Also	<code>isinf</code> , <code>NaN</code>

inferiorito

Purpose	Inferior class relationship
Syntax	<code>inferiorito('class1', 'class2', ...)</code>
Description	The <code>inferiorito</code> function establishes a hierarchy which determines the order in which MATLAB calls object methods. <code>inferiorito('class1', 'class2', ...)</code> invoked within a class constructor method (say <code>myclass.m</code>) indicates that <code>myclass</code> 's method should not be invoked if a function is called with an object of class <code>myclass</code> and one or more objects of class <code>class1</code> , <code>class2</code> , and so on.
Remarks	Suppose A is of class ' <code>class_a</code> ', B is of class ' <code>class_b</code> ' and C is of class ' <code>class_c</code> '. Also suppose the constructor <code>class_c.m</code> contains the statement: <code>inferiorito('class_a')</code> . Then <code>e = fun(a, c)</code> or <code>e = fun(c, a)</code> invokes <code>class_a.fun</code> . If a function is called with two objects having an unspecified relationship, the two objects are considered to have equal precedence, and the leftmost object's method is called. So, <code>fun(b, c)</code> calls <code>class_b.fun</code> , while <code>fun(c, b)</code> calls <code>class_c.fun</code> .
See Also	<code>superiorito</code>

Purpose	Display information about The MathWorks or products
Syntax	<code>info</code> <code>info tool box</code>
Description	<code>info</code> displays contact information about MATLAB and The MathWorks in the Command Window, including phone and fax numbers and e-mail addresses. <code>info tool box</code> displays the Readme file for the specified toolbox in the Help browser. If the Readme file does not exist, the Release Notes for the specified toolbox are displayed instead. These documents contain information about problems from previous releases that have been fixed in the current release.

inline

Purpose	Construct an inline object
Syntax	<pre>g = inline(expr) g = inline(expr, arg1, arg2, ...) g = inline(expr, n)</pre>
Description	<p><code>inline(expr)</code> constructs an inline function object from the MATLAB expression contained in the string <code>expr</code>. The input argument to the inline function is automatically determined by searching <code>expr</code> for an isolated lower case alphabetic character, other than <code>i</code> or <code>j</code>, that is not part of a word formed from several alphabetic characters. If no such character exists, <code>x</code> is used. If the character is not unique, the one closest to <code>x</code> is used. If two characters are found, the one later in the alphabet is chosen.</p> <p><code>inline(expr, arg1, arg2, ...)</code> constructs an inline function whose input arguments are specified by the strings <code>arg1</code>, <code>arg2</code>, ... Multicharacter symbol names may be used.</p> <p><code>inline(expr, n)</code> where <code>n</code> is a scalar, constructs an inline function whose input arguments are <code>x</code>, <code>P1</code>, <code>P2</code>,</p>
Remarks	<p>Three commands related to <code>inline</code> allow you to examine an inline function object and determine how it was created.</p> <p><code>char(fun)</code> converts the inline function into a character array. This is identical to <code>formula(fun)</code>.</p> <p><code>argnames(fun)</code> returns the names of the input arguments of the inline object <code>fun</code> as a cell array of strings.</p> <p><code>formula(fun)</code> returns the formula for the inline object <code>fun</code>.</p> <p>A fourth command <code>vectorize(fun)</code> inserts a <code>.</code> before any <code>^</code>, <code>*</code> or <code>/</code> in the formula for <code>fun</code>. The result is a vectorized version of the inline function.</p>
Examples	<p>Example 1. This example creates a simple inline function to square a number.</p> <pre>g = inline('t^2') g =</pre> <p>In line function:</p>

```
g(t) = t^2
```

You can convert the result to a string using the `char` function.

```
char(g)
```

```
ans =
```

```
t^2
```

Example 2. This example creates an inline function to represent the formula $f = 3 \sin(2x^2)$. The resulting inline function can be evaluated with the `argnames` and `formul a` functions.

```
f = inline('3*sin(2*x.^2)')
```

```
f =
```

```
Inline function:
```

```
f(x) = 3*sin(2*x.^2)
```

```
argnames(f)
```

```
ans =
```

```
'x'
```

```
formul a(f)
```

```
ans =
```

```
3*sin(2*x.^2) ans =
```

Example 3. This call to `inline` defines the function `f` to be dependent on two variables, `al pha` and `x`:

```
f = inline('sin(al pha*x)')
```

```
f =
```

```
Inline function:
```

```
f(al pha, x) = sin(al pha*x)
```

If `inline` does not return the desired function variables or if the function variables are in the wrong order, you can specify the desired variables explicitly with the `inline` argument list.

inline

```
g = inline('sin(al pha*x)', 'x', 'al pha')
```


```
g =
```

```
Inline function:  
g(x, al pha) = sin(al pha*x)
```

Purpose	Return functions in memory
Syntax	<code>M = inmem</code> <code>[M, X] = inmem</code> <code>[M, X, J] = inmem</code>
Description	<code>M = inmem</code> returns a cell array of strings containing the names of the M-files that are currently loaded. <code>[M, X] = inmem</code> returns an additional cell array, <code>X</code> , containing the names of the MEX-files that are currently loaded. <code>[M, X, J] = inmem</code> also returns a cell array, <code>J</code> , containing the names of the Java classes that are currently loaded.
Examples	This example lists the M-files that are required to run <code>erf</code> . <pre>clear all; % Clear the workspace erf(0.5); M = inmem</pre> <code>M =</code> <code>'erf'</code>
See Also	<code>clear</code>

inpolygon

Purpose	Detect points inside a polygonal region
Syntax	<code>IN = inpolygon(X, Y, xv, yv)</code>
Description	<code>IN = inpolygon(X, Y, xv, yv)</code> returns a matrix <code>IN</code> the same size as <code>X</code> and <code>Y</code> . Each element of <code>IN</code> is assigned one of the values 1, 0.5 or 0, depending on whether the point $(X(p, q), Y(p, q))$ is inside the polygonal region whose vertices are specified by the vectors <code>xv</code> and <code>yv</code> . In particular:
	$IN(p, q) = 1$ If $(X(p, q), Y(p, q))$ is inside the polygonal region
	$IN(p, q) = 0.5$ If $(X(p, q), Y(p, q))$ is on the polygon boundary
	$IN(p, q) = 0$ If $(X(p, q), Y(p, q))$ is outside the polygonal region
Examples	<pre>L = linspace(0, 2.*pi, 6); xv = cos(L)'; yv = sin(L)'; xv = [xv ; xv(1)]; yv = [yv ; yv(1)]; x = randn(250, 1); y = randn(250, 1); in = inpolygon(x, y, xv, yv); plot(xv, yv, x(in), y(in), 'r+', x(~in), y(~in), 'bo')</pre>




Purpose	Request user input
Syntax	<pre>user_entry = input('prompt') user_entry = input('prompt', 's')</pre>
Description	The response to the <code>input</code> prompt can be any MATLAB expression, which is evaluated using the variables in the current workspace. <code>user_entry = input('prompt')</code> displays <i>prompt</i> as a prompt on the screen, waits for input from the keyboard, and returns the value entered in <code>user_entry</code> . <code>user_entry = input('prompt', 's')</code> returns the entered string as a text variable rather than as a variable name or numerical value.
Remarks	If you press the Return key without entering anything, <code>input</code> returns an empty matrix. The text string for the prompt may contain one or more ' <code>\n</code> ' characters. The ' <code>\n</code> ' means to skip to the next line. This allows the prompt string to span several lines. To display just a backslash, use ' <code>\\"</code> '.
Examples	Press Return to select a default value by detecting an empty matrix: <pre>reply = input('Do you want more? Y/N [Y]: ', 's'); if isempty(reply) reply = 'Y'; end</pre>
See Also	<code>keyboard</code> , <code>menu</code> , <code>input</code> , <code>ui control</code>

inputdlg

Purpose	Create input dialog box
Syntax	<pre>answer = inputdlg(prompt) answer = inputdlg(prompt, title) answer = inputdlg(prompt, title, lineNo) answer = inputdlg(prompt, title, lineNo, defAns) answer = inputdlg(prompt, title, lineNo, defAns, Resize)</pre>
Description	<p><code>answer = inputdlg(prompt)</code> creates a modal dialog box and returns user inputs in the cell array. <code>prompt</code> is a cell array containing prompt strings.</p> <p><code>answer = inputdlg(prompt, title)</code> <code>title</code> specifies a title for the dialog box.</p> <p><code>answer = inputdlg(prompt, title, lineNo)</code> <code>lineNo</code> specifies the number of lines for each user entered value. <code>lineNo</code> can be a scalar, column vector, or matrix.</p> <ul style="list-style-type: none">• If <code>lineNo</code> is a scalar, it applies to all prompts.• If <code>lineNo</code> is a column vector, each element specifies the number of lines of input for a prompt.• If <code>lineNo</code> is a matrix, it should be size m-by-2, where m is the number of prompts on the dialog box. Each row refers to a prompt. The first column specifies the number of lines of input for a prompt. The second column specifies the width of the field in characters. <p><code>answer = inputdlg(prompt, title, lineNo, defAns)</code> <code>defAns</code> specifies the default value to display for each prompt. <code>defAns</code> must contain the same number of elements as <code>prompt</code> and all elements must be strings.</p> <p><code>answer = inputdlg(prompt, title, lineNo, defAns, Resize)</code> <code>Resize</code> specifies whether or not the dialog box can be resized. Permissible values are 'on' and 'off' where 'on' means that the dialog box can be resized and that the dialog box is not modal.</p>
Example	Create a dialog box to input an integer and colormap name. Allow one line for each value.
	<pre>prompt = {'Enter matrix size:', 'Enter colormap name:'}; title = 'Input for peaks function';</pre>

```
lines= 1;  
def     = {'20', ' hsv'};  
answer = inputdlg(prompt, title, lines, def);
```



See Also

[dialog](#), [errordlg](#), [helpdlg](#), [questdlg](#), [warndlg](#)

inputname

Purpose	Input argument name
Syntax	<code>inputname(argnum)</code>
Description	This command can be used only inside the body of a function. <code>inputname(argnum)</code> returns the workspace variable name corresponding to the argument number <code>argnum</code> . If the input argument has no name (for example, if it is an expression instead of a variable), the <code>inputname</code> command returns the empty string ('').
Examples	Suppose the function <code>myfun.m</code> is defined as: <pre>function c = myfun(a, b) disp(sprintf('First calling variable is "%s". ', inputname(1)))</pre> Then <code>x = 5; y = 3; myfun(x, y)</code> produces <code>First calling variable is "x".</code> But <code>myfun(pi+1, pi - 1)</code> produces <code>First calling variable is "".</code>
See Also	<code>nargin</code> , <code>nargout</code> , <code>nargchk</code>

Purpose	Start the Property Inspector
Syntax	<code>i nspect</code>
Description	<code>i nspect</code> displays the Property Inspector, which enables you to inspect and set the properties of any object you select in the figure window or Layout Editor.
See Also	<code>gui de</code>

instrcallback

Purpose	Display event information when an event occurs	
Syntax	instrcallback(obj, event)	
Arguments	obj	An serial port object.
	event	The event that caused the callback to execute.
Description	instrcallback(obj, event) displays a message that contains the event type, the time the event occurred, and the name of the serial port object that caused the event to occur. For error events, the error message is also displayed. For pin status events, the pin that changed value and its value are also displayed.	
Remarks	You should use instrcallback as a template from which you create callback functions that suit your specific application needs.	
Example	The following example creates the serial port objects s, and configures s to execute instrcallback when an output-empty event occurs. The event occurs after the *IDN? command is written to the instrument. <pre>s = serial('COM1'); set(s, 'OutputEmptyFcn', @instrcallback) fopen(s) fprintf(s, '*IDN?', 'async')</pre>	
	The resulting display from instrcallback is shown below.	
	<pre>OutputEmpty event occurred at 08:37:49 for the object: Serial - COM1.</pre>	
	Read the identification information from the input buffer and end the serial port session.	
	<pre>i dn = fscanf(s); fclose(s) delete(s) clear s</pre>	

Purpose	Return serial port objects from memory to the MATLAB workspace
Syntax	<pre>out = instrfind out = instrfind('PropertyName', PropertyValue, . . .) out = instrfind(S) out = instrfind(obj, 'PropertyName', PropertyValue, . . .)</pre>
Arguments	<p>'<i>PropertyName</i>' A property name for <i>obj</i>.</p> <p><i>PropertyValue</i> A property value supported by <i>PropertyName</i>.</p> <p><i>S</i> A structure of property names and property values.</p> <p><i>obj</i> A serial port object, or an array of serial port objects.</p> <p><i>out</i> An array of serial port objects.</p>
Description	<p><i>out</i> = <i>instrfind</i> returns all valid serial port objects as an array to <i>out</i>.</p> <p><i>out</i> = <i>instrfind</i>('<i>PropertyName</i>', <i>PropertyValue</i>, . . .) returns an array of serial port objects whose property names and property values match those specified.</p> <p><i>out</i> = <i>instrfind</i>(<i>S</i>) returns an array of serial port objects whose property names and property values match those defined in the structure <i>S</i>. The field names of <i>S</i> are the property names, while the field values are the associated property values.</p> <p><i>out</i> = <i>instrfind</i>(<i>obj</i>, '<i>PropertyName</i>', <i>PropertyValue</i>, . . .) restricts the search for matching property name/property value pairs to the serial port objects listed in <i>obj</i>.</p>
Remarks	<p>Refer to “Displaying Property Names and Property Values” for a list of serial port object properties that you can use with <i>instrfind</i>.</p> <p>You must specify property values using the same format as the <i>get</i> function returns. For example, if <i>get</i> returns the <i>Name</i> property value as <i>MyObj</i> ect, <i>instrfind</i> will not find an object with a <i>Name</i> property value of <i>myobj</i> ect. However, this is not the case for properties that have a finite set of string</p>

instrfind

values. For example, `instrfind` will find an object with a `Parity` property value of `Even` or `even`.

You can use property name/property value string pairs, structures, and cell array pairs in the same call to `instrfind`.

Example

Suppose you create the following two serial port objects.

```
s1 = serial('COM1');
s2 = serial('COM2');
set(s2, 'BaudRate', 4800)
fopen([s1 s2])
```

You can use `instrfind` to return serial port objects based on property values.

```
out1 = instrfind('Port', 'COM1');
out2 = instrfind({'Port', 'BaudRate'}, {'COM2', 4800});
```

You can also use `instrfind` to return cleared serial port objects to the MATLAB workspace.

```
clear s1 s2
newobjs = instrfind
```

Instrument Object Array			
Index:	Type:	Status:	Name:
1	serial	open	Serial - COM1
2	serial	open	Serial - COM2

To close both `s1` and `s2`

```
fclose(newobjs)
```

See Also

Functions

`clear`, `get`

Purpose	Integer to string conversion
Syntax	<code>str = int2str(N)</code>
Description	<code>str = int2str(N)</code> converts an integer to a string with integer format. The input <code>N</code> can be a single integer or a vector or matrix of integers. Noninteger inputs are rounded before conversion.
Examples	<code>int2str(2+3)</code> is the string ' <code>5</code> '. One way to label a plot is <code>title(['case number ' int2str(n)])</code> For matrix or vector inputs, <code>int2str</code> returns a string matrix: <code>int2str(eye(3))</code> <code>ans =</code> <code>1 0 0</code> <code>0 1 0</code> <code>0 0 1</code>
See Also	<code>fprintf</code> , <code>num2str</code> , <code>sprintf</code>

int8, int16, int32

Purpose	Convert to signed integer			
Syntax	<code>i = int8(x)</code> <code>i = int16(x)</code> <code>i = int32(x)</code>			
Description	<code>i = int*(x)</code> converts the vector <code>x</code> into a signed integer. <code>x</code> can be any numeric object (such as a <code>double</code>). The results of an <code>int*</code> operation are shown in the next table.			
<hr/>				
Operation	Output Range	Output Type	Bytes per Element	Output Class
<code>int8</code>	-128 to 127	Signed 8-bit integer	1	<code>int8</code>
<code>int16</code>	-32768 to 32767	Signed 16-bit integer	2	<code>int16</code>
<code>int32</code>	-2147483648 to 2147483647	Signed 32-bit integer	4	<code>int32</code>

A value of `x` above or below the range for a class is mapped to one of the endpoints of the range. If `x` is already a signed integer of the same class, `int*` has no effect.

The `int*` class is primarily meant to store integer values. Most operations that manipulate arrays without changing their elements are defined (examples are `reshape`, `size`, the logical and relational operators, subscripted assignment, and subscripted reference). No math operations except for `sum` are defined for `int*` since such operations are ambiguous on the boundary of the set (for example, they could wrap or truncate there). You can define your own methods for `int*` (as you can for any object) by placing the appropriately named method in an `@int*` directory within a directory on your path.


Type `help_datatypes` for the names of the methods you can overload.

See Also `double`, `single`, `uint8`, `uint16`, `uint32`

Purpose	One-dimensional data interpolation (table lookup)
Syntax	<pre>yi = interp1(x, Y, xi) yi = interp1(Y, xi) yi = interp1(x, Y, xi, method) yi = interp1(x, Y, xi, method, 'extrap') yi = interp1(x, Y, xi, method, extrapval)</pre>
Description	<p><code>yi = interp1(x, Y, xi)</code> returns vector <code>yi</code> containing elements corresponding to the elements of <code>xi</code> and determined by interpolation within vectors <code>x</code> and <code>Y</code>. The vector <code>x</code> specifies the points at which the data <code>Y</code> is given. If <code>Y</code> is a matrix, then the interpolation is performed for each column of <code>Y</code> and <code>yi</code> is <code>length(xi)</code>-by-<code>size(Y, 2)</code>.</p> <p><code>yi = interp1(Y, xi)</code> assumes that <code>x = 1:N</code>, where <code>N</code> is the length of <code>Y</code> for vector <code>Y</code>, or <code>size(Y, 1)</code> for matrix <code>Y</code>.</p> <p><code>yi = interp1(x, Y, xi, method)</code> interpolates using alternative methods:</p> <ul style="list-style-type: none"> 'nearest' Nearest neighbor interpolation 'linear' Linear interpolation (default) 'spline' Cubic spline interpolation 'pchip' Piecewise cubic Hermite interpolation 'cubic' (Same as 'pchip') 'v5cubic' Cubic interpolation used in MATLAB 5 <p>For the 'nearest', 'linear', and 'v5cubic' methods, <code>interp1(x, Y, xi, method)</code> returns NaN for any element of <code>xi</code> that is outside the interval spanned by <code>x</code>. For all other methods, <code>interp1</code> performs extrapolation for out of range values.</p> <p><code>yi = interp1(x, Y, xi, method, 'extrap')</code> uses the specified method to perform extrapolation for out of range values.</p> <p><code>yi = interp1(x, Y, xi, method, extrapval)</code> returns the scalar <code>extrapval</code> for out of range values. NaN and 0 are often used for <code>extrapval</code>.</p>

interp1

The `interp1` command interpolates between data points. It finds values at intermediate points, of a one-dimensional function $f(x)$ that underlies the data. This function is shown below, along with the relationship between vectors x , Y , xi , and yi .




Interpolation is the same operation as *table lookup*. Described in table lookup terms, the *table* is $[x, Y]$ and `interp1` *looks up* the elements of xi in x , and, based upon their locations, returns values yi interpolated within the elements of Y .

Note `interp1q` is quicker than `interp1` on non-uniformly spaced data because it does no input checking. For `interp1q` to work properly, x must be a monotonically increasing column vector and Y must be a column vector or matrix with `length(X)` rows. Type `help interp1q` at the command line for more information.

Examples

Example 1. Generate a coarse sine curve and interpolate over a finer abscissa.

```
x = 0: 10;  
y = sin(x);  
xi = 0: .25: 10;  
yi = interp1(x, y, xi);  
plot(x, y, 'o', xi, yi)
```



Example 2. Here are two vectors representing the census years from 1900 to 1990 and the corresponding United States population in millions of people.

```
t = 1900:10:1990;
p = [ 75.995 91.972 105.711 123.203 131.669...
      150.697 179.323 203.212 226.505 249.633];
```


The expression `interp1(t, p, 1975)` interpolates within the census data to estimate the population in 1975. The result is

```
ans =
214.8585
```

Now interpolate within the data at every year from 1900 to 2000, and plot the result.

```
x = 1900:1:2000;
y = interp1(t, p, x, 'spline');
plot(t, p, 'o', x, y)
```

interp1



Sometimes it is more convenient to think of interpolation in table lookup terms, where the data are stored in a single table. If a portion of the census data is stored in a single 5-by-2 table,

```
tab =  
    1950    150.697  
    1960    179.323  
    1970    203.212  
    1980    226.505  
    1990    249.633
```

then the population in 1975, obtained by table lookup within the matrix `tab`, is

```
p = interp1(tab(:, 1), tab(:, 2), 1975)  
p =  
    214.8585
```

Algorithm

The `interp1` command is a MATLAB M-file. The 'nearest' and 'linear' methods have straightforward implementations.

For the 'spline' method, `interp1` calls a function `spline` that uses the functions `ppval`, `mkpp`, and `unmkpp`. These routines form a small suite of functions for working with piecewise polynomials. `spline` uses them to

perform the cubic spline interpolation. For access to more advanced features, see the `spline` reference page, the M-file help for these functions, and the Spline Toolbox.

For the '`pchip`' and '`cubic`' methods, `interp1` calls a function `pchip` that performs piecewise cubic interpolation within the vectors `x` and `y`. This method preserves monotonicity and the shape of the data. See the `pchip` reference page for more information.

See Also

`interpft`, `interp2`, `interp3`, `interpn`, `pchip`, `spline`

References

[1] de Boor, C., *A Practical Guide to Splines*, Springer-Verlag, 1978.


interp2

Purpose	Two-dimensional data interpolation (table lookup)
Syntax	<pre>ZI = interp2(X, Y, Z, XI, YI) ZI = interp2(Z, XI, YI) ZI = interp2(Z, ntimes) ZI = interp2(X, Y, Z, XI, YI, method)</pre>
Description	<p><code>ZI = interp2(X, Y, Z, XI, YI)</code> returns matrix <code>ZI</code> containing elements corresponding to the elements of <code>XI</code> and <code>YI</code> and determined by interpolation within the two-dimensional function specified by matrices <code>X</code>, <code>Y</code>, and <code>Z</code>. <code>X</code> and <code>Y</code> must be monotonic, and have the same format ("plaid") as if they were produced by <code>meshgrid</code>. Matrices <code>X</code> and <code>Y</code> specify the points at which the data <code>Z</code> is given. Out of range values are returned as NaNs.</p> <p><code>XI</code> and <code>YI</code> can be matrices, in which case <code>interp2</code> returns the values of <code>Z</code> corresponding to the points $(XI(i, j), YI(i, j))$. Alternatively, you can pass in the row and column vectors <code>xi</code> and <code>yi</code>, respectively. In this case, <code>interp2</code> interprets these vectors as if you issued the command <code>meshgrid(xi, yi)</code>.</p> <p><code>ZI = interp2(Z, XI, YI)</code> assumes that <code>X = 1:n</code> and <code>Y = 1:m</code>, where <code>[m, n] = size(Z)</code>.</p> <p><code>ZI = interp2(Z, ntimes)</code> expands <code>Z</code> by interleaving interpolates between every element, working recursively for <code>ntimes</code>. <code>interp2(Z)</code> is the same as <code>interp2(Z, 1)</code>.</p> <p><code>ZI = interp2(X, Y, Z, XI, YI, method)</code> specifies an alternative interpolation method:</p> <ul style="list-style-type: none">'nearest' Nearest neighbor interpolation'linear' Bilinear interpolation (default)'spline' Cubic spline interpolation'cubic' Bicubic interpolation <p>All interpolation methods require that <code>X</code> and <code>Y</code> be monotonic, and have the same format ("plaid") as if they were produced by <code>meshgrid</code>. If you provide two monotonic vectors, <code>interp2</code> changes them to a plaid internally. Variable spacing is handled by mapping the given values in <code>X</code>, <code>Y</code>, <code>XI</code>, and <code>YI</code> to an equally</p>

spaced domain before interpolating. For faster interpolation when X and Y are equally spaced and monotonic, use the methods '**li near*', '**cubic*', '**spline*', or '**nearest*'.

Remarks

The `interp2` command interpolates between data points. It finds values of a two-dimensional function $f(x, y)$ underlying the data at intermediate points.




Interpolation is the same operation as table lookup. Described in table lookup terms, the table is `tab = [NaN, Y; X, Z]` and `interp2` looks up the elements of `XI` in `X`, `YI` in `Y`, and, based upon their location, returns values `ZI` interpolated within the elements of `Z`.

Examples

Example 1. Interpolate the peaks function over a finer grid.

```
[X, Y] = meshgrid(-3: .25: 3);
Z = peaks(X, Y);
[XI, YI] = meshgrid(-3: .125: 3);
ZI = interp2(X, Y, Z, XI, YI);
mesh(X, Y, Z), hold, mesh(XI, YI, ZI+15)
hold off
axis([-3 3 -3 3 -5 20])
```

interp2



Example 2. Given this set of employee data,

```
years = 1950:10:1990;
service = 10:10:30;
wage = [ 150.697 199.592 187.625
         179.323 195.072 250.287
         203.212 179.092 322.767
         226.505 153.706 426.730
         249.633 120.281 598.243];
```

it is possible to interpolate to find the wage earned in 1975 by an employee with 15 years' service:

```
w = interp2(service, years, wage, 15, 1975)
w =
    190.6287
```


See Also

`griddata`, `interp1`, `interp3`, `interpn`, `meshgrid`

Purpose	Three-dimensional data interpolation (table lookup)								
Syntax	<pre>VI = interp3(X, Y, Z, V, XI, YI, ZI) VI = interp3(V, XI, YI, ZI) VI = interp3(V, ntimes) VI = interp3(..., method)</pre>								
Description	<p><code>VI = interp3(X, Y, Z, V, XI, YI, ZI)</code> interpolates to find <code>VI</code>, the values of the underlying three-dimensional function <code>V</code> at the points in arrays <code>XI, YI</code> and <code>ZI</code>. <code>XI, YI, ZI</code> must be arrays of the same size, or vectors. Vector arguments that are not the same size, and have mixed orientations (i.e. with both row and column vectors) are passed through <code>meshgrid</code> to create the <code>Y1, Y2, Y3</code> arrays. Arrays <code>X, Y</code>, and <code>Z</code> specify the points at which the data <code>V</code> is given. Out of range values are returned as NaN.</p> <p><code>VI = interp3(V, XI, YI, ZI)</code> assumes <code>X=1:N, Y=1:M, Z=1:P</code> where <code>[M, N, P]=size(V)</code>.</p> <p><code>VI = interp3(V, ntimes)</code> expands <code>V</code> by interleaving interpolates between every element, working recursively for <code>ntimes</code> iterations. The command <code>interp3(V)</code> is the same as <code>interp3(V, 1)</code>.</p> <p><code>VI = interp3(..., method)</code> specifies alternative methods:</p> <table> <tr> <td>'linear'</td> <td>Linear interpolation (default)</td> </tr> <tr> <td>'cubic'</td> <td>Cubic interpolation</td> </tr> <tr> <td>'spline'</td> <td>Cubic spline interpolation</td> </tr> <tr> <td>'nearest'</td> <td>Nearest neighbor interpolation</td> </tr> </table>	'linear'	Linear interpolation (default)	'cubic'	Cubic interpolation	'spline'	Cubic spline interpolation	'nearest'	Nearest neighbor interpolation
'linear'	Linear interpolation (default)								
'cubic'	Cubic interpolation								
'spline'	Cubic spline interpolation								
'nearest'	Nearest neighbor interpolation								
Discussion	All the interpolation methods require that <code>X, Y</code> and <code>Z</code> be monotonic and have the same format ("plaid") as if they were created using <code>meshgrid</code> . <code>X, Y</code> , and <code>Z</code> can be non-uniformly spaced. For faster interpolation when <code>X, Y</code> , and <code>Z</code> are equally spaced and monotonic, use the methods ' <code>*linear</code> ', ' <code>*cubic</code> ', or ' <code>*nearest</code> '.								
Examples	To generate a coarse approximation of <code>flow</code> and interpolate over a finer mesh:								
	<pre>[x, y, z, v] = flow(10); [xi, yi, zi] = meshgrid(.1:.25:10, -3:.25:3, -3:.25:3);</pre>								

interp3

```
vi = interp3(x, y, z, v, xi, yi, zi); % vi is 25-by-40-by-25  
slice(xi, yi, zi, vi, [6 9.5], 2, [-2 .2]), shading flat
```



See Also

[interp1](#), [interp2](#), [interpn](#), [meshgrid](#)

Purpose	One-dimensional interpolation using the FFT method
Syntax	$y = \text{interpft}(x, n)$ $y = \text{interpft}(x, n, dim)$
Description	$y = \text{interpft}(x, n)$ returns the vector y that contains the value of the periodic function x resampled to n equally spaced points. If $\text{length}(x) = m$, and x has sample interval dx , then the new sample interval for y is $dy = dx*m/n$. Note that n cannot be smaller than m . If X is a matrix, interpft operates on the columns of X , returning a matrix Y with the same number of columns as X , but with n rows. $y = \text{interpft}(x, n, dim)$ operates along the specified dimension.
Algorithm	The interpft command uses the FFT method. The original vector x is transformed to the Fourier domain using fft and then transformed back with more points.
See Also	interp1

interpн

Purpose	Multidimensional data interpolation (table lookup)
Syntax	<pre>VI = interpн(X1, X2, X3, ..., V, Y1, Y2, Y3, ...) VI = interpн(V, Y1, Y2, Y3, ...) VI = interpн(V, ntimes) VI = interpн(..., method)</pre>
Description	<p><code>VI = interpн(X1, X2, X3, ..., V, Y1, Y2, Y3, ...)</code> interpolates to find <code>VI</code>, the values of the underlying multidimensional function <code>V</code> at the points in the arrays <code>Y1</code>, <code>Y2</code>, <code>Y3</code>, etc. For an <code>N</code>-D <code>V</code>, <code>interpн</code> is called with $2^N + 1$ arguments. Arrays <code>X1</code>, <code>X2</code>, <code>X3</code>, etc. specify the points at which the data <code>V</code> is given. Out of range values are returned as NaNs. <code>Y1</code>, <code>Y2</code>, <code>Y3</code>, etc. must be arrays of the same size, or vectors. Vector arguments that are not the same size, and have mixed orientations (i.e. with both row and column vectors) are passed through <code>ndgrid</code> to create the <code>Y1</code>, <code>Y2</code>, <code>Y3</code>, etc. arrays. <code>interpн</code> works for all <code>N</code>-D arrays with 2 or more dimensions.</p> <p><code>VI = interpн(V, Y1, Y2, Y3, ...)</code> interpolates as above, assuming <code>X1 = 1:size(V, 1), X2 = 1:size(V, 2), X3 = 1:size(V, 3)</code>, etc.</p> <p><code>VI = interpн(V, ntimes)</code> expands <code>V</code> by interleaving interpolates between each element, working recursively for <code>ntimes</code> iterations. <code>interpн(V, 1)</code> is the same as <code>interpн(V)</code>.</p> <p><code>VI = interpн(..., method)</code> specifies alternative methods:</p> <ul style="list-style-type: none">'linear' Linear interpolation (default)'cubic' Cubic interpolation'spline' Cubic spline interpolation'nearest' Nearest neighbor interpolation
Discussion	All the interpolation methods require that <code>X1, X2</code> , and <code>X3</code> be monotonic and have the same format ("plaid") as if they were created using <code>ndgrid</code> . <code>X1, X2, X3, ...</code> and <code>Y1, Y2, Y3</code> , etc. can be non-uniformly spaced. For faster interpolation when <code>X1, X2, X3</code> , etc. are equally spaced and monotonic, use the methods ' <code>*linear</code> ', ' <code>*cubic</code> ', or ' <code>*nearest</code> '.

See Also

`interp1`, `interp2`, `interp3`, `ndgrid`

interpstreamspeed

Purpose	Interpolate stream line vertices from flow speed
Syntax	<pre>interpstreamspeed(X, Y, Z, U, V, W, vertices) interpstreamspeed(U, V, W, vertices) interpstreamspeed(X, Y, Z, speed, vertices) interpstreamspeed(speed, vertices) interpstreamspeed(X, Y, U, V, vertices) interpstreamspeed(U, V, vertices) interpstreamspeed(X, Y, speed, vertices) interpstreamspeed(speed, vertices) interpstreamspeed(. . . , sf) vertsout = interpstreamspeed(. . .)</pre>
Description	<p><code>interpstreamspeed(X, Y, Z, U, V, W, vertices)</code> interpolates stream line vertices based on the magnitude of the vector data <code>U, V, W</code>. The arrays <code>X, Y, Z</code> define the coordinates for <code>U, V, W</code> and must be monotonic and 3-D plaid (as if produced by <code>meshgrid</code>).</p> <p><code>interpstreamspeed(U, V, W, vertices)</code> assumes <code>X, Y, and Z</code> are determined by the expression:</p> $[X \ Y \ Z] = \text{meshgrid}(1:n, 1:m, 1:p)$ <p>where $[m \ n \ p] = \text{size}(U)$.</p> <p><code>interpstreamspeed(X, Y, Z, speed, vertices)</code> uses the 3-D array <code>speed</code> for the speed of the vector field.</p> <p><code>interpstreamspeed(speed, vertices)</code> assumes <code>X, Y, and Z</code> are determined by the expression:</p> $[X \ Y \ Z] = \text{meshgrid}(1:n, 1:m, 1:p)$ <p>where $[m \ n \ p] = \text{size}(speed)$.</p> <p><code>interpstreamspeed(X, Y, U, V, vertices)</code> interpolates streamline vertices based on the magnitude of the vector data <code>U, V</code>. The arrays <code>X, Y</code> define the</p>

coordinates for U, V and must be monotonic and 2-D plaid (as if produced by meshgrid)

`interpstreamspeed(U, V, vertices)` assumes X and Y are determined by the expression:

`[X Y] = meshgrid(1:n, 1:m)`

where `[M N]=size(U)`.

`interpstreamspeed(X, Y, speed, vertices)` uses the 2-D array speed for the speed of the vector field.

`interpstreamspeed(speed, vertices)` assumes X and Y are determined by the expression:

`[X Y] = meshgrid(1:n, 1:m)`

where `[M, N]= size(speed)`

`interpstreamspeed(..., sf)` uses sf to scale the magnitude of the vector data and therefore controls the number of interpolated vertices. For example, if sf is 3, then `interpstreamspeed` creates only one third of the vertices.


`vertsout = interpstreamspeed(...)` returns a cell array of vertex arrays.

Examples

This example draws stream lines using the vertices returned by `interpstreamspeed`. Dot markers indicate the location of each vertex. This example enables you to visualize the relative speeds of the flow data. Stream lines having widely space vertices indicate faster flow; those with closely spaced vertices indicate slower flow.


```
load wind
[sx sy sz] = meshgrid(80, 20:1:55, 5);
verts = stream3(x, y, z, u, v, w, sx, sy, sz);
iverts = interpstreamspeed(x, y, z, u, v, w, verts, .2);
sl = streamline(iverts);
set(sl, 'Marker', '.')
axis tight; view(2); daspect([1 1 1])
```

interpstreamspeed



This example plots stream lines whose vertex spacing indicates the value of the gradient along the stream line.

```
z = membrane(6, 30);
[u v] = gradient(z);
[verts averts] = streamslice(u, v);
iverts = interpstreamspeed(u, v, verts, 15);
sl = streamline(iverts);
set(sl, 'Marker', '.')
hold on; pcolor(z); shading interp
axis tight; view(2); daspect([1 1 1])
```



See Also

[stream2](#), [stream3](#), [streamline](#), [streamslice](#), [streamparticles](#)

intersect

Purpose	Set intersection of two vectors
Syntax	<pre>c = intersect(A, B) c = intersect(A, B, 'rows') [c, ia, ib] = intersect(...)</pre>
Description	<p><code>c = intersect(A, B)</code> returns the values common to both A and B. The resulting vector is sorted in ascending order. In set theoretic terms, this is $A \cap B$. A and B can be cell arrays of strings.</p> <p><code>c = intersect(A, B, 'rows')</code> when A and B are matrices with the same number of columns returns the rows common to both A and B.</p> <p><code>[c, ia, ib] = intersect(a, b)</code> also returns column index vectors <code>ia</code> and <code>ib</code> such that <code>c = a(ia)</code> and <code>c = b(ib)</code> (or <code>c = a(ia, :)</code> and <code>c = b(ib, :)</code>).</p>
Examples	<pre>A = [1 2 3 6]; B = [1 2 3 4 6 10 20]; [c, ia, ib] = intersect(A, B); disp([c; ia; ib]) 1 2 3 6 1 2 3 4 1 2 3 5</pre>
See Also	<code>ismember</code> , <code>setdiff</code> , <code>setxor</code> , <code>union</code> , <code>unique</code>

Purpose	Matrix inverse
Syntax	$Y = \text{inv}(X)$
Description	$Y = \text{inv}(X)$ returns the inverse of the square matrix X . A warning message is printed if X is badly scaled or nearly singular. In practice, it is seldom necessary to form the explicit inverse of a matrix. A frequent misuse of inv arises when solving the system of linear equations $Ax = b$. One way to solve this is with $x = \text{inv}(A) * b$. A better way, from both an execution time and numerical accuracy standpoint, is to use the matrix division operator $x = A \backslash b$. This produces the solution using Gaussian elimination, without forming the inverse. See \backslash and $/$ for further information.
Examples	Here is an example demonstrating the difference between solving a linear system by inverting the matrix with $\text{inv}(A) * b$ and solving it directly with $A \backslash b$. A random matrix A of order 500 is constructed so that its condition number, $\text{cond}(A)$, is $1. \text{e}10$, and its norm, $\text{norm}(A)$, is 1. The exact solution x is a random vector of length 500 and the right-hand side is $b = A * x$. Thus the system of linear equations is badly conditioned, but consistent. On a 300 MHz, laptop computer the statements <pre>n = 500; Q = orth(randn(n, n)); d = logspace(0, -10, n); A = Q*diag(d)*Q'; x = randn(n, 1); b = A*x; tic, y = inv(A)*b; toc err = norm(y-x) res = norm(A*y-b)</pre> produce <pre>elapsed_time = 1.4320 err = 7.3260e-006 res = 4.7511e-007</pre>

while the statements

```
tic, z = A\b, toc  
err = norm(z-x)  
res = norm(A*z-b)
```

produce

```
elapsed_time =  
    0.6410  
err =  
    7.1209e-006  
res =  
    4.4509e-015
```

It takes almost two and one half times as long to compute the solution with $y = \text{inv}(A) * b$ as with $z = A \setminus b$. Both produce computed solutions with about the same error, $1. e- 6$, reflecting the condition number of the matrix. But the size of the residuals, obtained by plugging the computed solution back into the original equations, differs by several orders of magnitude. The direct solution produces residuals on the order of the machine accuracy, even though the system is badly conditioned.

The behavior of this example is typical. Using $A \setminus b$ instead of $\text{inv}(A) * b$ is two to three times as fast and produces residuals on the order of machine accuracy, relative to the magnitude of the data.

Algorithm

`inv` uses LAPACK routines to compute the matrix inverse:

Matrix	Routine
Real	DLANGE, DGETRF, DGECON, DGETRI
Complex	ZLANGE, ZGETRF, ZGECON, ZGETRI

See Also

`det`, `lu`, `rref`

The arithmetic operators `\`, `/`

References

[1] Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling, A. McKenney, and D. Sorensen,

LAPACK User's Guide (http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999.

invhilb

Purpose	Inverse of the Hilbert matrix
Syntax	$H = \text{invhilb}(n)$
Description	$H = \text{invhilb}(n)$ generates the exact inverse of the exact Hilbert matrix for n less than about 15. For larger n , $\text{invhilb}(n)$ generates an approximation to the inverse Hilbert matrix.
Limitations	The exact inverse of the exact Hilbert matrix is a matrix whose elements are large integers. These integers may be represented as floating-point numbers without roundoff error as long as the order of the matrix, n , is less than 15. Comparing $\text{invhilb}(n)$ with $\text{inv}(\text{hilb}(n))$ involves the effects of two or three sets of roundoff errors: <ul style="list-style-type: none">• The errors caused by representing $\text{hilb}(n)$• The errors in the matrix inversion process• The errors, if any, in representing $\text{invhilb}(n)$ It turns out that the first of these, which involves representing fractions like $1/3$ and $1/5$ in floating-point, is the most significant.
Examples	$\text{invhilb}(4)$ is
	$\begin{array}{cccc} 16 & -120 & 240 & -140 \\ -120 & 1200 & -2700 & 1680 \\ 240 & -2700 & 6480 & -4200 \\ -140 & 1680 & -4200 & 2800 \end{array}$
See Also	hilb
References	[1] Forsythe, G. E. and C. B. Moler, <i>Computer Solution of Linear Algebraic Systems</i> , Prentice-Hall, 1967, Chapter 19.

Purpose	Invoke a method on an object's interface and retrieve the return value of the method, if any, or display a list of methods.
Syntax	<pre>v = invoke (a [, 'methodname' [, arg1, arg2, ...]])</pre>
Arguments	<p>a An activex object previously returned from <code>actxcontrol</code>, <code>actxserver</code>, <code>get</code>, or <code>invoke</code>.</p> <p>methodname A string that is the name of the method to be invoked.</p> <p>arg1, ..., argn Arguments, if any, required by the method being invoked.</p>
Returns	The value returned by the method or a list of methods (if you use the form <code>invoke(a)</code> .) The data type of the value is dependent upon the specific method being invoked and is determined by the specific control or server. If the method returns an interface (described in ActiveX documentation as an <i>interface</i> , or an <i>Idispatch</i> *), this method will return a new MATLAB activex object that represents the interface returned. See “Converting Data” in <i>MATLAB External Interfaces</i> for a description of how MATLAB converts ActiveX data types.
Description	Invoke a method on an object's interface and retrieve the return value of the method, if any. (Some methods have no return value.)
Example	<p>Invoke a method:</p> <pre>f = figure ('pos', [100 200 200 200]); % create the control to fill the figure h = actxcontrol ('MMSAMP.MwsampCtrl.1', [0 0 200 200], f) set (h, 'Radius', 100); v = invoke (h, 'Redraw')</pre> <p>Display a list of methods:</p> <pre>invoke(h)</pre> <pre>AboutBox = Void AboutBox () ShowPropertyPage = Void ShowPropertyPage ()</pre>

ipermute

Purpose	Inverse permute the dimensions of a multidimensional array
Syntax	<code>A = ipermute(B, order)</code>
Description	<code>A = ipermute(B, order)</code> is the inverse of <code>permute</code> . <code>ipermute</code> rearranges the dimensions of <code>B</code> so that <code>permute(A, order)</code> will produce <code>B</code> . <code>B</code> has the same values as <code>A</code> but the order of the subscripts needed to access any particular element are rearranged as specified by <code>order</code> . All the elements of <code>order</code> must be unique.
Remarks	<code>permute</code> and <code>ipermute</code> are a generalization of transpose (<code>.</code>) for multidimensional arrays.
Examples	Consider the 2-by-2-by-3 array <code>a</code> : <code>a = cat(3, eye(2), 2*eye(2), 3*eye(2))</code> $a(:,:,1) = \begin{matrix} 1 & 0 \\ 0 & 1 \end{matrix} \quad a(:,:,2) = \begin{matrix} 2 & 0 \\ 0 & 2 \end{matrix}$ $a(:,:,3) = \begin{matrix} 3 & 0 \\ 0 & 3 \end{matrix}$ Permuting and inverse permuting <code>a</code> in the same fashion restores the array to its original form: <code>B = permute(a, [3 2 1]);</code> <code>C = ipermute(B, [3 2 1]);</code> <code>isequall(a, C)</code> <code>ans=</code> 1 See Also <code>permute</code>

Purpose	Detect state
Description	These functions detect the state of MATLAB entities:
<code>i sappdata</code>	Determine if object has specific application-defined data
<code>i scell</code>	Determine if item is a cell array
<code>i scellstr</code>	Determine if item is a cell array of strings
<code>i schar</code>	Determine if item is a character array
<code>i isempty</code>	Determine if item is an empty array
<code>i sequal</code>	Determine if arrays are numerically equal
<code>i sfiel d</code>	Determine if item is a MATLAB structure array field
<code>i sfinite</code>	Detect finite elements of an array
<code>i sglobal</code>	Determine if item is a global variable
<code>i shandle</code>	Detect valid graphics object handles
<code>i shold</code>	Determine if graphics hold state is on
<code>i sinf</code>	Detect infinite elements of an array.
<code>i sjava</code>	Determine if item is a Java object
<code>i skeyword</code>	Determine if item is a MATLAB keyword
<code>i sletter</code>	Detect array elements that are letters of the alphabet
<code>i slogical</code>	Determine if item is a logical array
<code>i smember</code>	Detect members of a specific set
<code>i snan</code>	Detect elements of an array that are not a number (NaN)
<code>i snumeric</code>	Determine if item is a numeric array
<code>i sobject</code>	Determine if item is a MATLAB OOPs object
<code>i spc</code>	Determine if PC (Windows) version of MATLAB

<code>isprime</code>	Detect prime elements of an array.
<code>isreal</code>	Determine if all array elements are real numbers
<code>isruntime</code>	Determine if MATLAB is or emulates the Runtime Server
<code>isspace</code>	Detect elements that are ASCII white spaces
<code>issparse</code>	Determine if item is a sparse array
<code>isstruct</code>	Determine if item is a MATLAB structure array
<code>isstudent</code>	Determine if student edition of MATLAB
<code>isunix</code>	Determine if UNIX version of MATLAB
<code>isvarname</code>	Determine if item is a valid variable name

See Also`isa`

Purpose	Detect an object of a given MATLAB class or Java class
Syntax	<code>K = isa(obj, 'class_name')</code>
Description	<code>K = isa(obj, 'class_name')</code> returns logical true (1) if <code>obj</code> is of class (or a subclass of) <code>class_name</code> , and logical false (0) otherwise.
	The argument <code>obj</code> is a MATLAB object or a Java object. The argument <code>class_name</code> is the name of a MATLAB (predefined or user-defined) or a Java class. Predefined MATLAB classes include:
cell	Cell array
char	Characters array
double	Double-precision floating-point array
function_handle	Function Handle
int8	8-bit signed integer array
int16	16-bit signed integer array
int32	32-bit signed integer array
numeric	Integer or floating-point array
single	Single-precision floating-point array
sparse	2-D real (or complex) sparse array
struct	Structure array
uint8	8-bit unsigned integer array
uint16	16-bit unsigned integer array
uint32	32-bit unsigned integer array

You cannot use `isa` to identify a logical value. Use `islogical` for this instead.

Examples	<pre>isa(rand(3, 4), 'double') ans = 1</pre>
-----------------	--

The following example creates an instance of the user-defined MATLAB class, named `polynom`. The `isa` function identifies the object as being of the `polynom` class.

```
polynom_obj = polynom([1 0 -2 -5]);
isa(polynom_obj, 'polynom')
ans =
1
```

See Also

`class`, `is*`

Purpose	True if application-defined data exists
Syntax	<code>isappdata(h, name)</code>
Description	<code>isappdata(h, name)</code> returns 1 if application-defined data with the specified name exists on the object specified by handle <code>h</code> , and returns 0 otherwise.
See Also	<code>getappdata</code> , <code>rmappdata</code> , <code>setappdata</code>

iscell

Purpose	Determine if item is a cell array
Syntax	<code>tf = iscell(A)</code>
Description	<code>tf = iscell(A)</code> returns logical true (1) if A is a cell array and logical false (0) otherwise.
Examples	<pre>A{1, 1} = [1 4 3; 0 5 8; 7 2 9]; A{1, 2} = 'Anne Smith'; A{2, 1} = 3+7i; A{2, 2} = -pi : pi /10: pi; iscell(A) ans = 1</pre>
See Also	<code>cell, iscellstr, isstruct, isnumeric, islogical, isobject, isa, is*</code>

Purpose	Determine if item is a cell array of strings
Syntax	<code>tf = iscellstr(A)</code>
Description	<code>tf = iscellstr(A)</code> returns logical true (1) if <code>A</code> is a cell array of strings and logical false (0) otherwise. A cell array of strings is a cell array where every element is a character array.
Examples	<pre>A{1, 1} = 'Thomas Lee'; A{1, 2} = 'Marketing'; A{2, 1} = 'Allison Jones'; A{2, 2} = 'Development'; iscellstr(A) ans = 1</pre>
See Also	<code>cell</code> , <code>char</code> , <code>iscell</code> , <code>isstruct</code> , <code>isa</code> , <code>is*</code>

ischar

Purpose	Determine if item is a character array
Syntax	<code>tf = ischar(A)</code>
Description	<code>tf = ischar(A)</code> returns logical true (1) if A is a character array and logical false (0) otherwise.
Examples	Given the following cell array, <code>C{1, 1} = magic(3); C{1, 2} = 'John Doe'; C{1, 3} = 2 + 4i</code> <code>C =</code> <code>[3x3 double] 'John Doe' [2.0000+ 4.0000i]</code> <code>ischar</code> shows that only <code>C{1, 2}</code> is a character array. <code>for k = 1:3 x(k) = ischar(C{1, k}); end</code> <code>x</code> <code>x =</code> <code>0 1 0</code>

See Also `char, isnumeric, islogical, isobject, isstruct, iscell, isa, is*`

Purpose	Test if array is empty
Syntax	<code>tf = isempty(A)</code>
Description	<code>tf = isempty(A)</code> returns logical true (1) if A is an empty array and logical false (0) otherwise. An empty array has at least one dimension of size zero, for example, 0-by-0 or 0-by-5.
Examples	<pre>B = rand(2, 2, 2); B(:,:, :) = []; isempty(B) ans = 1</pre>
See Also	<code>is*</code>

isequal

Purpose	Determine if arrays are numerically equal
Syntax	<code>tf = isequal(A, B, ...)</code>
Description	<code>tf = isequal(A, B, ...)</code> returns logical true (1) if the input arrays are the same type and size and hold the same contents, and logical false (0) otherwise.
Examples	Given, $A = \begin{matrix} 1 & 0 \\ 0 & 1 \end{matrix} \quad B = \begin{matrix} 1 & 0 \\ 0 & 1 \end{matrix} \quad C = \begin{matrix} 1 & 0 \\ 0 & 0 \end{matrix}$ <code>isequal(A, B, C)</code> returns 0, and <code>isequal(A, B)</code> returns 1.
See Also	relational operators , strcmp , isa , is*

Purpose Determine if item is a MATLAB structure array field

Syntax `tf = isfield(A, 'field')`

Description `tf = isfield(A, 'field')` returns logical true (1) if `field` is the name of a field in the structure array `A`, and logical false (0) otherwise.

Examples Given the following MATLAB structure,

```
patient.name = 'John Doe';
patient.billing = 127.00;
patient.test = [79 75 73; 180 178 177.5; 220 210 205];
```

`isfield` identifies `billing` as a field of that structure.

```
isfield(patient, 'billing')
```

```
ans =
```

```
1
```

See Also `struct`, `isstruct`, `iscell`, `isa`, `is*`

isfinite

Purpose	Detect finite elements of an array
Syntax	<code>TF = isfinite(A)</code>
Description	<code>TF = isfinite(A)</code> returns an array the same size as <code>A</code> containing logical true (1) where the elements of the array <code>A</code> are finite and logical false (0) where they are infinite or NaN.
	For any <code>A</code> , exactly one of the three quantities <code>isfinite(A)</code> , <code>isinf(A)</code> , and <code>isnan(A)</code> is equal to one.
Examples	<pre>a = [-2 -1 0 1 2]; isfinite(1./a) Warning: Divide by zero. ans = 1 1 0 1 1 isfinite(0./a) Warning: Divide by zero. ans = 1 1 0 1 1</pre>
See Also	<code>isinf</code> , <code>isnan</code> , <code>is*</code>

Purpose	Determine if item is a global variable
Syntax	<code>tf = isglobal(A)</code>
Description	<code>tf = isglobal(A)</code> returns logical true (1) if A has been declared to be a global variable, and logical false (0) otherwise.
See Also	<code>global</code> , <code>isvarname</code> , <code>isa</code> , <code>is*</code>

ishandle

Purpose	Determines if values are valid graphics object handles
Syntax	<code>array = ishandl e(h)</code>
Description	<code>array = ishandl e(h)</code> returns an array that contains 1's where the elements of <code>h</code> are valid graphics handles and 0's where they are not.
Examples	Determine whether the handles previously returned by <code>fill</code> remain handles of existing graphical objects: <code>X = rand(4); Y = rand(4); h = fill(X, Y, 'bl ue');</code> . . <code>del ete(h(3))</code> . . <code>is handl e(h)</code> <code>ans =</code> 1 1 0 1
See Also	<code>fi ndobj</code>

Purpose	Return hold state
Syntax	<code>k = ishold</code>
Description	<code>k = ishold</code> returns the hold state of the current axes. If <code>hold</code> is on <code>k = 1</code> , if <code>hold</code> is off, <code>k = 0</code> .
Examples	<code>ishold</code> is useful in graphics M-files where you want to perform a particular action only if <code>hold</code> is not on. For example, these statements set the view to 3-D only if <code>hold</code> is off:
	<pre>if ~ishold view(3); end</pre>
See Also	<code>axes</code> , <code>figure</code> , <code>hold</code> , <code>newplot</code>

isinf

Purpose	Detect infinite elements of an array
Syntax	<code>TF = isinf(A)</code>
Description	<code>TF = isinf(A)</code> returns an array the same size as <code>A</code> containing logical true (1) where the elements of <code>A</code> are +Inf or -Inf and logical false (0) where they are not. For any <code>A</code> , exactly one of the three quantities <code>isfinite(A)</code> , <code>isinf(A)</code> , and <code>isnan(A)</code> is equal to one.
Examples	<pre>a = [-2 -1 0 1 2] isinf(1./a) Warning: Divide by zero. ans = 0 0 1 0 0</pre> <pre>isinf(0./a) Warning: Divide by zero. ans = 0 0 0 0 0</pre>
See Also	<code>isfinite</code> , <code>isnan</code> , <code>is*</code>

Purpose	Determine if item is a Java object
Syntax	<code>tf = isjava(A)</code>
Description	<code>tf = isjava(A)</code> returns logical true (1) if A is a Java object, and logical false (0) otherwise.
Examples	<p>Create an instance of the Java Frame class and <code>isjava</code> indicates that it is a Java object.</p> <pre>frame = java.awt.Frame('Frame A'); isjava(frame) ans = 1</pre> <p>Note that, <code>isobject</code>, which tests for MATLAB objects, returns false (0).</p> <pre>isobject(frame) ans = 0</pre>
See Also	<code>isobject</code> , <code>javaArray</code> , <code>javaMethod</code> , <code>javaObject</code> , <code>isa</code> , <code>is*</code>

iskeyword

Purpose	Determine if item is a MATLAB keyword
Syntax	<pre>tf = iskeyword('str') iskeyword str iskeyword</pre>
Description	<p><code>tf = iskeyword('str')</code> returns logical true (1) if the string, <code>str</code>, is a keyword in the MATLAB language and logical false (0) otherwise.</p> <p><code>iskeyword str</code> uses the MATLAB command format.</p> <p><code>iskeyword</code> returns a list of all MATLAB keywords.</p>
Examples	<p>To test if the word <code>while</code> is a MATLAB keyword</p> <pre>iskeyword while ans = 1</pre> <p>To obtain a list of all MATLAB keywords</p> <pre>iskeyword 'break' 'case' 'catch' 'continue' 'else' 'elseif' 'end' 'for' 'function' 'global' 'if' 'otherwise' 'persistent' 'return' 'switch' 'try' 'while'</pre>

See Also

i svarname, i s*

isletter

Purpose	Detect array elements that are letters of the alphabet
Syntax	<code>TF = isletter('str')</code>
Description	<code>TF = isletter('str')</code> returns an array the same size as <code>str</code> containing logical true (1) where the elements of <code>str</code> are letters of the alphabet and logical false (0) where they are not.
Examples	<pre>s = 'A1, B2, C3'; isletter(s) ans = 1 0 0 1 0 0 1 0</pre>
See Also	<code>char</code> , <code>ischar</code> , <code>isspace</code> , <code>isa</code> , <code>is*</code>

Purpose	Determine if item is a logical array
Syntax	<code>tf = islogical(A)</code>
Description	<code>tf = islogical(A)</code> returns logical true (1) if A is a logical array and logical false (0) otherwise.
Examples	Given the following cell array,

```
C{1, 1} = pi;
C{1, 2} = 1;
C{1, 3} = ispc;
C{1, 4} = magic(3)
```

`C =`

```
[3. 1416] [1] [1] [3x3 double]
```

`islogical` shows that only `C{1, 3}` is a logical array.

```
for k = 1:4
x(k) = islogical(C{1, k});
end
```

`x`

`x =`

```
0 0 1 0
```

See Also	<code>logical</code> , <code>logical operators</code> , <code>isnumeric</code> , <code>ischar</code> , <code>isa</code> , <code>is*</code>
-----------------	--

ismember

Purpose	Detect members of a specific set
Syntax	<code>TF = ismember(A, S)</code> <code>TF = ismember(A, S, 'rows')</code>
Description	<code>TF = ismember(A, S)</code> returns a vector the same length as A containing logical true (1) where the elements of A are in the set S, and logical false (0) elsewhere. In set theoretic terms, k is 1 where $A \in S$. A and S can be cell arrays of strings. <code>TF = ismember(A, S, 'rows')</code> when A and S are matrices with the same number of columns returns a vector containing 1 where the rows of A are also rows of S and 0 otherwise.
Examples	<pre>set = [0 2 4 6 8 10 12 14 16 18 20]; a = reshape(1:5, [5 1]) a = 1 2 3 4 5 ismember(a, set) ans = 0 1 0 1 0</pre>
See Also	<code>intersect</code> , <code>setdiff</code> , <code>setxor</code> , <code>union</code> , <code>unique</code> , <code>is*</code>

Purpose	Detect NaN elements of an array										
Syntax	<code>TF = isnan(A)</code>										
Description	<code>TF = isnan(A)</code> returns an array the same size as <code>A</code> containing logical true (1) where the elements of <code>A</code> are NaNs and logical false (0) where they are not. For any <code>A</code> , exactly one of the three quantities <code>isfinite(A)</code> , <code>isinf(A)</code> , and <code>isnan(A)</code> is equal to one.										
Examples	<pre>a = [-2 -1 0 1 2]</pre> <code>isnan(1./a)</code> Warning: Divide by zero. <code>ans =</code> <table style="margin-left: 100px;"><tr><td>0</td><td>0</td><td>0</td><td>0</td><td>0</td></tr></table> <code>isnan(0./a)</code> Warning: Divide by zero. <code>ans =</code> <table style="margin-left: 100px;"><tr><td>0</td><td>0</td><td>1</td><td>0</td><td>0</td></tr></table>	0	0	0	0	0	0	0	1	0	0
0	0	0	0	0							
0	0	1	0	0							
See Also	<code>isfinite</code> , <code>isinf</code> , <code>is*</code>										

isnumeric

Purpose	Determine if item is a numeric array
Syntax	<code>tf = isnumeric(A)</code>
Description	<code>tf = isnumeric(A)</code> returns logical true (1) if A is a numeric array and logical false (0) otherwise. For example, sparse arrays, and double-precision arrays are numeric while strings, cell arrays, and structure arrays are not.
Examples	<p>Given the following cell array,</p> <pre>C{1, 1} = pi; C{1, 2} = 'John Doe'; C{1, 3} = 2 + 4i; C{1, 4} = ispc; C{1, 5} = magic(3)</pre> <p><code>C =</code></p> <pre>[3. 1416] 'John Doe' [2. 0000+ 4. 0000i] [1] [3x3 double]</pre> <p><code>isnumeric</code> shows that all but <code>C{1, 2}</code> are numeric arrays.</p> <pre>for k = 1:5 x(k) = isnumeric(C{1, k}); end</pre> <p><code>x</code></p> <pre>x =</pre> <pre>1 0 1 1 1</pre>

See Also `isnan`, `isreal`, `isprime`, `isfinite`, `isinf`, `isa`, `is*`


Purpose	Determine if item is a MATLAB OOPs object
Syntax	<code>tf = isobject(A)</code>
Description	<code>tf = isobject(A)</code> returns logical true (1) if A is a MATLAB object and logical false (0) otherwise.
Examples	Create an instance of the <code>polynom</code> class as defined in “Using MATLAB” in the section entitled, “Example - A Polynomial Class.” <code>p = polynom([1 0 -2 -5])</code> <code>p =</code> <code>x^3 - 2*x - 5</code> <code>isobject</code> indicates that p is a MATLAB object. <code>isobject(p)</code> <code>ans =</code> <code>1</code>
	Note that <code>isjava</code> , which tests for Java objects in MATLAB, returns false (0). <code>isjava(p)</code> <code>ans =</code> <code>0</code>
See Also	<code>isjava</code> , <code>isstruct</code> , <code>iscell</code> , <code>ischar</code> , <code>isnumeric</code> , <code>islogical</code> , <code>isa</code> , <code>is*</code>

isocaps

Purpose	Compute isosurface end-cap geometry
Syntax	<pre>fvc = isocaps(X, Y, Z, V, isoval ue) fvc = isocaps(V, isoval ue) fvc = isocaps(..., 'enclose') fvc = isocaps(..., 'whichplane') [f, v, c] = isocaps(...) isocaps(...)</pre>
Description	<p><code>fvc = isocaps(X, Y, Z, V, isoval ue)</code> computes isosurface end cap geometry for the volume data <code>V</code> at isosurface value <code>isoval ue</code>. The arrays <code>X</code>, <code>Y</code>, and <code>Z</code> define the coordinates for the volume <code>V</code>.</p> <p>The struct <code>fvc</code> contains the face, vertex, and color data for the end caps and can be passed directly to the <code>patch</code> command.</p> <p><code>fvc = isocaps(V, isoval ue)</code> assumes the arrays <code>X</code>, <code>Y</code>, and <code>Z</code> are defined as <code>[X, Y, Z] = meshgrid(1:n, 1:m, 1:p)</code> where <code>[m, n, p] = size(V)</code>.</p> <p><code>fvc = isocaps(..., 'enclose')</code> specifies whether the end caps enclose data values above or below the value specified in <code>isoval ue</code>. The string <code>enclose</code> can be either <code>above</code> (default) or <code>below</code>.</p> <p><code>fvc = isocaps(..., 'whichplane')</code> specifies on which planes to draw the end caps. Possible values for <code>whichplane</code> are: <code>all</code> (default), <code>xmin</code>, <code>xmax</code>, <code>ymin</code>, <code>ymax</code>, <code>zmin</code>, or <code>zmax</code>.</p> <p><code>[f, v, c] = isocaps(...)</code> returns the face, vertex, and color data for the end caps in three arrays instead of the struct <code>fvc</code>.</p> <p><code>isocaps(...)</code> without output arguments draws a patch with the computed faces, vertices, and colors.</p>
Examples	<p>This example uses a data set that is a collection of MRI slices of a human skull. It illustrates the use of <code>isocaps</code> to draw the end caps on this cut-away volume. The red isosurface shows the outline of the volume (skull) and the end caps show what is inside of the volume.</p> <p>The patch created from the end cap data (<code>p2</code>) uses interpolated face coloring, which means the gray colormap and the light sources determine how it is</p>

colored. The isosurface patch (p1) used a flat red face color, which is affected by the lights, but does not use the colormap.

```
load mri
D = squeeze(D);
D(:, 1:60, :) = [];
p1 = patch(isosurface(D, 5), 'FaceColor', 'red', ...
    'EdgeColor', 'none');
p2 = patch(isocaps(D, 5), 'FaceColor', 'interp', ...
    'EdgeColor', 'none');
view(3); axis tight; daspect([1, 1, .4])
colormap(gray(100))
camlight left; camlight; lighting gouraud
isnormal(D, p1)
```




See Also

[isosurface](#), [isnormal](#), [smooth3](#), [subvolume](#), [reducevolume](#), [reducepatch](#)

isocolors

Purpose	Calculates isosurface and patch colors
Syntax	<pre>nc = isocolors(X, Y, Z, C, vertices) nc = isocolors(X, Y, Z, R, G, B, vertices) nc = isocolors(C, vertices) nc = isocolors(R, G, B, vertices) nc = isocolors(..., PatchHandle) isocolors(..., PatchHandle)</pre>
Description	<p><code>nc = isocolors(X, Y, Z, C, vertices)</code> computes the colors of isosurface (patch object) vertices (<code>vertices</code>) using color values <code>C</code>. Arrays <code>X</code>, <code>Y</code>, <code>Z</code> define the coordinates for the color data in <code>C</code> and must be monotonic vectors or 3-D plaid arrays (as if produced by <code>meshgrid</code>). The colors are returned in <code>nc</code>. <code>C</code> must be 3-D (index colors).</p> <p><code>nc = isocolors(X, Y, Z, R, G, B, vertices)</code> uses <code>R</code>, <code>G</code>, <code>B</code> as the red, green, and blue color arrays (truecolor).</p> <p><code>nc = isocolors(C, vertices)</code>, <code>nc = isocolors(R, G, B, vertices)</code> assumes <code>X</code>, <code>Y</code>, and <code>Z</code> are determined by the expression:</p> $[X \ Y \ Z] = meshgrid(1:n, 1:m, 1:p)$ <p>where <code>[m n p] = size(C)</code>.</p> <p><code>nc = isocolors(..., PatchHandle)</code> uses the vertices from the patch identified by <code>PatchHandle</code>.</p> <p><code>isocolors(..., PatchHandle)</code> sets the <code>FaceVertexCData</code> property of the patch specified by <code>PatchHandle</code> to the computed colors.</p>
Examples	<h3>Indexed Color Data</h3> <p>This example displays an isosurface and colors it with random data using indexed color. (See "Interpolating in Indexed Color vs. Truecolor" for information on how patch objects interpret color data.)</p> <pre>[x y z] = meshgrid(1:20, 1:20, 1:20); data = sqrt(x.^2 + y.^2 + z.^2); cdata = smooth3(rand(size(data)), 'box', 7); p = patch(isosurface(x, y, z, data, 10));</pre>


```
isonormal s(x, y, z, data, p);
isocolors(x, y, z, cdata, p);
set(p, 'FaceColor', 'interp', 'EdgeColor', 'none');
view(150, 30); daspect([1 1 1]); axis tight
camlight; lighting phong;
```



Truecolor Data

This example displays an isosurface and colors it with truecolor (RGB) data.


```
[x y z] = meshgrid(1:20, 1:20, 1:20);
data = sqrt(x.^2 + y.^2 + z.^2);
p = patch(isosurface(x, y, z, data, 20));
isonormal s(x, y, z, data, p);
[r g b] = meshgrid(-1:1, 1:20, 1:20);
isocolors(x, y, z, r/20, g/20, b/20, p);
set(p, 'FaceColor', 'interp', 'EdgeColor', 'none');
view(150, 30); daspect([1 1 1]);
camlight; lighting phong;
```



Modified Truecolor Data

This example uses `isocolors` to calculate the truecolor data using the isosurface's (patch object's) vertices, but then returns the color data in a variable (`c`) in order to modify the values. It then explicitly sets the isosurface's `FaceVertexCData` to the new data (`1 - c`).

```
[x y z] = meshgrid(1:20, 1:20, 1:20);
data = sqrt(x.^2 + y.^2 + z.^2);
p = patch(isosurface(data, 20));
isonormals(data, p);
[r g b] = meshgrid(20:-1:1, 1:20, 1:20);
c = isocolors(r/20, g/20, b/20, p);
set(p, 'FaceVertexCData', 1-c)
set(p, 'FaceColor', 'interp', 'EdgeColor', 'none')
view(150, 30); daspect([1 1 1]);
camlight; lighting phong;
```

**See Also**

`isosurface`, `isocaps`, `smooth3`, `subvolume`, `reducevolume`, `reducepatch`, `isonormals`.

isonormals

Purpose	Compute normals of isosurface vertices
Syntax	<pre>n = isonormals(X, Y, Z, V, vertices) n = isonormals(V, vertices) n = isonormals(V, p), n = isonormals(X, Y, Z, V, p) n = isonormals(..., 'negate') isnormals(V, p), isnormals(X, Y, Z, V, p)</pre>
Description	<p><code>n = isonormals(X, Y, Z, V, vertices)</code> computes the normals of the isosurface vertices from the vertex list, <code>vertices</code>, using the gradient of the data <code>V</code>. The arrays <code>X</code>, <code>Y</code>, and <code>Z</code> define the coordinates for the volume <code>V</code>. The computed normals are returned in <code>n</code>.</p> <p><code>n = isonormals(V, vertices)</code> assumes the arrays <code>X</code>, <code>Y</code>, and <code>Z</code> are defined as <code>[X, Y, Z] = meshgrid(1:n, 1:m, 1:p)</code> where <code>[m, n, p] = size(V)</code>.</p> <p><code>n = isonormals(V, p)</code> and <code>n = isonormal s(X, Y, Z, V, p)</code> compute normals from the vertices of the patch identified by the handle <code>p</code>.</p> <p><code>n = isonormals(..., 'negate')</code> negates (reverses the direction of) the normals.</p> <p><code>isnormal s(V, p)</code> and <code>isnormal s(X, Y, Z, V, p)</code> set the <code>VertexNormals</code> property of the patch identified by the handle <code>p</code> to the computed normals rather than returning the values.</p>
Examples	<p>This example compares the effect of different surface normals on the visual appearance of lit isosurfaces. In one case, the triangles used to draw the isosurface define the normals. In the other, the <code>isonormals</code> function uses the volume data to calculate the vertex normals based on the gradient of the data points. The latter approach generally produces a smoother-appearing isosurface.</p> <p>Define a 3-D array of volume data (<code>cat</code>, <code>interp3</code>):</p> <pre>data = cat(3, [0 .2 0; 0 .3 0; 0 0 0], ... [.1 .2 0; 0 1 0; .2 .7 0], ... [0 .4 .2; .2 .4 0;.1 .1 0]); data = interp3(data, 3, 'cubic');</pre>


Draw an isosurface from the volume data and add lights. This isosurface uses triangle normals (`patch`, `isosurface`, `view`, `daspect`, `axis`, `camlight`, `lighting`, `title`):

```
subplot(1, 2, 1)
p1 = patch(isosurface(data, .5), ...
    'FaceColor', 'red', 'EdgeColor', 'none');
view(3); daspect([1, 1, 1]); axis tight
camlight; camlight(-80, -10); lighting phong;
title('Triangle Normals')
```

Draw the same lit isosurface using normals calculated from the volume data:

```
subplot(1, 2, 2)
p2 = patch(isosurface(data, .5), ...
    'FaceColor', 'red', 'EdgeColor', 'none');
isonormals(data, p2)
view(3); daspect([1 1 1]); axis tight
camlight; camlight(-80, -10); lighting phong;
title('Data Normals')
```

These isosurfaces illustrate the difference between triangle and data normals:



See Also

`interp3`, `isosurface`, `isocaps`, `smooth3`, `subvolume`, `reducevolume`, `reducepatch`

isosurface

Purpose	Extract isosurface data from volume data
Syntax	<pre>fv = isosurface(X, Y, Z, V, isoval ue) fv = isosurface(V, isoval ue) fv = isosurface(X, Y, Z, V), fv = isosurface(X, Y, Z, V) fvc = isosurface(..., col ors) fv = isosurface(..., 'noshare') fv = isosurface(..., 'verbose') [f, v] = isosurface... isosurface...</pre>
Description	<p><code>fv = isosurface(X, Y, Z, V, isoval ue)</code> computes isosurface data from the volume data <code>V</code> at the isosurface value specified in <code>isoval ue</code>. The arrays <code>X</code>, <code>Y</code>, and <code>Z</code> define the coordinates for the volume <code>V</code>. The structure <code>fv</code> contains the faces and vertices of the isosurface, which you can pass directly to the <code>patch</code> command.</p> <p><code>fv = isosurface(V, isoval ue)</code> assumes the arrays <code>X</code>, <code>Y</code>, and <code>Z</code> are defined as <code>[X, Y, Z] = meshgrid(1:n, 1:m, 1:p)</code> where <code>[m, n, p] = size(V)</code>.</p> <p><code>fvc = isosurface(..., col ors)</code> interpolates the array <code>col ors</code> onto the scalar field and returns the interpolated values in the <code>facevertexdata</code> field of the <code>fvc</code> structure. The size of the <code>col ors</code> array must be the same as <code>V</code>. The <code>colors</code> argument enables you to control the color mapping of the isosurface with data different from that used to calculate the isosurface (e.g., temperature data superimposed on a wind current isosurface).</p> <p><code>fv = isosurface(..., 'noshare')</code> does not create shared vertices. This is faster, but produces a larger set of vertices.</p> <p><code>fv = isosurface(..., 'verbose')</code> prints progress messages to the command window as the computation progresses.</p> <p><code>[f, v] = isosurface(...)</code> returns the faces and vertices in two arrays instead of a struct.</p> <p><code>isosurface(...)</code> with no output arguments creates a patch using the computed faces and vertices.</p>

Remarks

You can pass the fv structure created by `isosurface` directly to the `patch` command, but you cannot pass the individual faces and vertices arrays (`f`, `v`) to `patch` without specifying property names. For example,

```
patch(isosurface(X, Y, Z, V, isovalue))
```

or

```
[f, v] = isosurface(X, Y, Z, V, isovalue);  
patch('Faces', f, 'Vertices', v)
```


Examples

This example uses the flow data set, which represents the speed profile of a submerged jet within an infinite tank (type `help flow` for more information). The `isosurface` is drawn at the data value of -3. The statements that follow the `patch` command prepare the `isosurface` for lighting by:

- Recalculating the `isosurface` normals based on the volume data (`isonormals`)
- Setting the face and edge color (`set`, `FaceColor` or, `EdgeColor` or)
- Specifying the view (`daspect`, `view`)
- Adding lights (`camlight`, `lighting`)

```
[x, y, z, v] = flow;  
p = patch(isosurface(x, y, z, v, -3));  
isonormals(x, y, z, v, p)  
set(p, 'FaceColor', 'red', 'EdgeColor', 'none');  
daspect([1 1 1])  
view(3); axis tight  
camlight  
lighting gouraud
```

isosurface



See Also

[isnormal](#) [socaps](#), [reducepatch](#), [reducevolume](#), [shrinkfaces](#), [smooth3](#), [subvolume](#)

Purpose	Determine if PC (Windows) version of MATLAB
Syntax	<code>tf = ispc</code>
Description	<code>tf = ispc</code> returns logical true (1) for the PC version of MATLAB and logical false (0) otherwise.
See Also	<code>isunix</code> , <code>isstudent</code> , <code>is*</code>

isprime

Purpose	Detect prime elements of an array
Syntax	<code>TF = isprime(A)</code>
Description	<code>TF = isprime(A)</code> returns an array the same size as <code>A</code> containing logical true (1) for the elements of <code>A</code> which are prime, and logical false (0) otherwise. <code>A</code> must contain only positive integers.
Examples	<pre>c = [2 3 0 6 10] c = 2 3 0 6 10 isprime(c) ans = 1 1 0 0 0</pre>
See Also	<code>is*</code>

Purpose	Determine if all array elements are real numbers
Syntax	<code>tf = isreal(A)</code>
Description	<p><code>tf = isreal(A)</code> returns logical false (0) if any element of array A has an imaginary component, even if the value of that component is 0. It returns logical true (1) otherwise.</p> <p><code>~isreal(x)</code> returns logical true for arrays that have at least one element with an imaginary component. The value of that component may be 0.</p>

Note If a is real, `complex(a)` returns a complex number whose imaginary component is 0, and `isreal(complex(a))` returns false. In contrast, the addition `a + 0i` returns the real value a, and `isreal(a + 0i)` returns true.

Because MATLAB supports complex arithmetic, certain of its functions can introduce significant imaginary components during the course of calculations that appear to be limited to real numbers. Thus, you should use `isreal` with discretion.

Examples	Example 1. These examples use <code>isreal</code> to detect presence or absence of imaginary numbers in an array. Let
	<pre>x = magic(3); y = complex(x);</pre>

`isreal(x)` returns true because no element of x has an imaginary component.

`isreal(x)`

```
ans =
1
```

`isreal(y)` returns false, because every element of x has an imaginary component, even though the value of the imaginary components is 0.

`isreal(y)`

isreal

```
ans =  
0
```

This expression detects strictly real arrays, i.e., elements with 0-valued imaginary components are treated as real.

```
~any(imag(y(:)))
```

```
ans =  
1
```

Example 2. Given the following cell array,

```
C{1, 1} = pi;  
C{1, 2} = 'John Doe';  
C{1, 3} = 2 + 4i;  
C{1, 4} = ispc;  
C{1, 5} = magic(3);  
C{1, 6} = complex(5, 0)
```

```
C =  
[3.1416] 'John Doe' [2.0000+4.0000i] [1] [3x3 double] [5]
```

isreal shows that all but C{1, 3} and C{1, 6} are real arrays.

```
for k = 1:6  
x(k) = isreal(C{1, k});  
end
```

```
x
```

```
x =  
1 1 0 1 1 0
```

See Also

complex, isnumeric, isnan, isprime, isfinite, isnf, isa, is*

Purpose Determine if MATLAB is or emulates the Runtime Server

Syntax `tf = isruntime`

Description `tf = isruntime` returns logical true (1) if MATLAB is either the Runtime Server variant, or commercial MATLAB currently emulating the Runtime Server. `isruntime` returns logical false (0) otherwise.

Examples

```
runtime on  
isruntime
```

```
ans =
```

```
1
```

```
runtime off  
isruntime
```

```
ans =
```

```
0
```

See Also `runtime`, `is*`

isspace

Purpose	Detect elements that are ASCII white spaces
Syntax	<code>TF = isspace('str')</code>
Description	<code>TF = isspace('str')</code> returns an array the same size as 'str' containing logical true (1) where the elements of str are ASCII white spaces and logical false (0) where they are not. White spaces in ASCII are space, newline, carriage return, tab, vertical tab, or formfeed characters.
Examples	<pre>isspace('Find spaces') ans = Columns 1 through 13 1 1 0 0 0 0 1 0 0 0 1 0 0 Columns 14 through 15 0 1</pre>
See Also	<code>isletter</code> , <code>ischar</code> , <code>char</code> , <code>isa</code> , <code>is*</code>

Purpose Test if matrix is sparse

Syntax `tf = issparse(S)`

Description `tf = issparse(S)` returns logical true (1) if the storage class of `S` is sparse and logical false (0) otherwise.

See Also `is*`

isstr

Purpose Determine if item is a character array

Description This MATLAB 4 function has been renamed `ischar` in MATLAB 5.

See Also `ischar`, `isa`, `is*`

Purpose	Determine if item is a MATLAB structure array
Syntax	<code>tf = isstruct(A)</code>
Description	<code>tf = isstruct(A)</code> returns logical true (1) if A is a MATLAB structure and logical false (0) otherwise.
Examples	<pre>patient.name = 'John Doe'; patient.billing = 127.00; patient.test = [79 75 73; 180 178 177.5; 220 210 205]; isstruct(patient) ans = 1</pre>
See Also	<code>struct</code> , <code>isfield</code> , <code>iscell</code> , <code>ischar</code> , <code>isobject</code> , <code>isnumeric</code> , <code>islogical</code> , <code>isa</code> , <code>is*</code>

isstudent

Purpose	Determine if student edition of MATLAB
Syntax	<code>tf = isstudent</code>
Description	<code>tf = isstudent</code> returns logical true (1) for the student edition of MATLAB and logical false (0) for commercial editions.
See Also	<code>ispcl</code> , <code>isunix</code> , <code>is*</code>

Purpose	Determine if UNIX version of MATLAB
Syntax	<code>tf = isunix</code>
Description	<code>tf = isunix</code> returns logical true (1) for the UNIX version of MATLAB and logical false (0) otherwise.
See Also	<code>ispcl, issstudent, is*</code>

isValid

Purpose	Determine if serial port objects are valid				
Syntax	<code>out = isValid(obj)</code>				
Arguments	<table><tr><td><code>obj</code></td><td>A serial port object or array of serial port objects.</td></tr><tr><td><code>out</code></td><td>A logical array.</td></tr></table>	<code>obj</code>	A serial port object or array of serial port objects.	<code>out</code>	A logical array.
<code>obj</code>	A serial port object or array of serial port objects.				
<code>out</code>	A logical array.				
Description	<code>out = isValid(obj)</code> returns the logical array <code>out</code> , which contains a 0 where the elements of <code>obj</code> are invalid serial port objects and a 1 where the elements of <code>obj</code> are valid serial port objects.				
Remarks	<code>obj</code> becomes invalid after it is removed from memory with the <code>delete</code> function. Since you cannot connect an invalid serial port object to the device, you should remove it from the workspace with the <code>clear</code> command.				
Example	<p>Suppose you create the following two serial port objects.</p> <pre>s1 = serial('COM1'); s2 = serial('COM1');</pre> <p><code>s2</code> becomes invalid after it is deleted.</p> <pre>delete(s2)</pre> <p><code>isValid</code> verifies that <code>s1</code> is valid and <code>s2</code> is invalid.</p> <pre>sarray = [s1 s2]; isValid(sarray) ans = 1 0</pre>				
See Also	Functions <code>clear</code> , <code>delete</code>				

Purpose Determine if item is a valid variable name

Syntax
`tf = isvarname('str')`
`isvarname str`

Description `tf = isvarname 'str'` returns logical true (1) if the string, `str`, is a valid MATLAB variable name and logical false (0) otherwise. A valid variable name is a character string of letters, digits, and underscores, totaling not more than 31 characters and beginning with a letter.

`isvarname str` uses the MATLAB command format.

Examples `isvarname foo`

```
ans =
```

```
1
```

```
isvarname name_with_more_than_31_characters
```

```
ans =
```

```
0
```

If you are building strings from various pieces, place the construction in parentheses.

```
d = date;  
isvarname(['Monday_', d(1:2)])
```

```
ans =
```

```
1
```

See Also `isglobal`, `iskeyword`, `is*`

j

Purpose	Imaginary unit
Syntax	j x+yj x+j *y
Description	Use the character j in place of the character i , if desired, as the imaginary unit. As the basic imaginary unit sqrt (- 1) , j is used to enter complex numbers. Since j is a function, it can be overridden and used as a variable. This permits you to use j as an index in for loops, etc. It is possible to use the character j without a multiplication sign as a suffix in forming a numerical constant.
Examples	Z = 2+3j Z = x+j *y Z = r*exp(j *theta)
See Also	conj , i , i mag, real

Purpose	Constructs a Java array
Syntax	<code>j avaArray(' package_name. class_name' , x1, . . . , xn)</code>
Description	<code>j avaArray(' package_name. class_name' , x1, . . . , xn)</code> constructs an empty Java array capable of storing objects of Java class, ' <i>class_name</i> '. The dimensions of the array are x1 by . . . by xn. You must include the package name when specifying the class.
	The array that you create with <code>j avaArray</code> is equivalent to the array that you would create with the Java code
	<pre>A = new class_name[x1] . . . [xn];</pre>
Examples	The following example constructs and populates a 4-by-5 array of <code>j ava. lang. Double</code> objects.
	<pre>dblArray = j avaArray ('j ava. lang. Double' , 4, 5); for m = 1:4 for n = 1:5 dblArray(m, n) = j ava. lang. Double((m*10) + n); end end dblArray dblArray = j ava. lang. Double[][]: [11] [12] [13] [14] [15] [21] [22] [23] [24] [25] [31] [32] [33] [34] [35] [41] [42] [43] [44] [45]</pre>
See Also	<code>j avaObj ect</code> , <code>j avaMethod</code> , <code>cl ass</code> , <code>meth odsvi ew</code> , <code>i sj ava</code>

javachk

Purpose	Generate an error message based on Java feature support
Syntax	<code>javachk(feature)</code> <code>javachk(feature, component)</code>
Description	<code>javachk(feature)</code> returns a generic error message if the specified Java feature is not available in the current MATLAB session. If it is available, <code>javachk</code> returns an empty matrix. Possible feature arguments are shown in the following table.

Feature	Description
'awt'	Abstract Window Toolkit components ¹ are available.
'desktop'	The MATLAB interactive desktop is running.
'jvm'	The Java Virtual Machine is running.
'swing'	Swing components ² are available.

1. Java's GUI components in the Abstract Window Toolkit
2. Java's lightweight GUI components in the Java Foundation Classes

`javachk(feature, component)` works the same as the above syntax, except that the specified component is also named in the error message. (See the example below.)

Examples	The following M-file displays an error with the message "CreateFrame is not supported on this platform." when run in a MATLAB session in which the AWT's GUI components are not available. The second argument to <code>javachk</code> specifies the name of the M-file, which is then included in the error message generated by MATLAB.
-----------------	---

```
j avamsg = j avachk('awt', mfilename);
if isempty(j avamsg)
    myFrame = java.awt.Frame;
    myFrame.setVisible(1);
else
    error(j avamsg);
end
```

See Also

usejava

javaMethod

Purpose	Invokes a Java method
Syntax	<pre>X = javaMethod('method_name', 'class_name', x1, ..., xn)</pre> <pre>X = javaMethod('method_name', J, x1, ..., xn)</pre>
Description	<p><code>javaMethod('method_name', 'class_name', x1, ..., xn)</code> invokes the static method <code>method_name</code> in the class <code>class_name</code>, with the argument list that matches <code>x1, ..., xn</code>.</p> <p><code>javaMethod('method_name', J, x1, ..., xn)</code> invokes the nonstatic method <code>method_name</code> on the object <code>J</code>, with the argument list that matches <code>x1, ..., xn</code>.</p>
Remarks	<p>Using the <code>javaMethod</code> function enables you to</p> <ul style="list-style-type: none">• Use methods having names longer than 31 characters• Specify the method you want to invoke at run-time, for example, as input from an application user <p>The <code>javaMethod</code> function enables you to use methods having names longer than 31 characters. This is the only way you can invoke such a method in MATLAB. For example:</p> <pre>javaMethod('DataDefinitionAndDataManipulationTransactions', T);</pre> <p>With <code>javaMethod</code>, you can also specify the method to be invoked at run-time. In this situation, your code calls <code>javaMethod</code> with a string variable in place of the <code>method_name</code> argument. When you use <code>javaMethod</code> to invoke a static method, you can also use a string variable in place of the <code>class_name</code> argument.</p>
Note	Typically, you do not need to use <code>javaMethod</code> . The default MATLAB syntax for invoking a Java method is somewhat simpler and is preferable for most applications. Use <code>javaMethod</code> primarily for the two cases described above.
Examples	To invoke the static Java method <code>isNaN</code> on class, <code>java.lang.Double</code> , use <pre>javaMethod('isNaN', 'java.lang.Double', 2, 2)</pre>

The following example invokes the nonstatic method `setTitle`, where `frameObj` is a `java.awt.Frame` object.

```
frameObj = java.awt.Frame;
javaMethod('setTitle', frameObj, 'New Title');
```

See Also

`javaArray`, `javaObject`, `import`, `methods`, `isJava`

javaObject

Purpose	Constructs a Java object
Syntax	<code>J = javaObject('class_name', x1, ..., xn)</code>
Description	<code>javaObject('class_name', x1, ..., xn)</code> invokes the Java constructor for class ' <code>class_name</code> ' with the argument list that matches <code>x1, ..., xn</code> , to return a new object.
	If there is no constructor that matches the class name and argument list passed to <code>javaObject</code> , an error occurs.
Remarks	<p>Using the <code>javaObject</code> function enables you to</p> <ul style="list-style-type: none">• Use classes having names with more than 31 consecutive characters• Specify the class for an object at run-time, for example, as input from an application user <p>The default MATLAB constructor syntax requires that no segment of the input class name be longer than 31 characters. (A <i>name segment</i>, is any portion of the class name before, between, or after a period. For example, there are three segments in <code>class.javax.lang.String</code>.) Any class name segment that exceeds 31 characters is truncated by MATLAB. In the rare case where you need to use a class name of this length, you must use <code>javaObject</code> to instantiate the class.</p> <p>The <code>javaObject</code> function also allows you to specify the Java class for the object being constructed at run-time. In this situation, you call <code>javaObject</code> with a string variable in place of the class name argument.</p> <pre>class = 'java.lang.String'; text = 'hello'; strObj = javaObject(class, text);</pre> <p>In the usual case, when the class to instantiate is known at development time, it is more convenient to use the MATLAB constructor syntax. For example, to create a <code>java.lang.String</code> object, you would use</p> <pre>strObj = java.lang.String('hello');</pre>

Note Typically, you will not need to use `javaObject`. The default MATLAB syntax for instantiating a Java class is somewhat simpler and is preferable for

most applications. Use `javaObject` primarily for the two cases described above.

Examples

The following example constructs and returns a Java object of class `java.lang.String`:

```
strObj = javaObject('java.lang.String', 'hello')
```

See Also

`javaArray`, `javaMethod`, `import`, `methods`, `filenames`, `isJava`

keyboard

Purpose	Invoke the keyboard in an M-file
Syntax	keyboard
Description	keyboard , when placed in an M-file, stops execution of the file and gives control to the keyboard. The special status is indicated by a K appearing before the prompt. You can examine or change variables; all MATLAB commands are valid. This keyboard mode is useful for debugging your M-files.
	To terminate the keyboard mode, type the command: return then press the Return key.

See Also dbstop, input, quit, return

Purpose Kronecker tensor product

Syntax $K = \text{kron}(X, Y)$

Description $K = \text{kron}(X, Y)$ returns the Kronecker tensor product of X and Y. The result is a large array formed by taking all possible products between the elements of X and those of Y. If X is m-by-n and Y is p-by-q, then $\text{kron}(X, Y)$ is m*p-by-n*q.

Examples If X is 2-by-3, then $\text{kron}(X, Y)$ is


$$\begin{bmatrix} X(1, 1) * Y & X(1, 2) * Y & X(1, 3) * Y \\ X(2, 1) * Y & X(2, 2) * Y & X(2, 3) * Y \end{bmatrix}$$

The matrix representation of the discrete Laplacian operator on a two-dimensional, n-by-n grid is a n^2 -by- n^2 sparse matrix. There are at most five nonzero elements in each row or column. The matrix can be generated as the Kronecker product of one-dimensional difference operators with these statements:

```
I = speye(n, n);
E = sparse(2:n, 1:n-1, 1, n, n);
D = E+E' - 2*I;
A = kron(D, I) + kron(I, D);
```

Plotting this with the spy function for $n = 5$ yields:

kron



Purpose	Last error message
Syntax	<code>str = lasterr</code> <code>lasterr('')</code>
Description	<code>str = lasterr</code> returns the last error message generated by MATLAB. <code>lasterr('')</code> resets <code>lasterr</code> so it returns an empty matrix until the next error occurs.
Examples	Here is a function that examines the <code>lasterr</code> string and displays its own message based on the error that last occurred. This example deals with two cases, each of which is an error that can result from a matrix multiply.

```
function catchfcn
l = lasterr;
f1 = findstr(l, 'Inner matrix dimensions');
if ~isempty(f1)
    disp('Wrong dimensions for matrix multiply')
else
    f2 = findstr(l, 'Undefined function or variable');
    if ~isempty(f2)
        disp('At least one operand does not exist')
    end
end
```

The `lasterr` function is useful in conjunction with the two-argument form of the `eval` function:

```
eval ('string', 'catchstr')
```

or the `try ... catch... end` statements. The `catch` action examines the `lasterr` string to determine the cause of the error and takes appropriate action.

The `eval` function evaluates `string` and returns if no error occurs. If an error occurs, `eval` executes `catchstr`. Using `eval` with the `catchfcn` function above:

```
clear
A = [1 2 3; 6 7 2; 0 -1 5];
B = [9 5 6; 0 4 9];
```

```
eval ('A*B', 'catchfcn')
```

MATLAB responds with Wrong dimensions for matrix multiply.

See Also

[error](#), [eval](#)

Purpose	Last warning message
Syntax	<code>lastwarn</code> <code>lastwarn('')</code> <code>lastwarn('string')</code>
Description	<code>lastwarn</code> returns a string containing the last warning message issued by MATLAB. <code>lastwarn('')</code> resets the <code>lastwarn</code> function so that it will return an empty string matrix until the next warning is encountered. <code>lastwarn('string')</code> sets the last warning message to 'string'. The last warning message is updated regardless of whether warning is on or off.
See Also	<code>lasterr</code> , <code>warning</code>

Icm

Purpose	Least common multiple
Syntax	<code>L = lcm(A, B)</code>
Description	<code>L = lcm(A, B)</code> returns the least common multiple of corresponding elements of arrays A and B. Inputs A and B must contain positive integer elements and must be the same size (or either can be scalar).
Examples	<pre>lcm(8, 40) ans = 40 lcm(pascal(3), magic(3)) ans = 8 1 6 3 10 21 4 9 6</pre>
See Also	<code>gcd</code>

Purpose	Display a legend on graphs
Syntax	<pre>legend('string1', 'string2', ...) legend(h, 'string1', 'string2', ...) legend(string_matrix) legend(h, string_matrix) legend(axes_handle, ...) legend('off') legend('hide') legend('show') legend('boxoff') legend('boxon') legend(h, ...) legend(..., pos) h = legend(...) [legend_h, object_h, plot_h, text_strings] = legend(...)</pre>
Description	<p><code>legend</code> places a legend on various types of graphs (line plots, bar graphs, pie charts, etc.). For each line plotted, the legend shows a sample of the line type, marker symbol, and color beside the text label you specify. When plotting filled areas (patch or surface objects), the legend contains a sample of the face color next to the text label.</p> <p><code>legend('string1', 'string2', ...)</code> displays a legend in the current axes using the specified strings to label each set of data.</p> <p><code>legend(h, 'string1', 'string2', ...)</code> displays a legend on the plot containing the handles in the vector <code>h</code>, using the specified strings to label the corresponding graphics object (line, bar, etc.).</p> <p><code>legend(string_matrix)</code> adds a legend containing the rows of the matrix <code>string_matrix</code> as labels. This is the same as <code>legend(string_matrix(1, :), string_matrix(2, :), ...).</code></p> <p><code>legend(h, string_matrix)</code> associates each row of the matrix <code>string_matrix</code> with the corresponding graphics object in the vector <code>h</code>.</p>

legend

`legend(axes_handle, ...)` displays the legend for the axes specified by `axes_handle`.

`legend('off')`, `legend(axes_handle, 'off')` removes the legend in the current axes or the axes specified by `axes_handle`.

`legend('hide')`, `legend(axes_handle, 'hide')` makes the legend in the current axes or the axes specified by `axes_handle` invisible.

`legend('show')`, `legend(axes_handle, 'show')` makes the legend in the current axes or the axes specified by `axes_handle` visible.

`legend('boxoff')`, `legend(axes_handle, 'boxoff')` removes the box from the legend in the current axes or the axes specified by `axes_handle`.

`legend('boxon')`, `legend(axes_handle, 'boxon')` adds a box to the legend in the current axes or the axes specified by `axes_handle`.

`legend_handle = legend` returns the handle to the legend on the current axes or an empty vector if no legend exists.

`legend` with no arguments refreshes all the legends in the current figure.

`legend(legend_handle)` refreshes the specified legend.

`legend(..., pos)` uses `pos` to determine where to place the legend.

- `pos = -1` places the legend outside the axes boundary on the right side.
- `pos = 0` places the legend inside the axes boundary, obscuring as few points as possible.
- `pos = 1` places the legend in the upper-right corner of the axes (default).
- `pos = 2` places the legend in the upper-left corner of the axes.
- `pos = 3` places the legend in the lower-left corner of the axes.
- `pos = 4` places the legend in the lower-right corner of the axes.

`[legend_h, object_h, plot_h, text_strings] = legend(...)` returns:

- `legend_h` – handle of the legend axes

- `object_h` – handles of the line, patch and text graphics objects used in the legend
- `plot_h` – handles of the lines and patches used in the plot
- `text_strings` – cell array of the text strings used in the legend.

These handles enable you to modify the properties of the respective objects.

Remarks

`legend` associates strings with the objects in the axes in the same order that they are listed in the axes `Children` property. By default, the legend annotates the current axes.

`MATLAB` displays only one legend per axes. `legend` positions the legend based on a variety of factors, such as what objects the legend obscures.

`legend` installs a figure `Resi zeFc`n, if there is not already a user-defined `Resi zeFc`n assigned to the figure. This `Resi zeFc`n attempts to keep the legend the same size.

Moving the Legend

You can move the legend by pressing the left mouse button while the cursor is over the legend and dragging the legend to a new location. Double clicking on a label allows you to edit the label.


Examples

Add a legend to a graph showing a sine and cosine function:

```
x = -pi : pi /20: pi ;  
plot(x, cos(x), '-ro', x, sin(x), '-. b')
```

legend

```
h = legend('cos', 'sin', 2);
```



In this example, the `plot` command specifies a solid, red line ('`-r`') for the cosine function and a dash-dot, blue line ('`-. b`') for the sine function.

See Also

`LineSpec`, `plot`

Purpose Associated Legendre functions

Syntax

$$P = \text{legendre}(n, X)$$

$$S = \text{legendre}(n, X, 'sch')$$

Definition The Legendre functions are defined by

$$P_n^m(x) = (-1)^m (1 - x^2)^{m/2} \frac{d^m}{dx^m} P_n(x)$$

where

$$P_n(x)$$

is the Legendre polynomial of degree n .

$$P_n(x) = \frac{1}{2^n n!} \left[\frac{d^n}{dx^n} (x^2 - 1)^n \right]$$

The Schmidt seminormalized associated Legendre functions are related to the nonnormalized associated Legendre functions $P_n^m(x)$ by

$$S_n^m(x) = (-1)^m \sqrt{\frac{2(n-m)!}{(n+m)!}} P_n^m(x)$$

where $m > 0$.

Description $P = \text{legendre}(n, X)$ computes the associated Legendre functions of degree n and order $m = 0, 1, \dots, n$, evaluated at X . Argument n must be a scalar integer less than 256, and X must contain real values in the domain $-1 \leq x \leq 1$.

The returned array P has one more dimension than X , and each element $P(m+1, d1, d2, \dots)$ contains the associated Legendre function of degree n and order m evaluated at $X(d1, d2, \dots)$.

legendre

If X is a vector, then P is a matrix of the form:

$$\begin{matrix} P_2^0(x(1)) & P_2^0(x(2)) & P_2^0(x(3)) & \dots \\ P_2^1(x(1)) & P_2^1(x(2)) & P_2^1(x(3)) & \dots \\ P_2^2(x(1)) & P_2^2(x(2)) & P_2^2(x(3)) & \dots \end{matrix}$$

S = legendre(..., 'sch') computes the Schmidt seminormalized associated Legendre functions $S_n^m(x)$.

Examples

The statement legendre(2, 0: 0.1: 0.2) returns the matrix

	x = 0	x = 0.1	x = 0.2
m = 0	- 0. 5000	- 0. 4850	- 0. 4400
m = 1	0	- 0. 2985	- 0. 5879
m = 2	3. 0000	2. 9700	2. 8800

Note that this matrix is of the form shown at the bottom of the previous page.

Given,

```
X = rand(2, 4, 5); N = 2;  
P = legendre(N, X)
```

Then size(P) is 3-by-2-by-4-by-5, and P(:, 1, 2, 3) is the same as legendre(n, X(1, 2, 3)).

Purpose	Length of vector
Syntax	<code>n = length(X)</code>
Description	The statement <code>length(X)</code> is equivalent to <code>max(size(X))</code> for nonempty arrays and 0 for empty arrays.
	<code>n = length(X)</code> returns the size of the longest dimension of <code>X</code> . If <code>X</code> is a vector, this is the same as its length.
Examples	<pre>x = ones(1, 8); n = length(x) n = 8</pre> <pre>x = rand(2, 10, 3); n = length(x) n = 10</pre>
See Also	<code>ndims</code> , <code>size</code>

length (serial)


Purpose	Length of serial port object array
Syntax	<code>length(obj)</code>
Arguments	<code>obj</code> A serial port object or an array of serial port objects.
Description	<code>length(obj)</code> returns the length of <code>obj</code> . It is equivalent to the command <code>max(size(obj))</code> .
See Also	Functions size

Purpose	Show license number for MATLAB
Syntax	<code>license</code>
Description	<code>license</code> shows the license number for MATLAB, as a string. It returns <code>demo</code> for demonstration versions and <code>unknown</code> if the license number cannot be determined.
See Also	<code>version</code>

light

Purpose	Create a light object
Syntax	<pre>light('PropertyName', PropertyValue, . . .) handl e = light(. . .)</pre>
Description	<p>light creates a light object in the current axes. lights affect only patch and surface object.</p> <p>light('PropertyName', PropertyValue, . . .) creates a light object using the specified values for the named properties. MATLAB parents the light to the current axes unless you specify another axes with the Parent property.</p> <p>handl e = light(. . .) returns the handle of the light object created.</p>
Remarks	<p>You cannot see a light object <i>per se</i>, but you can see the effects of the light source on patch and surface objects. You can also specify an axes-wide ambient light color that illuminates these objects. However, ambient light is visible only when at least one light object is present and visible in the axes.</p> <p>You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see set and get for examples of how to specify these data types).</p> <p>See also the patch and surface Ambi entStrength, DiffuseStrength, SpecularStrength, SpecularExponent, SpecularColorOrReflectance, and VertexNormals properties. Also see the lighting and material commands.</p>
Examples	<p>Light the peaks surface plot with a light source located at infinity and oriented along the direction defined by the vector [1 0 0], that is, along the <i>x</i>-axis.</p> <pre>h = surf(peaks); set(h, 'FaceLighting', 'phong', 'FaceColor', 'interp', ... 'AmbientStrength', 0.5) light('Position', [1 0 0], 'Style', 'infinite');</pre>

Object Hierarchy



Setting Default Properties

You can set default light properties on the axes, figure, and root levels:

```

set(0, 'DefaultLightProperty', PropertyValue...)
set(gcf, 'DefaultLightProperty', PropertyValue...)
set(gca, 'DefaultLightProperty', PropertyValue...)
  
```

Where *Property* is the name of the light property and *PropertyValue* is the value you are specifying. Use *set* and *get* to access light properties.

The following table lists all light properties and provides a brief description of each. The property name links take you to an expanded description of the properties.

Property Name	Property Description	Property Value
Defining the Light		
Color	Color of the light produced by the light object	Values: ColorSpec
Position	Location of light in the axes	Values: x-, y-, z-coordinates in axes units Default: [1 0 1]
Style	Parallel or divergent light source	Values: infinite, local

light

Property Name	Property Description	Property Value
Controlling the Appearance		
Selecti onH i gh t	This property is not used by light objects	Values: on, off Default: on
Vi si bl e	Make the effects of the light visible or invisible	Values: on, off Default: on
Controlling Access to Objects		
Handl eVi si bi li ty	Determines if and when the the line's handle is visible to other functions	Values: on, call back, off Default: on
Hi tTest	This property is not used by light objects	Values: on, off Default: on
General Information About the Light		
Chi ldren	Light objects have no children	Values: [] (empty matrix)
Parent	The parent of a light object is always an axes object	Value: axes handle
Sel ect ed	This property is not used by light objects	Values: on, off Default: on
Tag	User-specified label	Value: any string Default: '' (empty string)
Type	The type of graphics object (read only)	Value: the string ' l i ght '
UserData	User-specified data	Values: any matrix Default: [] (empty matrix)
Properties Related to Callback Routine Execution		
BusyAction	Specify how to handle callback routine interruption	Values: cancel , queue Default: queue
ButtonDownFcn	This property is not used by light objects	Values: string Default: empty string

Property Name	Property Description	Property Value
CreateFcn	Define a callback routine that executes when a light is created	Values: string (command or M-file name) Default: empty string
DeleteFcn	Define a callback routine that executes when the light is deleted (via close or delete)	Values: string (command or M-file name) Default: empty string
Interruptible	Determine if callback routine can be interrupted	Values: on, off Default: on (can be interrupted)
UIContextMenu	This property is not used by light objects	Values: handle of a Uicontextmenu

Light Properties

Modifying Properties

You can set and query graphics object properties in two ways:

- The Property Editor is an interactive tool that enables you to see and change object property values.
- The set and get commands enable you to set and query the values of properties

To change the default value of properties see [Setting Default Property Values](#).

Light Property Descriptions

This section lists property names along with the type of values each accepts.

BusyAction `cancel | {queue}`

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback routines. If there is a callback routine executing, subsequently invoked callback routes always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are:

- `cancel` – discard the event that attempted to execute a second callback routine.
- `queue` – queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn `string`

This property is not useful on lights.

Children `handles`

The empty matrix; light objects have no children.

Clipping `on | off`

Clipping has no effect on light objects.

Color `Col or Spec`

Color of light. This property defines the color of the light emanating from the light object. Define it as three-element RGB vector or one of MATLAB's predefined names. See the Col or Spec reference page for more information.

CreateFcn string

Callback routine executed during object creation. This property defines a callback routine that executes when MATLAB creates a light object. You must define this property as a default value for lights. For example, the statement,

```
set(0, 'DefaultLightCreateFcn', 'set(gcf, ''Colormap'', hsv)')
```

sets the current figure colormap to hsv whenever you create a light object. MATLAB executes this routine after setting all light properties. Setting this property on an existing light object has no effect.

The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

DeleteFcn string

Delete light callback routine. A callback routine that executes when you delete the light object (i.e., when you issue a delete command or clear the axes or figure containing the light). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

HandleVisibility {on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when HandleVisibility is on.

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaling a user-typed string), and so temporarily hides its own handles during the execution of that function.

Light Properties

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes `get`, `findobj`, `gca`, `gcf`, `gco`, `newplot`, `cla`, `clf`, and `close`.

When a handle's visibility is restricted using `callback` or `off`, the object's handle does not appear in its parent's `Children` property, figures do not appear in the root's `CurrentFigure` property, objects do not appear in the root's `CallbackObject` property or in the figure's `CurrentObject` property, and axes do not appear in their parent's `CurrentAxes` property.

You can set the root `ShowHiddenHandles` property to `on` to make all handles visible, regardless of their `HandleVisibility` settings (this does not affect the values of the `HandleVisibility` properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

HitTest {`on`} | `off`

This property is not used by light objects.

Interruptible {`on`} | `off`

Callback routine interruption mode. Light object callback routines defined for the `DeleteFcn` property are not affected by the `Interruptible` property.

Parent handle of parent axes

Light objects parent. The handle of the light object's parent axes. You can move a light object to another axes by changing this property to the new axes handle.

Position [x, y, z] in axes data units

Location of light object. This property specifies a vector defining the location of the light object. The vector is defined from the origin to the specified x, y, and z coordinates. The placement of the light depends on the setting of the `Style` property:

- If the `Style` property is set to `local`, `Position` specifies the actual location of the light (which is then a point source that radiates from the location in all directions).
- If the `Style` property is set to `infinite`, `Position` specifies the direction from which the light shines in parallel rays.

Selected on | off

This property is not used by light objects.

SelectionHighlight {on} | off

This property is not used by light objects.

Style {infinite} | local

Parallel or divergent light source. This property determines whether MATLAB places the light object at infinity, in which case the light rays are parallel, or at the location specified by the Position property, in which case the light rays diverge in all directions. See the Position property.

Tag string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Type string (read only)

Type of graphics object. This property contains a string that identifies the class of graphics object. For light objects, Type is always 'light'.

UIContextMenu handle of a uicontextmenu object

This property is not used by light objects.

UserData matrix

User-specified data. This property can be any data you want to associate with the light object. The light does not use this property, but you can access it using set and get.

Visible {on} | off

Light visibility. While light objects themselves are not visible, you can see the light on patch and surface objects. When you set Visible to off, the light emanating from the source is not visible. There must be at least one light object in the axes whose Visible property is on for any lighting features to be enabled (including the axes AmbientLightColor and patch and surface AmbientStrength).

Light Properties

See Also

[lighting](#), [material](#), [patch](#), [surface](#)

Purpose	Create or position a light object in spherical coordinates
Syntax	<pre>lightangle(az, el) light_handle = lightangle(az, el) lightangle(light_handle, az, el) [az el] = lightangle(light_handle)</pre>
Description	<p><code>lightangle(az, el)</code> creates a light at the position specified by azimuth and elevation. <code>az</code> is the azimuthal (horizontal) rotation and <code>el</code> is the vertical elevation (both in degrees). The interpretation of azimuth and elevation is the same as that of the <code>view</code> command.</p> <p><code>light_handle = lightangle(az, el)</code> creates a light and returns the handle of the light in <code>light_handle</code>.</p> <p><code>lightangle(light_handle, az, el)</code> sets the position of the light specified by <code>light_handle</code>.</p> <p><code>[az, el] = lightangle(light_handle)</code> returns the azimuth and elevation of the light specified by <code>light_handle</code>.</p>
Remarks	By default, when a light is created, its style is <code>infinite</code> . If the light handle passed into <code>lightangle</code> refers to a local light, the distance between the light and the camera target is preserved as the position is changed.
Examples	<pre>surf(peaks) axis vis3d h = light; for az = -50: 10: 50 lightangle(h, az, 30) drawnow end</pre>
See Also	<code>light</code> , <code>camlight</code> , <code>view</code>

lighting

Purpose	Select the lighting algorithm
Syntax	<code>lighting flat</code> <code>lighting gouraud</code> <code>lighting phong</code> <code>lighting none</code>
Description	<code>lighting</code> selects the algorithm used to calculate the effects of light objects on all surface and patch objects in the current axes. <code>lighting flat</code> selects flat lighting. <code>lighting gouraud</code> selects gouraud lighting. <code>lighting phong</code> selects phong lighting. <code>lighting none</code> turns off lighting.
Remarks	The <code>surf</code> , <code>mesh</code> , <code>pcolor</code> , <code>fill</code> , <code>fill3</code> , <code>surface</code> , and <code>patch</code> functions create graphics objects that are affected by light sources. The <code>lighting</code> command sets the <code>FaceLighting</code> and <code>EdgeLighting</code> properties of surfaces and patches appropriately for the graphics object.
See Also	<code>light</code> , <code>material</code> , <code>patch</code> , <code>surface</code>

Purpose	Convert linear audio signal to mu-law
Syntax	<code>mu = lin2mu(y)</code>
Description	<code>mu = lin2mu(y)</code> converts linear audio signal amplitudes in the range $-1 \leq Y \leq 1$ to mu-law encoded “flints” in the range $0 \leq u \leq 255$.
See Also	<code>auwrite, mu2lin</code>

line

Purpose	Create line object
Syntax	<code>line(X, Y)</code> <code>line(X, Y, Z)</code> <code>line(X, Y, Z, '<i>PropertyName</i>', <i>PropertyValue</i>, ...)</code> <code>line('PropertyName', <i>PropertyValue</i>, ...)</code> low-level-PN/PV pairs only <code>h = line(...)</code>
Description	<p><code>line</code> creates a line object in the current axes. You can specify the color, width, line style, and marker type, as well as other characteristics.</p> <p>The <code>line</code> function has two forms:</p> <ul style="list-style-type: none">Automatic color and line style cycling. When you specify matrix coordinate data using the informal syntax (i.e., the first three arguments are interpreted as the coordinates), <code>line(X, Y, Z)</code> MATLAB cycles through the axes <code>ColorOrder</code> and <code>LineStyleOrder</code> property values the way the <code>plot</code> function does. However, unlike <code>plot</code>, <code>line</code> does not call the <code>newplot</code> function.Purely low-level behavior. When you call <code>line</code> with only property name/property value pairs, <code>line('XData', x, 'YData', y, 'ZData', z)</code> MATLAB draws a line object in the current axes using the default line color (see the <code>colordef</code> function for information on color defaults). Note that you cannot specify matrix coordinate data with the low-level form of the <code>line</code> function. <p><code>line(X, Y)</code> adds the line defined in vectors <code>X</code> and <code>Y</code> to the current axes. If <code>X</code> and <code>Y</code> are matrices of the same size, <code>line</code> draws one line per column.</p> <p><code>line(X, Y, Z)</code> creates lines in three-dimensional coordinates.</p> <p><code>line(X, Y, Z, '<i>PropertyName</i>', <i>PropertyValue</i>, ...)</code> creates a line using the values for the property name/property value pairs specified and default values for all other properties.</p> <p>See the <code>LineStyle</code> and <code>Marker</code> properties for a list of supported values.</p>

`line('XData', x, 'YData', y, 'ZData', z, 'PropertyName', PropertyValue, ...)` creates a line in the current axes using the property values defined as arguments. This is the low-level form of the `line` function, which does not accept matrix coordinate data as the other informal forms described above.

`h = line(...)` returns a column vector of handles corresponding to each line object the function creates.

Remarks

In its informal form, the `line` function interprets the first three arguments (two for 2-D) as the X, Y, and Z coordinate data, allowing you to omit the property names. You must specify all other properties as name/value pairs. For example,

```
line(X, Y, Z, 'Color', 'r', 'LineWidth', 4)
```

The low-level form of the `line` function can have arguments that are only property name/property value pairs. For example,

```
line('XData', x, 'YData', y, 'ZData', z, 'Color', 'r', 'LineWidth', 4)
```

Line properties control various aspects of the line object and are described in the “Line Properties” section. You can also set and query property values after creating the line using `set` and `get`.

You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see the `set` and `get` reference pages for examples of how to specify these data types).

Unlike high-level functions such as `plot`, `line` does not respect the setting of the figure and axes `NextPlot` properties. It simply adds line objects to the current axes. However, axes properties that are under automatic control such as the axis limits can change to accommodate the line within the current axes.

Examples

This example uses the `line` function to add a shadow to plotted data. First, plot some data and save the line’s handle:


```
t = 0:pi/20:2*pi;
hline1 = plot(t, sin(t), 'k');
```

Next, add a shadow by offsetting the *x* coordinates. Make the shadow line light gray and wider than the default `LineWidth`:

```
hline2 = line(t+.06, sin(t), 'LineWidth', 4, 'Color', [.8 .8 .8]);
```

Finally, pop the first line to the front:

```
set(gca, 'Children', [hLine1 hLine2])
```



Input Argument Dimensions – Informal Form

This statement reuses the one column matrix specified for ZData to produce two lines, each having four points.

```
line(rand(4, 2), rand(4, 2), rand(4, 1))
```

If all the data has the same number of columns and one row each, MATLAB transposes the matrices to produce data for plotting. For example,

```
line(rand(1, 4), rand(1, 4), rand(1, 4))
```

is changed to:

```
line(rand(4, 1), rand(4, 1), rand(4, 1))
```


This also applies to the case when just one or two matrices have one row. For example, the statement,

```
line(rand(2, 4), rand(2, 4), rand(1, 4))
```

is equivalent to:

```
line(rand(4, 2), rand(4, 2), rand(4, 1))
```

Object Hierarchy



Setting Default Properties

You can set default line properties on the axes, figure, and root levels.

```
set(0, 'DefaultLinePropertyName', PropertyValue, . . .)
set(gcf, 'DefaultLinePropertyName', PropertyValue, . . .)
set(gca, 'DefaultLinePropertyName', PropertyValue, . . .)
```

Where *PropertyName* is the name of the line property and *PropertyValue* is the value you are specifying. Use `set` and `get` to access line properties.

The following table lists all light properties and provides a brief description of each. The property name links take you to an expanded description of the properties.

line

Property Name	Property Description	Property Value
Data Defining the Object		
XData	The <i>x</i> -coordinates defining the line	Values: vector or matrix Default: [0 1]
YData	The <i>y</i> -coordinates defining the line	Values: vector or matrix Default: [0 1]
ZData	The <i>z</i> -coordinates defining the line	Values: vector or matrix Default: [] empty matrix
Defining Line Styles and Markers		
LineStyle	Select from five line styles.	Values: -, --, :, -., none Default: -
LineWidth	The width of the line in points	Values: scalar Default: 0.5 points
Marker	Marker symbol to plot at data points	Values: see Marker property Default: none
MarkerEdgeColor	Color of marker or the edge color for filled markers	Values: Col or Spec, none, auto Default: auto
MarkerFaceColor	Fill color for markers that are closed shapes	Values: Col or Spec, none, auto Default: none
MarkerSize	Size of marker in points	Values: size in points Default: 6
Controlling the Appearance		
Clipping	Clipping to axes rectangle	Values: on, off Default: on
EraseMode	Method of drawing and erasing the line (useful for animation)	Values: normal, none, xor, background Default: normal
SelectionHighlight	Highlight line when selected (Selected property set to on)	Values: on, off Default: on

Property Name	Property Description	Property Value
Visible	Make the line visible or invisible	Values: on, off Default: on
Color	Color of the line	ColorSpec

Controlling Access to Objects

HandleVisibility	Determines if and when the line's handle is visible to other functions	Values: on, callback, off Default: on
HitTest	Determines if the line can become the current object (see the figure CurrentObject property)	Values: on, off Default: on

General Information About the Line

Children	Line objects have no children	Values: [] (empty matrix)
Parent	The parent of a line object is always an axes object	Value: axes handle
Selected	Indicate whether the line is in a "selected" state.	Values: on, off Default: on
Tag	User-specified label	Value: any string Default: '' (empty string)
Type	The type of graphics object (read only)	Value: the string 'line'
UserData	User-specified data	Values: any matrix Default: [] (empty matrix)

Properties Related to Callback Routine Execution

BusyAction	Specify how to handle callback routine interruption	Values: cancel, queue Default: queue
ButtonDownFcn	Define a callback routine that executes when a mouse button is pressed on over the line	Values: string Default: '' (empty string)

line

Property Name	Property Description	Property Value
CreateFcn	Define a callback routine that executes when a line is created	Values: string Default: '' (empty string)
DeleteFcn	Define a callback routine that executes when the line is deleted (via close or delete)	Values: string Default: '' (empty string)
Interruptible	Determine if callback routine can be interrupted	Values: on, off Default: on (can be interrupted)
UIContextMenu	Associate a context menu with the line	Values: handle of a Uicontextmenu

Modifying Properties

You can set and query graphics object properties in two ways:

- The Property Editor is an interactive tool that enables you to see and change object property values.
- The set and get commands enable you to set and query the values of properties

To change the default value of properties see Setting Default Property Values.

Line Property Descriptions

This section lists property names along with the type of values each accepts. Curly braces {} enclose default values.

BusyAction cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback routines. If there is a callback routine executing, subsequently invoked callback routes always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are:

- cancel – discard the event that attempted to execute a second callback routine.
- queue – queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn string

Button press callback routine. A callback routine that executes whenever you press a mouse button while the pointer is over the line object. Define this routine as a string that is a valid MATLAB expression or the name of an M-file. The expression executes in the MATLAB workspace.

Children vector of handles

The empty matrix; line objects have no children.

Clipping {on} | off

Clipping mode. MATLAB clips lines to the axes plot box by default. If you set Clipping to off, lines display outside the axes plot box. This can occur if you

Line Properties

create a line, set `hold` to on, freeze axis scaling (`axis manual`), and then create a longer line.

Color `Col orSpec`

Line color. A three-element RGB vector or one of MATLAB's predefined names, specifying the line color. See the `Col orSpec` reference page for more information on specifying color.

CreateFcn `string`

Callback routine executed during object creation. This property defines a callback routine that executes when MATLAB creates a line object. You must define this property as a default value for lines. For example, the statement,

```
set(0, 'DefaultLineCreateFcn', 'set(gca, ''LineStyleOrder'', '-. |---'))
```

defines a default value on the root level that sets the axes `LineStyleOrder` whenever you create a line object. MATLAB executes this routine after setting all line properties. Setting this property on an existing line object has no effect.

The handle of the object whose `CreateFcn` is being executed is accessible only through the root `CallbackObject` property, which you can query using `gcbo`.

DeleteFcn `string`

Delete line callback routine. A callback routine that executes when you delete the line object (e.g., when you issue a `delete` command or clear the axes or figure). MATLAB executes the routine before deleting the object's properties so these values are available to the callback routine.

The handle of the object whose `DeleteFcn` is being executed is accessible only through the root `CallbackObject` property, which you can query using `gcbo`.

EraseMode `{normal} | none | xor | background`

Erase mode. This property controls the technique MATLAB uses to draw and erase line objects. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects redraw is necessary to improve performance and obtain the desired effect.

- `normal` (the default) — Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the

slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.

- none – Do not erase the line when it is moved or destroyed. While the object is still visible on the screen after erasing with EraseMode none, you cannot print it because MATLAB stores no information about its former location.
- xor – Draw and erase the line by performing an exclusive OR (XOR) with the color of the screen beneath it. This mode does not damage the color of the objects beneath the line. However, the line's color depends on the color of whatever is beneath it on the display.
- background – Erase the line by drawing it in the axes' background Col or, or the figure background Col or if the axes Col or is set to none. This damages objects that are behind the erased line, but lines are always properly colored.

Printing with Non-normal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal . This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB may mathematically combine layers of colors (e.g., XORing a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

You can use the MATLAB `getframe` command or other screen capture application to create an image of a figure containing non-normal mode objects.

HitTest {on} | off

Selectable by mouse click. HitTest determines if the line can become the current object (as returned by the `gco` command and the figure `CurrentObj ect` property) as a result of a mouse click on the line. If HitTest is off, clicking on the line selects the object below it (which may be the axes containing it).

HandleVisibility {on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. Handl eVi si bi l i ty is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when Handl eVi si bi l i ty is on.

Line Properties

Setting `HandleVisibility` to `callback` causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Setting `HandleVisibility` to `off` makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaling a user-typed string), and so temporarily hides its own handles during the execution of that function.

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes `get`, `findobj`, `gca`, `gcf`, `gco`, `newplot`, `cla`, `clf`, and `close`.

When a handle's visibility is restricted using `callback` or `off`, the object's handle does not appear in its parent's `Children` property, figures do not appear in the root's `CurrentFigure` property, objects do not appear in the root's `CallbackObject` property or in the figure's `CurrentObject` property, and axes do not appear in their parent's `CurrentAxes` property.

You can set the root `ShowHiddenHandles` property to `on` to make all handles visible, regardless of their `HandleVisibility` settings (this does not affect the values of the `HandleVisibility` properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

Interruptible {`on`} | `off`

Callback routine interruption mode. The `Interruptible` property controls whether a line callback routine can be interrupted by subsequently invoked callback routines. Only callback routines defined for the `ButtonDownFcn` are affected by the `Interruptible` property. MATLAB checks for events that can interrupt a callback routine only when it encounters a `drawnow`, `figure`, `getframe`, or `pause` command in the routine.

LineStyle `{-} | -- | : | -. | none`

Line style. This property specifies the line style. Available line styles are shown in the table.

Symbol	Line Style
-	solid line (default)
--	dashed line
:	dotted line
-.	dash-dot line
none	no line

You can use `LineStyle none` when you want to place a marker at each point but do not want the points connected with a line (see the `Marker` property).

LineWidth scalar

The width of the line object. Specify this value in points (1 point = $1/72$ inch). The default `LineWidth` is 0.5 points.

Marker character (see table)

Marker symbol. The `Marker` property specifies marks that display at data points. You can set values for the `Marker` property independently from the `LineStyle` property. Supported markers include those shown in the table.

Marker Specifier	Description
+	plus sign
o	circle
*	asterisk
.	point
x	cross
s	square

Line Properties

Marker Specifier	Description
d	diamond
^	upward pointing triangle
v	downward pointing triangle
>	right pointing triangle
<	left pointing triangle
p	five-pointed star (pentagram)
h	six-pointed star (hexagram)
none	no marker (default)

MarkerEdgeColor Col orSpec | none | {auto}

Marker edge color. The color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles). Col orSpec defines the color to use. none specifies no color, which makes nonfilled markers invisible. auto sets MarkerEdgeCol or to the same color as the line's Col or property.

MarkerFaceColor Col orSpec | {none} | auto

Marker face color. The fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles). Col orSpec defines the color to use. none makes the interior of the marker transparent, allowing the background to show through. auto sets the fill color to the axes color, or the figure color, if the axes Col or property is set to none (which is the factory default for axes).

MarkerSize size in points

Marker size. A scalar specifying the size of the marker, in points. The default value for MarkerSize is six points (1 point = 1/72 inch). Note that MATLAB draws the point marker (specified by the ' .' symbol) at one-third the specified size.

Parent handle

Line's parent. The handle of the line object's parent axes. You can move a line object to another axes by changing this property to the new axes handle.

Selected on | off

Is object selected. When this property is on, MATLAB displays selection handles if the SelectionHighlight property is also on. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight {on} | off

Objects highlight when selected. When the Selected property is on, MATLAB indicates the selected state by drawing handles at each vertex. When SelectionHighlight is off, MATLAB does not draw the handles.

Tag string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Type string (read only)

Class of graphics object. For line objects, Type is always the string 'line'.

UIContextMenu handle of a uicontextmenu object

Associate a context menu with the line. Assign this property the handle of a uicontextmenu object created in same figure as the line. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the line.

UserData matrix

User-specified data. Any data you want to associate with the line object. MATLAB does not use this data, but you can access it using the set and get commands.

Visible {on} | off

Line visibility. By default, all lines are visible. When set to off, the line is not visible, but still exists and you can get and set its properties.

Line Properties

XData vector of coordinates

X-coordinates. A vector of *x*-coordinates defining the line. YData and ZData must have the same number of rows. (See Examples).

YData vector or matrix of coordinates

Y-coordinates. A vector of *y*-coordinates defining the line. XData and ZData must have the same number of rows.

ZData vector of coordinates

Z-coordinates. A vector of *z*-coordinates defining the line. XData and YData must have the same number of rows.

See Also axes, newplot, plot, plot3

Purpose Line specification syntax

Description This page describes how to specify the properties of lines used for plotting. MATLAB enables you to define many characteristics including:

- Line style
- Line width
- Color
- Marker type
- Marker size
- Marker face and edge coloring (for filled markers)

MATLAB defines string specifiers for line styles, marker types, and colors. The following tables list these specifiers.

LineSpec

Line Style Specifiers

Specifier	Line Style
-	solid line (default)
--	dashed line
:	dotted line
-.	dash-dot line

Marker Specifiers

Specifier	Marker Type
+	plus sign
o	circle
*	asterisk
.	point
x	cross
s	square
d	diamond
^	upward pointing triangle
v	downward pointing triangle
>	right pointing triangle
<	left pointing triangle
p	five-pointed star (pentagram)
h	six-pointed star (hexagram)

Color Specifiers

Specifier	Color
r	red
g	green
b	blue
c	cyan
m	magenta
y	yellow
k	black
w	white

Many plotting commands accept a LineSpec argument that defines three components used to specify lines:

- Line style
- Marker symbol
- Color

For example,

```
plot(x, y, '-o')
```

plots y versus x using a dash-dot line (-.), places circular markers (o) at the data points, and colors both line and marker red (r). Specify the components (in any order) as a quoted string after the data arguments.

If you specify a marker, but not a line style, MATLAB plots only the markers. For example,

```
plot(x, y, 'd')
```

Related Properties

When using the `plot` and `plot3` functions, you can also specify other characteristics of lines using graphics properties:

LineSpec

- LineWidth – specifies the width (in points) of the line
- MarkerEdgeColor – specifies the color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles).
- MarkerFaceColor – specifies the color of the face of filled markers.
- MarkerSize – specifies the size of the marker in points.


In addition, you can specify the LineStyle, Color, and Marker properties instead of using the symbol string. This is useful if you want to specify a color that is not in the list by using RGB values. See ColorSpec for more information on color.

Examples

Plot the sine function over three different ranges using different line styles, colors, and markers.

```
t = 0: pi/20: 2*pi;
plot(t, sin(t), '-.r*')
hold on
plot(sin(t-pi/2), '--mo')
plot(sin(t-pi), ':bs')
```


hold off



Create a plot illustrating how to set line properties.

```
plot(t, sin(2*t), 'mo', ...
      'LineWidth', 2, ...
      'MarkerEdgeColor', 'k', ...
      'MarkerFaceColor', [.49 1 .63], ...
      'MarkerSize', 12)
```

LineSpec



See Also

`line`, `plot`, `patch`, `set`, `surface`, `axes LineStyleOrder` property

Purpose Generate linearly spaced vectors

Syntax

```
y = linspace(a, b)
y = linspace(a, b, n)
```

Description The `linspace` function generates linearly spaced vectors. It is similar to the colon operator “`:`”, but gives direct control over the number of points.

`y = linspace(a, b)` generates a row vector `y` of 100 points linearly spaced between and including `a` and `b`.

`y = linspace(a, b, n)` generates a row vector `y` of `n` points linearly spaced between and including `a` and `b`.

See Also

`logspace`
The colon operator :

listdlg

Purpose	Create list selection dialog box																								
Syntax	[Selection, ok] = listdlg('ListString', S, ...)																								
Description	[Selection, ok] = listdlg('ListString', S) creates a modal dialog box that enables you to select one or more items from a list. Selection is a vector of indices of the selected strings (in single selection mode, its length is 1). Selection is [] when ok is 0. ok is 1 if you click the OK button, or 0 if you click the Cancel button or close the dialog box. Double-clicking on an item or pressing Return when multiple items are selected has the same effect as clicking the OK button. The dialog box has a Select all button (when in multiple selection mode) that enables you to select all list items.																								
Inputs are in parameter/value pairs:																									
<table border="1"><thead><tr><th>Parameter</th><th>Description</th></tr></thead><tbody><tr><td>'ListString'</td><td>Cell array of strings that specify the list box items.</td></tr><tr><td>'SelectionMode'</td><td>String indicating whether one or many items can be selected: 'single' or 'multiple' (the default).</td></tr><tr><td>'ListSize'</td><td>List box size in pixels, specified as a two element vector, [width height]. Default is [160 300].</td></tr><tr><td>'InitialValue'</td><td>Vector of indices of the list box items that are initially selected. Default is 1, the first item.</td></tr><tr><td>'Name'</td><td>String for the dialog box's title. Default is "".</td></tr><tr><td>'PromptString'</td><td>String matrix or cell array of strings that appears as text above the list box. Default is {}.</td></tr><tr><td>'OKString'</td><td>String for the OK button. Default is 'OK'.</td></tr><tr><td>'CancelString'</td><td>String for the Cancel button. Default is 'Cancel'.</td></tr><tr><td>'uh'</td><td>Uicontrol button height, in pixels. Default is 18.</td></tr><tr><td>'fus'</td><td>Frame/uicontrol spacing, in pixels. Default is 8.</td></tr><tr><td>'ffs'</td><td>Frame/figure spacing, in pixels. Default is 8.</td></tr></tbody></table>		Parameter	Description	'ListString'	Cell array of strings that specify the list box items.	'SelectionMode'	String indicating whether one or many items can be selected: 'single' or 'multiple' (the default).	'ListSize'	List box size in pixels, specified as a two element vector, [width height]. Default is [160 300].	'InitialValue'	Vector of indices of the list box items that are initially selected. Default is 1, the first item.	'Name'	String for the dialog box's title. Default is "".	'PromptString'	String matrix or cell array of strings that appears as text above the list box. Default is {}.	'OKString'	String for the OK button. Default is 'OK'.	'CancelString'	String for the Cancel button. Default is 'Cancel'.	'uh'	Uicontrol button height, in pixels. Default is 18.	'fus'	Frame/uicontrol spacing, in pixels. Default is 8.	'ffs'	Frame/figure spacing, in pixels. Default is 8.
Parameter	Description																								
'ListString'	Cell array of strings that specify the list box items.																								
'SelectionMode'	String indicating whether one or many items can be selected: 'single' or 'multiple' (the default).																								
'ListSize'	List box size in pixels, specified as a two element vector, [width height]. Default is [160 300].																								
'InitialValue'	Vector of indices of the list box items that are initially selected. Default is 1, the first item.																								
'Name'	String for the dialog box's title. Default is "".																								
'PromptString'	String matrix or cell array of strings that appears as text above the list box. Default is {}.																								
'OKString'	String for the OK button. Default is 'OK'.																								
'CancelString'	String for the Cancel button. Default is 'Cancel'.																								
'uh'	Uicontrol button height, in pixels. Default is 18.																								
'fus'	Frame/uicontrol spacing, in pixels. Default is 8.																								
'ffs'	Frame/figure spacing, in pixels. Default is 8.																								

Example

This example displays a dialog box that enables the user to select a file from the current directory. The function returns a vector. Its first element is the index to the selected file; its second element is 0 if no selection is made, or 1 if a selection is made.

```
d = dir;
str = {d.name};
[s, v] = listdlg('PromptString', 'Select a file:', ...
    'SelectionMode', 'single', ...
    'ListString', str)
```

See Also

dir

load

Purpose	Load workspace variables from disk
Syntax	<pre>load load filename load filename X Y Z load filename -ascii load filename -mat S = load(...)</pre>
Description	<p><code>load</code> loads all the variables from the MAT-file <code>matlab.mat</code>, if it exists, and returns an error if it doesn't exist.</p> <p><code>load filename</code> loads all the variables from <code>filename</code> given a full pathname or a MATLABPATH relative partial pathname. If <code>filename</code> has no extension, <code>load</code> looks for file named <code>filename</code> or <code>filename.mat</code> and treats it as a binary MAT-file. If <code>filename</code> has an extension other than <code>.mat</code>, <code>load</code> treats the file as ASCII data.</p> <p><code>load filename X Y Z ...</code> loads just the specified variables from the MAT-file. The wildcard '*' loads variables that match a pattern (MAT-file only).</p> <p><code>load -ascii filename</code> or <code>load -mat filename</code> forces <code>load</code> to treat the file as either an ASCII file or a MAT-file, regardless of file extension. With <code>-ascii</code>, <code>load</code> returns an error if the file is not numeric text. With <code>-mat</code>, <code>load</code> returns an error if the file is not a MAT-file.</p> <p><code>load -ascii filename</code> returns all the data in the file as a single two dimensional double array with its name taken from the filename (minus any extension). The number of rows is equal to the number of lines in the file and the number of columns is equal to the number of values on a line. An error occurs if the number of values differs between any two rows.</p> <p><code>load filename.ext</code> reads ASCII files that contain rows of space-separated values. The resulting data is placed into a variable with the same name as the file (without the extension). ASCII files may contain MATLAB comments (lines that begin with %).</p> <p>If <code>filename</code> is a MAT-file, <code>load</code> creates the requested variables from <code>filename</code> in the workspace. If <code>filename</code> is not a MAT-file, <code>load</code> creates a double precision array with a name based on <code>filename</code>. <code>load</code> replaces leading underscores or</p>

digits in `filename` with an X and replaces other non-alphabetic character with underscores. The text file must be organized as a rectangular table of numbers, separated by blanks, with one row per line, and an equal number of elements in each row.

`S = load(...)` returns the contents of a MAT-file in the variable `S`. If the file is a MAT-file, `S` is a struct containing fields that match the variables in retrieved. When the file contains ASCII data, `S` is a double-precision array.

Use the functional form of `load`, such as `load('filename')`, when the file name is stored in a string, when an output argument is requested, or if `filename` contains spaces. To specify a command line option with this functional form, specify the option as a string argument, including the hyphen. For example,

```
load('myfile.dat', '-mat')
```

Remarks

MAT-files are double-precision binary MATLAB format files created by the `save` command and readable by the `load` command. They can be created on one machine and later read by MATLAB on another machine with a different floating-point format, retaining as much accuracy and range as the disparate formats allow. They can also be manipulated by other programs, external to MATLAB.

The Application Program Interface Libraries contain C- and Fortran-callable routines to read and write MAT-files from external programs.

See Also

`fprintf`, `fscanf`, `partialpath`, `save`, `spconvert`

load (activex)

Purpose	Initialize an ActiveX object from a file.				
Syntax	<code>load(h, filename)</code>				
Arguments	<table><tr><td><code>h</code></td><td>A MATLAB ActiveX object.</td></tr><tr><td><code>filename</code></td><td>The full pathname of the serialized data.</td></tr></table>	<code>h</code>	A MATLAB ActiveX object.	<code>filename</code>	The full pathname of the serialized data.
<code>h</code>	A MATLAB ActiveX object.				
<code>filename</code>	The full pathname of the serialized data.				
Returns	<code>void</code>				
Description	<code>load</code> initializes the ActiveX object associated with the interface represented by the MATLAB ActiveX object <code>H</code> from a file. The file must have been created previously by serializing an instance of the same control.				
Example	<pre>h = actxcontrol('MwSamp.mwsampctrl.1'); load(h, 'c:\temp\mycontrol.acx');</pre>				

Purpose	Load serial port objects and variables into the MATLAB workspace						
Syntax	<pre>load filename load filename obj1 obj2... out = load('filename', 'obj1', 'obj2', ...)</pre>						
Arguments	<table><tr><td>filename</td><td>The MAT-file name.</td></tr><tr><td>obj1 obj2...</td><td>Serial port objects or arrays of serial port objects.</td></tr><tr><td>out</td><td>A structure containing the specified serial port objects.</td></tr></table>	filename	The MAT-file name.	obj1 obj2...	Serial port objects or arrays of serial port objects.	out	A structure containing the specified serial port objects.
filename	The MAT-file name.						
obj1 obj2...	Serial port objects or arrays of serial port objects.						
out	A structure containing the specified serial port objects.						
Description	<p><code>load filename</code> returns all variables from the MAT-file specified by <code>filename</code> into the MATLAB workspace.</p> <p><code>load filename obj1 obj2...</code> returns the serial port objects specified by <code>obj1</code> <code>obj2...</code> from the MAT-file <code>filename</code> into the MATLAB workspace.</p> <p><code>out = load('filename', 'obj1', 'obj2', ...)</code> returns the specified serial port objects from the MAT-file <code>filename</code> as a structure to <code>out</code> instead of directly loading them into the workspace. The field names in <code>out</code> match the names of the loaded serial port objects.</p>						
Remarks	<p>Values for read-only properties are restored to their default values upon loading. For example, the <code>Status</code> property is restored to <code>closed</code>. To determine if a property is read-only, examine its reference pages.</p> <p>If you use the <code>help</code> command to display help for <code>load</code>, then you need to supply the pathname shown below.</p> <pre>help serial/private/load</pre>						
Example	<p>Suppose you create the serial port objects <code>s1</code> and <code>s2</code>, configure a few properties for <code>s1</code>, and connect both objects to their instruments.</p> <pre>s1 = serial('COM1'); s2 = serial('COM2'); set(s1, 'Parity', 'mark', 'DataBits', 7) fopen(s1) fopen(s2)</pre>						

load (serial)

Save s1 and s2 to the file `MyObject.mat`, and then load the objects into the workspace using new variables.

```
save MyObject s1 s2
news1 = load MyObject s1
news2 = load('MyObject', 's2')
```

Values for read-only properties are restored to their default values upon loading, while all other properties values are honored.

```
get(news1, {'Parity', 'DataBits', 'Status'})
ans =
    'mark'      [7]      'closed'
get(news2, {'Parity', 'DataBits', 'Status'})
ans =
    'none'      [8]      'closed'
```

See Also

Functions

`save`

Properties

`Status`

Purpose	User-defined extension of the <code>load</code> function for user objects
Syntax	<code>b = loadobj(a)</code>
Description	<p><code>b = loadobj(a)</code> extends the <code>load</code> function for user objects. When an object is loaded from a MAT file, the <code>load</code> function calls the <code>loadobj</code> method for the object's class if it is defined. The <code>loadobj</code> method must have the calling sequence shown; the input argument <code>a</code> is the object as loaded from the MAT file and the output argument <code>b</code> is the object that the <code>load</code> function will load into the workspace.</p> <p>These steps describe how an object is loaded from a MAT file into the workspace:</p> <ol style="list-style-type: none">1 The <code>load</code> function detects the object <code>a</code> in the MAT file.2 The <code>load</code> function looks in the current workspace for an object of the same class as the object <code>a</code>. If there isn't an object of the same class in the workspace, <code>load</code> calls the default constructor, registering an object of that class in the workspace. The default constructor is the constructor function called with no input arguments.3 The <code>load</code> function checks to see if the structure of the object <code>a</code> matches the structure of the object registered in the workspace. If the objects match, <code>a</code> is loaded. If the objects don't match, <code>load</code> converts <code>a</code> to a structure variable.4 The <code>load</code> function calls the <code>loadobj</code> method for the object's class if it is defined. <code>load</code> passes the object <code>a</code> to the <code>loadobj</code> method as an input argument. Note, the format of the object <code>a</code> is dependent on the results of step 3 (object or structure). The output argument of <code>loadobj</code>, <code>b</code>, is loaded into the workspace in place of the object <code>a</code>.
Remarks	<p><code>loadobj</code> can be overloaded only for user objects. <code>load</code> will not call <code>loadobj</code> for built-in datatypes (such as <code>double</code>).</p> <p><code>loadobj</code> is invoked separately for each object in the MAT file. The <code>load</code> function recursively descends cell arrays and structures applying the <code>loadobj</code> method to each object encountered.</p> <p>A child object does not inherit the <code>loadobj</code> method of its parent class. To implement <code>loadobj</code> for any class, including a class that inherits from a parent, you must define a <code>loadobj</code> method within that class directory.</p>

loadobj

See Also

[load](#), [save](#), [saveobj](#)

Purpose	Natural logarithm
Syntax	$Y = \log(X)$
Description	The <code>log</code> function operates element-wise on arrays. Its domain includes complex and negative numbers, which may lead to unexpected results if used unintentionally. $Y = \log(X)$ returns the natural logarithm of the elements of X . For complex or negative z , where $z = x + y*i$, the complex logarithm is returned.
	$\log(z) = \log(\text{abs}(z)) + i * \text{atan2}(y, x)$
Examples	The statement <code>abs(log(-1))</code> is a clever way to generate π . <code>ans =</code> 3. 1416
See Also	<code>exp, log10, log2, logm</code>

log2

Purpose	Base 2 logarithm and dissect floating-point numbers into exponent and mantissa																					
Syntax	$Y = \log2(X)$ $[F, E] = \log2(X)$																					
Description	$Y = \log2(X)$ computes the base 2 logarithm of the elements of X . $[F, E] = \log2(X)$ returns arrays F and E . Argument F is an array of real values, usually in the range $0.5 \leq \text{abs}(F) < 1$. For real X , F satisfies the equation: $X = F \cdot 2^E$. Argument E is an array of integers that, for real X , satisfy the equation: $X = F \cdot 2^E$.																					
Remarks	This function corresponds to the ANSI C function <code>frexp()</code> and the IEEE floating-point standard function <code>logb()</code> . Any zeros in X produce $F = 0$ and $E = 0$.																					
Examples	For IEEE arithmetic, the statement $[F, E] = \log2(X)$ yields the values:																					
	<table><thead><tr><th>X</th><th>F</th><th>E</th></tr></thead><tbody><tr><td>1</td><td>1/2</td><td>1</td></tr><tr><td>pi</td><td>pi / 4</td><td>2</td></tr><tr><td>-3</td><td>-3/4</td><td>2</td></tr><tr><td>eps</td><td>1/2</td><td>-51</td></tr><tr><td>real max</td><td>1 - eps / 2</td><td>1024</td></tr><tr><td>real min</td><td>1/2</td><td>-1021</td></tr></tbody></table>	X	F	E	1	1/2	1	pi	pi / 4	2	-3	-3/4	2	eps	1/2	-51	real max	1 - eps / 2	1024	real min	1/2	-1021
X	F	E																				
1	1/2	1																				
pi	pi / 4	2																				
-3	-3/4	2																				
eps	1/2	-51																				
real max	1 - eps / 2	1024																				
real min	1/2	-1021																				
See Also	<code>log</code> , <code>pow2</code>																					

Purpose	Common (base 10) logarithm
Syntax	$Y = \log10(X)$
Description	The <code>log10</code> function operates element-by-element on arrays. Its domain includes complex numbers, which may lead to unexpected results if used unintentionally.
	$Y = \log10(X)$ returns the base 10 logarithm of the elements of X .
Examples	<code>log10(real max)</code> is 308.2547 and <code>log10(eps)</code> is -15.6536
See Also	<code>exp, log, log2, logm</code>


logical

Purpose	Convert numeric values to logical												
Syntax	<code>K = logical(A)</code>												
Description	<code>K = logical(A)</code> returns an array that can be used for logical indexing or logical tests. <code>A(B)</code> , where <code>B</code> is a logical array, returns the values of <code>A</code> at the indices where the real part of <code>B</code> is nonzero. <code>B</code> must be the same size as <code>A</code> .												
Remarks	Most arithmetic operations remove the logicalness from an array. For example, adding zero to a logical array removes its logical characteristic. <code>A = +A</code> is the easiest way to convert a logical double array, <code>A</code> , to a strictly numeric double array. Logical arrays are also created by the relational operators (<code>==,<,>,~, etc.</code>) and functions like <code>any</code> , <code>all</code> , <code>isnan</code> , <code>isinf</code> , and <code>isfinite</code> .												
Examples	Given <code>A = [1 2 3; 4 5 6; 7 8 9]</code> , the statement <code>B = logical(eye(3))</code> returns a logical array <code>B =</code> <table><tr><td>1</td><td>0</td><td>0</td></tr><tr><td>0</td><td>1</td><td>0</td></tr><tr><td>0</td><td>0</td><td>1</td></tr></table> which can be used in logical indexing that returns <code>A</code> 's diagonal elements: <code>A(B)</code> <code>ans =</code> <table><tr><td>1</td></tr><tr><td>5</td></tr><tr><td>9</td></tr></table> However, attempting to index into <code>A</code> using the <i>numeric</i> array <code>eye(3)</code> results in: <code>A(eye(3))</code> <code>??? Index into matrix is negative or zero.</code>	1	0	0	0	1	0	0	0	1	1	5	9
1	0	0											
0	1	0											
0	0	1											
1													
5													
9													
See Also	<code>islogical</code> , <code>logical</code> operators												

Purpose	Log-log scale plot
Syntax	<pre>loglog(Y) loglog(X1, Y1, ...) loglog(X1, Y1, LineSpec, ...) loglog(..., 'PropertyName', PropertyValue, ...) h = loglog(...)</pre>
Description	<p><code>loglog(Y)</code> plots the columns of <code>Y</code> versus their index if <code>Y</code> contains real numbers. If <code>Y</code> contains complex numbers, <code>loglog(Y)</code> and <code>loglog(real(Y), imag(Y))</code> are equivalent. <code>loglog</code> ignores the imaginary component in all other uses of this function.</p> <p><code>loglog(X1, Y1, ...)</code> plots all <code>Xn</code> versus <code>Yn</code> pairs. If only <code>Xn</code> or <code>Yn</code> is a matrix, <code>loglog</code> plots the vector argument versus the rows or columns of the matrix, depending on whether the vector's row or column dimension matches the matrix.</p> <p><code>loglog(X1, Y1, LineSpec, ...)</code> plots all lines defined by the <code>Xn</code>, <code>Yn</code>, <code>LineSpec</code> triples, where <code>LineSpec</code> determines line type, marker symbol, and color of the plotted lines. You can mix <code>Xn</code>, <code>Yn</code>, <code>LineSpec</code> triples with <code>Xn</code>, <code>Yn</code> pairs, for example,</p> <pre>loglog(X1, Y1, X2, Y2, LineSpec, X3, Y3)</pre> <p><code>loglog(..., 'PropertyName', PropertyValue, ...)</code> sets property values for all line graphics objects created by <code>loglog</code>. See the <code>line</code> reference page for more information.</p> <p><code>h = loglog(...)</code> returns a column vector of handles to line graphics objects, one handle per line.</p>
Remarks	If you do not specify a color when plotting more than one line, <code>loglog</code> automatically cycles through the colors and line styles in the order specified by the current axes.
Examples	<p>Create a simple <code>loglog</code> plot with square markers.</p> <pre>x = logspace(-1, 2); loglog(x, exp(x), '-s')</pre>

loglog

grid on



See Also

[line](#), [LineSpec](#), [plot](#), [semilogx](#), [semilogy](#)

Purpose	Matrix logarithm
Syntax	$Y = \text{logm}(X)$ $[Y, \text{esterr}] = \text{logm}(X)$
Description	$Y = \text{logm}(X)$ returns the matrix logarithm: the inverse function of $\text{expm}(X)$. Complex results are produced if X has negative eigenvalues. A warning message is printed if the computed $\text{expm}(Y)$ is not close to X . $[Y, \text{esterr}] = \text{logm}(X)$ does not print any warning message, but returns an estimate of the relative residual, $\text{norm}(\text{expm}(Y) - X) / \text{norm}(X)$.
Remarks	If X is real symmetric or complex Hermitian, then so is $\text{logm}(X)$. Some matrices, like $X = [0 \ 1; \ 0 \ 0]$, do not have any logarithms, real or complex, and logm cannot be expected to produce one.
Limitations	For most matrices: $\text{logm}(\text{expm}(X)) = X = \text{expm}(\text{logm}(X))$ These identities may fail for some X . For example, if the computed eigenvalues of X include an exact zero, then $\text{logm}(X)$ generates infinity. Or, if the elements of X are too large, $\text{expm}(X)$ may overflow.
Examples	Suppose A is the 3-by-3 matrix $\begin{matrix} 1 & 1 & 0 \\ 0 & 0 & 2 \\ 0 & 0 & -1 \end{matrix}$ and $X = \text{expm}(A)$ is $X = \begin{matrix} 2.7183 & 1.7183 & 1.0862 \\ 0 & 1.0000 & 1.2642 \\ 0 & 0 & 0.3679 \end{matrix}$ Then $A = \text{logm}(X)$ produces the original matrix A . $A = \begin{matrix} 1 & 1 & 0 \\ 0 & 0 & 2 \\ 0 & 0 & -1 \end{matrix}$

logm

```
1. 0000    1. 0000    0. 0000
      0        0        2. 0000
      0        0     - 1. 0000
```

But $\log(X)$ involves taking the logarithm of zero, and so produces

ans =

```
1. 0000    0. 5413    0. 0826
      - Inf      0        0. 2345
      - Inf      - Inf     - 1. 0000
```

Algorithm

The matrix functions are evaluated using an algorithm due to Parlett, which is described in [1]. The algorithm uses the Schur factorization of the matrix and may give poor results or break down completely when the matrix has repeated eigenvalues. A warning message is printed when the results may be inaccurate.

See Also

expm, funm, sqrtm

References

[1] Golub, G. H. and C. F. Van Loan, *Matrix Computation*, Johns Hopkins University Press, 1983, p. 384.

[2] Moler, C. B. and C. F. Van Loan, "Nineteen Dubious Ways to Compute the Exponential of a Matrix," *SIAM Review* 20, 1979, pp. 801-836.

Purpose	Generate logarithmically spaced vectors
Syntax	$y = \text{logspace}(a, b)$ $y = \text{logspace}(a, b, n)$ $y = \text{logspace}(a, \pi)$
Description	The <code>logspace</code> function generates logarithmically spaced vectors. Especially useful for creating frequency vectors, it is a logarithmic equivalent of <code>linspace</code> and the ":" or colon operator. $y = \text{logspace}(a, b)$ generates a row vector y of 50 logarithmically spaced points between decades 10^a and 10^b . $y = \text{logspace}(a, b, n)$ generates n points between decades 10^a and 10^b . $y = \text{logspace}(a, \pi)$ generates the points between 10^a and π , which is useful for digital signal processing where frequencies over this interval go around the unit circle.
Remarks	All the arguments to <code>logspace</code> must be scalars.
See Also	<code>linspace</code> The colon operator :

lookfor

Purpose	Search for specified keyword in all help entries
Syntax	<code>lookfor topic</code> <code>lookfor topic -all</code>
Description	<code>lookfor topic</code> searches for the string <code>topic</code> in the first comment line (the H1 line) of the help text in all M-files found on MATLAB's search path. For all files in which a match occurs, <code>lookfor</code> displays the H1 line. <code>lookfor topic -all</code> searches the entire first comment block of an M-file looking for <code>topic</code> .
Examples	For example <code>lookfor inverse</code> finds at least a dozen matches, including H1 lines containing “inverse hyperbolic cosine,” “two-dimensional inverse FFT,” and “pseudoinverse.” Contrast this with <code>which inverse</code> or <code>what inverse</code> These functions run more quickly, but probably fail to find anything because MATLAB does not have a function <code>inverse</code> . In summary, <code>what</code> lists the functions in a given directory, <code>which</code> finds the directory containing a given function or file, and <code>lookfor</code> finds all functions in all directories that might have something to do with a given keyword. Even more extensive than the <code>lookfor</code> function is the Find feature in the Current Directory browser. It looks for all occurrences of a specified word in all the M-files in the current directory. See “Finding and Replacing Content Within Files” for instructions.
See Also	<code>dir</code> , <code>doc</code> , <code>filebrowser</code> , <code>help</code> , <code>helpdesk</code> , <code>helpwin</code> , <code>what</code> , <code>which</code> , <code>who</code>

Purpose	Convert string to lower case
Syntax	<code>t = lower('str')</code> <code>B = lower(A)</code>
Description	<code>t = lower('str')</code> returns the string formed by converting any upper-case characters in <code>str</code> to the corresponding lower-case characters and leaving all other characters unchanged. <code>B = lower(A)</code> when <code>A</code> is a cell array of strings, returns a cell array the same size as <code>A</code> containing the result of applying <code>lower</code> to each string within <code>A</code> .
Examples	<code>lower('MathWorks')</code> is <code>mathworks</code> .
Remarks	Character sets supported: <ul style="list-style-type: none">• PC: Windows Latin-1• Other: ISO Latin-1 (ISO 8859-1)
See Also	<code>upper</code>

ls

Purpose	List directory on UNIX
Syntax	ls
Description	ls displays the results of the ls command on UNIX. You can pass any flags to ls that your operating system supports. On UNIX, ls returns a \n delimited string of filenames. On all other platforms, ls executes dir.
See Also	dir

Purpose	Least squares solution in the presence of known covariance
Syntax	$x = \text{lscov}(A, b, V)$ $[x, dx] = \text{lscov}(A, b, V)$
Description	$x = \text{lscov}(A, b, V)$ returns the vector x that solves $A*x = b + e$ where e is normally distributed with zero mean and covariance V . Matrix A must be m -by- n where $m > n$. This is the over-determined least squares problem with covariance V . The solution is found without inverting V .
	$[x, dx] = \text{lscov}(A, b, V)$ returns the standard errors of x in dx . The standard statistical formula for the standard error of the coefficients is:
	$\text{mse} = B' * (\text{inv}(V) - \text{inv}(V) * A * \text{inv}(A' * \text{inv}(V) * A) * A' * \text{inv}(V)) * B. / (m - n)$ $dx = \sqrt{\text{diag}(\text{inv}(A' * \text{inv}(V) * A) * mse)}$
Algorithm	The vector x minimizes the quantity $(A*x - b)' * \text{inv}(V) * (A*x - b)$. The classical linear algebra solution to this problem is
	$x = \text{inv}(A' * \text{inv}(V) * A) * A' * \text{inv}(V) * b$
	but the <code>lscov</code> function instead computes the QR decomposition of A and then modifies Q by V .
See Also	<code>lsqnonneg</code> , <code>qr</code> The arithmetic operator <code>\</code>
Reference	[1] Strang, G., <i>Introduction to Applied Mathematics</i> , Wellesley-Cambridge, 1986, p. 398.

lsqnonneg

Purpose	Linear least squares with nonnegativity constraints				
Syntax	<pre>x = lsqnonneg(C, d) x = lsqnonneg(C, d, x0) x = lsqnonneg(C, d, x0, options) [x, resnorm] = lsqnonneg(...) [x, resnorm, residual] = lsqnonneg(...) [x, resnorm, residual, exitflag] = lsqnonneg(...) [x, resnorm, residual, exitflag, output] = lsqnonneg(...) [x, resnorm, residual, exitflag, output, lambda] = lsqnonneg(...)</pre>				
Description	<p><code>x = lsqnonneg(C, d)</code> returns the vector <code>x</code> that minimizes <code>norm(C*x-d)</code> subject to <code>x >= 0</code>. <code>C</code> and <code>d</code> must be real.</p> <p><code>x = lsqnonneg(C, d, x0)</code> uses <code>x0</code> as the starting point if all <code>x0 >= 0</code>; otherwise, the default is used. The default start point is the origin (the default is used when <code>x0==[]</code> or when only two input arguments are provided).</p> <p><code>x = lsqnonneg(C, d, x0, options)</code> minimizes with the optimization parameters specified in the structure <code>options</code>. You can define these parameters using the <code>optimset</code> function. <code>lsqnonneg</code> uses these <code>options</code> structure fields:</p> <table><tr><td>Display</td><td>Level of display. 'off' displays no output; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.</td></tr><tr><td>TolX</td><td>Termination tolerance on <code>x</code>.</td></tr></table> <p><code>[x, resnorm] = lsqnonneg(...)</code> returns the value of the squared 2-norm of the residual: <code>norm(C*x-d)^2</code>.</p> <p><code>[x, resnorm, residual] = lsqnonneg(...)</code> returns the residual, <code>C*x-d</code>.</p>	Display	Level of display. 'off' displays no output; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.	TolX	Termination tolerance on <code>x</code> .
Display	Level of display. 'off' displays no output; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.				
TolX	Termination tolerance on <code>x</code> .				

`[x, resnorm, residual, exitflag] = lsqnonneg(...)` returns a value `exitflag` that describes the exit condition of `lsqnonneg`:

- | | |
|--------------------|--|
| <code>>0</code> | Indicates that the function converged to a solution <code>x</code> . |
| <code>0</code> | Indicates that the iteration count was exceeded.
Increasing the tolerance (<code>TolX</code> parameter in <code>options</code>) may lead to a solution. |

`[x, resnorm, residual, exitflag, output] = lsqnonneg(...)` returns a structure `output` that contains information about the operation:

- | | |
|---------------------------------|--------------------------------|
| <code>output.algorithm</code> | The algorithm used |
| <code>output. iterations</code> | The number of iterations taken |

`[x, resnorm, residual, exitflag, output, lambda] = lsqnonneg(...)` returns the dual vector (Lagrange multipliers) `lambda`, where `lambda(i) <= 0` when `x(i)` is (approximately) 0, and `lambda(i)` is (approximately) 0 when `x(i) > 0`.

Examples

Compare the unconstrained least squares solution to the `lsqnonneg` solution for a 4-by-2 problem:

```
C = [
    0.0372    0.2869
    0.6861    0.7071
    0.6233    0.6245
    0.6344    0.6170];
```

```
d = [
    0.8587
    0.1781
    0.0747
    0.8405];
```

```
[C\d lsqnonneg(C, d)] =
    -2.5627      0
    3.1108    0.6929
```

```
[norm(C*(C\d) - d) norm(C*lsqnonneg(C, d) - d)] =
    0.6674 0.9118
```

The solution from `lsqnonneg` does not fit as well (has a larger residual), as the least squares solution. However, the nonnegative least squares solution has no negative components.

Algorithm

`lsqnonneg` uses the algorithm described in [1]. The algorithm starts with a set of possible basis vectors and computes the associated dual vector λ . It then selects the basis vector corresponding to the maximum value in λ in order to swap out of the basis in exchange for another possible candidate. This continues until $\lambda \leq 0$.

See Also

The arithmetic operator `\`, `optimset`

References

[1] Lawson, C.L. and R.J. Hanson, *Solving Least Squares Problems*, Prentice-Hall, 1974, Chapter 23, p. 161.

Purpose LSQR implementation of Conjugate Gradients on the Normal Equations

Syntax

```
x = lsqr(A, b)
lsqr(A, b, tol)
lsqr(A, b, tol, maxit)
lsqr(A, b, tol, maxit, M)
lsqr(A, b, tol, maxit, M1, M2)
lsqr(A, b, tol, maxit, M1, M2, x0)
lsqr(afun, b, tol, maxit, m1fun, m2fun, x0, p1, p2, ...)
[x, flag] = lsqr(A, b, ...)
[x, flag, relres] = lsqr(A, b, ...)
[x, flag, relres, iter] = lsqr(A, b, ...)
[x, flag, relres, iter, resvec] = lsqr(A, b, ...)
```

Description

`x = lsqr(A, b)` attempts to solve the system of linear equations $A^*x=b$ for x if A is consistent, otherwise it attempts to solve the least squares solution x that minimizes $\text{norm}(b - A^*x)$. The m -by- n coefficient matrix A need not be square but the column vector b must have length m . A can be a function `afun` such that `afun(x)` returns A^*x and `afun(x, 'transp')` returns $A' *x$.

If `lsqr` converges, a message to that effect is displayed. If `lsqr` fails to converge after the maximum number of iterations or halts for any reason, a warning message is printed displaying the relative residual $\text{norm}(b - A^*x) / \text{norm}(b)$ and the iteration number at which the method stopped or failed.

`lsqr(A, b, tol)` specifies the tolerance of the method. If `tol` is `[]`, then `lsqr` uses the default, `1e-6`.

`lsqr(A, b, tol, maxit)` specifies the maximum number of iterations. If `maxit` is `[]`, then `lsqr` uses the default, `min([m, n, 20])`.

`lsqr(A, b, tol, maxit, M1)` and `lsqr(A, b, tol, maxit, M1, M2)` use n -by- n preconditioner M or $M = M1 * M2$ and effectively solve the system $A^*inv(M)^*y = b$ for y , where $x = M^*y$. If M is `[]` then `lsqr` applies no preconditioner. M can be a function `mfun` such that `mfun(x)` returns $M*x$ and `mfun(x, 'transp')` returns $M' \x$.

`lsqr(A, b, tol, maxit, M1, M2, x0)` specifies the n -by-1 initial guess. If `x0` is `[]`, then `lsqr` uses the default, an all zero vector.

lqr

`lqr(afun, b, tol, maxit, m1fun, m2fun, x0, p1, p2, ...)` passes parameters `p1, p2, ...` to functions `afun(x, p1, p2, ...)` and `afun(x, p1, p2, ..., 'transp')` and similarly to the preconditioner functions `m1fun` and `m2fun`.

`[x, flag] = lqr(A, b, tol, maxit, M1, M2, x0)` also returns a convergence flag.

Flag	Convergence
0	<code>lqr</code> converged to the desired tolerance <code>tol</code> within <code>maxit</code> iterations.
1	<code>lqr</code> iterated <code>maxit</code> times but did not converge.
2	Preconditioner <code>M</code> was ill-conditioned.
3	<code>lqr</code> stagnated. (Two consecutive iterates were the same.)
4	One of the scalar quantities calculated during <code>lqr</code> became too small or too large to continue computing.

Whenever `flag` is not 0, the solution `x` returned is that with minimal norm residual computed over all the iterations. No messages are displayed if the `flag` output is specified.

`[x, flag, relres] = lqr(A, b, tol, maxit, M1, M2, x0)` also returns an estimate of the relative residual `norm(b - A*x) / norm(b)`. If `flag` is 0, `relres <= tol`.

`[x, flag, relres, iter] = lqr(A, b, tol, maxit, M1, M2, x0)` also returns the iteration number at which `x` was computed, where `0 <= iter <= maxit`.

`[x, flag, relres, iter, resvec] = lqr(A, b, tol, maxit, M1, M2, x0)` also returns a vector of the residual norm estimates at each iteration, including `norm(b - A*x0)`.

Examples

```
n = 100;
on = ones(n, 1);
A = spdiags([-2*on 4*on -on], -1:1, n, n);
b = sum(A, 2);
```

```

tol = 1e-8;
maxit = 15;
M1 = spdiags([on/(-2) on], -1:0, n, n);
M2 = spdiags([4*on -on], 0:1, n, n);

x = lsqr(A, b, tol, maxit, M1, M2, []);
lsqr converged at iteration 12 to a solution with relative
residual 3.5e-009

```

Alternatively, use this matrix-vector product function

```

function y = afun(x, n, transp_flag)
if (nargin > 2) & strcmp(transp_flag, 'transp')
    y = 4 * x;
    y(1:n-1) = y(1:n-1) - 2 * x(2:n);
    y(2:n) = y(2:n) - x(1:n-1);
else
    y = 4 * x;
    y(2:n) = y(2:n) - 2 * x(1:n-1);
    y(1:n-1) = y(1:n-1) - x(2:n);
end

```

as input to lsqr.

```
x1 = lsqr(@afun, b, tol, maxit, M1, M2, [], n);
```

See Also

`bicg`, `bicgstab`, `cgs`, `gmres`, `minres`, `pcg`, `qmr`, `symmlq`
`@` (function handle)

References

- [1] Barrett, R., M. Berry, T. F. Chan, et al., *Templates for the Solution of Linear Systems: Building Blocks for Iterative Methods*, SIAM, Philadelphia, 1994.
- [2] Paige, C. C. and M. A. Saunders, "LSQR: An Algorithm for Sparse Linear Equations And Sparse Least Squares," *ACM Trans. Math. Soft.*, Vol.8, 1982, pp. 43-71.

Purpose	LU matrix factorization
Syntax	$[L, U] = \text{lu}(X)$ $[L, U, P] = \text{lu}(X)$ $\text{lu}(X)$ $\text{lu}(X, \text{thresh})$
Description	<p>The <code>lu</code> function expresses a matrix X as the product of two essentially triangular matrices, one of them a permutation of a lower triangular matrix and the other an upper triangular matrix. The factorization is often called the <i>LU</i>, or sometimes the <i>LR</i>, factorization.</p> <p>$[L, U] = \text{lu}(X)$ returns an upper triangular matrix in U and a psychologically lower triangular matrix (i.e., a product of lower triangular and permutation matrices) in L, so that $X = L^*U$.</p> <p>$[L, U, P] = \text{lu}(X)$ returns an upper triangular matrix in U, a lower triangular matrix in L, and a permutation matrix in P, so that $L^*U = P^*X$.</p> <p>$\text{lu}(X)$ returns the output from the LAPACK routine DGETRF or ZGETRF.</p> <p>$\text{lu}(X, \text{thresh})$ controls pivoting for sparse matrices, where thresh is a pivot threshold in $[0, 1]$. Pivoting occurs when the diagonal entry in a column has magnitude less than thresh times the magnitude of any sub-diagonal entry in that column. $\text{thresh} = 0$ forces diagonal pivoting. $\text{thresh} = 1$ is the default.</p>
Remarks	<p>Most of the algorithms for computing LU factorization are variants of Gaussian elimination. The factorization is a key step in obtaining the inverse with <code>inv</code> and the determinant with <code>det</code>. It is also the basis for the linear equation solution or matrix division obtained with <code>\</code> and <code>/</code>.</p>
Arguments	<p>X Rectangular matrix to be factored.</p> <p>thresh Pivot threshold for sparse matrices. Valid values are in $[0, 1]$. The default is 1.</p> <p>L A factor of X. Depending on the form of the function, L is either lower triangular, or else the product of a lower triangular matrix with a permutation matrix P.</p>

U An upper triangular matrix that is a factor of X.

P The permutation matrix satisfying the equation $L^*U = P^*X$.

Examples

Start with

$$A = \begin{matrix} & 1 & 2 & 3 \\ 1 & & & \\ 4 & & 5 & 6 \\ 7 & & 8 & 0 \end{matrix}$$

To see the LU factorization, call `lu` with two output arguments:

$$[L, U] = \text{lu}(A)$$

$$L =$$

$$\begin{matrix} 0.1429 & 1.0000 & 0 \\ 0.5714 & 0.5000 & 1.0000 \\ 1.0000 & 0 & 0 \end{matrix}$$

$$U =$$

$$\begin{matrix} 7.0000 & 8.0000 & 0.0000 \\ 0 & 0.8571 & 3.0000 \\ 0 & 0 & 4.5000 \end{matrix}$$

Notice that L is a permutation of a lower triangular matrix that has 1's on the permuted diagonal, and that U is upper triangular. To check that the factorization does its job, compute the product:

$$L^*U$$

which returns the original A. Using three arguments on the left-hand side to get the permutation matrix as well

$$[L, U, P] = \text{lu}(A)$$

returns the same value of U, but L is reordered:

$$L =$$

$$\begin{matrix} 1.0000 & 0 & 0 \end{matrix}$$

$$\begin{array}{ccc} 0.1429 & 1.0000 & 0 \\ 0.5714 & 0.5000 & 1.0000 \end{array}$$

$U =$

$$\begin{array}{ccc} 7.0000 & 8.0000 & 0 \\ 0 & 0.8571 & 3.0000 \\ 0 & 0 & 4.5000 \end{array}$$

$P =$

$$\begin{array}{ccc} 0 & 0 & 1 \\ 1 & 0 & 0 \\ 0 & 1 & 0 \end{array}$$

To verify that L^*U is a permuted version of A , compute L^*U and subtract it from P^*A :

$$P^*A - L^*U$$

The inverse of the example matrix, $X = \text{inv}(A)$, is actually computed from the inverses of the triangular factors:

$$X = \text{inv}(U) * \text{inv}(L)$$

The determinant of the example matrix is

$$d = \det(A)$$

$d =$

27

It is computed from the determinants of the triangular factors:

$$d = \det(L) * \det(U)$$

The solution to $Ax = b$ is obtained with matrix division:

$$x = A \setminus b$$

The solution is actually computed by solving two triangular systems:

$$y = L \setminus b, \quad x = U \setminus y$$

Algorithm lu uses the subroutines DGETRF (real) and ZGETRF (complex) from LAPACK.

See Also cond, det, inv, linsolve, qr, rref

The arithmetic operators \ and /

References [1] Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling, A. McKenney, and D. Sorensen, *LAPACK User's Guide* (http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999.

Purpose	Incomplete LU matrix factorizations
Syntax	$\text{luinc}(X, '0')$ $[L, U] = \text{luinc}(X, '0')$ $[L, U, P] = \text{luinc}(X, '0')$ $\text{luinc}(X, \text{droptol})$ $\text{luinc}(X, \text{options})$ $[L, U] = \text{luinc}(X, \text{options})$ $[L, U] = \text{luinc}(X, \text{droptol})$ $[L, U, P] = \text{luinc}(X, \text{options})$ $[L, U, P] = \text{luinc}(X, \text{droptol})$
Description	<p>luinc produces a unit lower triangular matrix, an upper triangular matrix, and a permutation matrix.</p> <p>$\text{luinc}(X, '0')$ computes the incomplete LU factorization of level 0 of a square sparse matrix. The triangular factors have the same sparsity pattern as the permutation of the original sparse matrix X, and their product agrees with the permuted X over its sparsity pattern. $\text{luinc}(X, '0')$ returns the strict lower triangular part of the factor and the upper triangular factor embedded within the same matrix. The permutation information is lost, but $\text{nnz}(\text{luinc}(X, '0')) = \text{nnz}(X)$, with the possible exception of some zeros due to cancellation.</p> <p>$[L, U] = \text{luinc}(X, '0')$ returns the product of permutation matrices and a unit lower triangular matrix in L and an upper triangular matrix in U. The exact sparsity patterns of L, U, and X are not comparable but the number of nonzeros is maintained with the possible exception of some zeros in L and U due to cancellation:</p> $\text{nnz}(L) + \text{nnz}(U) = \text{nnz}(X) + n, \text{ where } X \text{ is } n \text{- by- } n.$ <p>The product L^*U agrees with X over its sparsity pattern. $(L^*U) . * \text{spones}(X) - X$ has entries of the order of eps.</p> <p>$[L, U, P] = \text{luinc}(X, '0')$ returns a unit lower triangular matrix in L, an upper triangular matrix in U and a permutation matrix in P. L has the same sparsity pattern as the lower triangle of the permuted X</p> $\text{spones}(L) = \text{spones}(\text{tril}(P^*X))$

with the possible exceptions of 1s on the diagonal of L where P^*X may be zero, and zeros in L due to cancellation where P^*X may be nonzero. U has the same sparsity pattern as the upper triangle of P^*X

$$\text{spones}(U) = \text{spones}(\text{triu}(P^*X))$$

with the possible exceptions of zeros in U due to cancellation where P^*X may be nonzero. The product L^*U agrees within rounding error with the permuted matrix P^*X over its sparsity pattern. $(L^*U) . * \text{spones}(P^*X) - P^*X$ has entries of the order of eps.

`lui nc(X, droptol)` computes the incomplete LU factorization of any sparse matrix using a drop tolerance. `droptol` must be a non-negative scalar.

`lui nc(X, droptol)` produces an approximation to the complete LU factors returned by `lu(X)`. For increasingly smaller values of the drop tolerance, this approximation improves, until the drop tolerance is 0, at which time the complete LU factorization is produced, as in `lu(X)`.

As each column j of the triangular incomplete factors is being computed, the entries smaller in magnitude than the local drop tolerance (the product of the drop tolerance and the norm of the corresponding column of X)

$$\text{droptol} * \text{norm}(X(:, j))$$

are dropped from the appropriate factor.

The only exceptions to this dropping rule are the diagonal entries of the upper triangular factor, which are preserved to avoid a singular factor.

`lui nc(X, options)` specifies a structure with up to four fields that may be used in any combination: `droptol`, `mi lu`, `udi ag`, `thresh`. Additional fields of `options` are ignored.

`droptol` is the drop tolerance of the incomplete factorization.

If `mi lu` is 1, `lui nc` produces the modified incomplete LU factorization that subtracts the dropped elements in any column from the diagonal element of the upper triangular factor. The default value is 0.

If `udi ag` is 1, any zeros on the diagonal of the upper triangular factor are replaced by the local drop tolerance. The default is 0.

`thresh` is the pivot threshold between 0 (forces diagonal pivoting) and 1, the default, which always chooses the maximum magnitude entry in the column to be the pivot. `thresh` is described in greater detail in [l u i n c](#).

`l u i n c(X, options)` is the same as `l u i n c(X, droptol)` if `options` has `droptol` as its only field.

`[L, U] = l u i n c(X, options)` returns a permutation of a unit lower triangular matrix in `L` and an upper triangular matrix in `U`. The product `L*U` is an approximation to `X`. `l u i n c(X, options)` returns the strict lower triangular part of the factor and the upper triangular factor embedded within the same matrix. The permutation information is lost.

`[L, U] = l u i n c(X, options)` is the same as `l u i n c(X, droptol)` if `options` has `droptol` as its only field.

`[L, U, P] = l u i n c(X, options)` returns a unit lower triangular matrix in `L`, an upper triangular matrix in `U`, and a permutation matrix in `P`. The nonzero entries of `U` satisfy

$$\text{abs}(U(i, j)) \geq \text{droptol} * \text{norm}(X(:, j)),$$

with the possible exception of the diagonal entries which were retained despite not satisfying the criterion. The entries of `L` were tested against the local drop tolerance before being scaled by the pivot, so for nonzeros in `L`

$$\text{abs}(L(i, j)) \geq \text{droptol} * \text{norm}(X(:, j)) / U(j, j).$$

The product `L*U` is an approximation to the permuted `P*X`.

`[L, U, P] = l u i n c(X, options)` is the same as `[L, U, P] = l u i n c(X, droptol)` if `options` has `droptol` as its only field.


Remarks

These incomplete factorizations may be useful as preconditioners for solving large sparse systems of linear equations. The lower triangular factors all have 1s along the main diagonal but a single 0 on the diagonal of the upper triangular factor makes it singular. The incomplete factorization with a drop tolerance prints a warning message if the upper triangular factor has zeros on the diagonal. Similarly, using the `udi ag` option to replace a zero diagonal only gets rid of the symptoms of the problem but does not solve it. The preconditioner may not be singular, but it probably is not useful and a warning message is printed.

Limitations `lui nc(X, '0')` works on square matrices only.

Examples Start with a sparse matrix and compute its LU factorization.

```
load west0479;
S = west0479;
LU = lu(S);
```




Compute the incomplete LU factorization of level 0.

```
[L, U, P] = lui nc(S, '0');
D = (L*U) . *spones(P*S) - P*S;
```

`spones(U)` and `spones(triu(P*S))` are identical.

`spones(L)` and `spones(tril(P*S))` disagree at 73 places on the diagonal, where L is 1 and `P*S` is 0, and also at position (206,113), where L is 0 due to cancellation, and `P*S` is -1. D has entries of the order of eps.






$[IL0, IU0, IP0] = \text{luinc}(S, 0);$
 $[IL1, IU1, IP1] = \text{luinc}(S, 1e-10);$

.

.

.

A drop tolerance of 0 produces the complete LU factorization. Increasing the drop tolerance increases the sparsity of the factors (decreases the number of nonzeros) but also increases the error in the factors, as seen in the plot of drop tolerance versus $\text{norm}(L^*U - P^*S, 1) / \text{norm}(S, 1)$ in the second figure below.



Algorithm	<code>luinc(X, '0')</code> is based on the “KJI” variant of the LU factorization with partial pivoting. Updates are made only to positions which are nonzero in X.
	<code>luinc(X, droptol)</code> and <code>luinc(X, options)</code> are based on the column-oriented <code>lu</code> for sparse matrices.
See Also	<code>lu</code> , <code>cholinc</code> , <code>bicg</code>
References	[1] Saad, Yousef, <i>Iterative Methods for Sparse Linear Systems</i> , PWS Publishing Company, 1996, Chapter 10 - Preconditioning Techniques.

Purpose	Magic square
Syntax	$M = \text{magic}(n)$
Description	$M = \text{magic}(n)$ returns an n -by- n matrix constructed from the integers 1 through n^2 with equal row and column sums. The order n must be a scalar greater than or equal to 3.

Remarks A magic square, scaled by its magic sum, is doubly stochastic.

Examples The magic square of order 3 is

$$M = \text{magic}(3)$$

$$M =$$

$$\begin{matrix} 8 & 1 & 6 \\ 3 & 5 & 7 \\ 4 & 9 & 2 \end{matrix}$$

This is called a magic square because the sum of the elements in each column is the same.

$$\text{sum}(M) =$$

$$15 \quad 15 \quad 15$$

And the sum of the elements in each row, obtained by transposing twice, is the same.

$$\text{sum}(M')' =$$

$$\begin{matrix} 15 \\ 15 \\ 15 \end{matrix}$$

This is also a special magic square because the diagonal elements have the same sum.

$$\text{sum}(\text{diag}(M)) =$$

$$15$$

magic

The value of the characteristic sum for a magic square of order n is

`sum(1:n^2)/n`

which, when $n = 3$, is 15.

Algorithm

There are three different algorithms:

- n odd
- n even but not divisible by four
- n divisible by four

To make this apparent, type


```
for n = 3:20
    A = magic(n);
    r(n) = rank(A);
end
```

For n odd, the rank of the magic square is n . For n divisible by 4, the rank is 3.
For n even but not divisible by 4, the rank is $n/2 + 2$.

```
[ (3:20)', r(3:20)' ]
```

```
ans =
    3      3
    4      3
    5      5
    6      5
    7      7
    8      3
    9      9
   10      7
   11     11
   12      3
   13     13
   14      9
   15     15
   16      3
   17     17
   18     11
   19     19
   20      3
```

Plotting A for $n = 18, 19, 20$ shows the characteristic plot for each category.

**Limitations**

If you supply n less than 3, `magic` returns either a nonmagic square, or else the degenerate magic squares 1 and [].

See Also

`ones`, `rand`

mat2str

Purpose	Convert a matrix into a string
Syntax	<pre>str = mat2str(A) str = mat2str(A, n)</pre>
Description	<p><code>str = mat2str(A)</code> converts matrix A into a string, suitable for input to the <code>eval</code> function, using full precision.</p> <p><code>str = mat2str(A, n)</code> converts matrix A using n digits of precision.</p>
Limitations	The <code>mat2str</code> function is intended to operate on scalar, vector, or rectangular array inputs only. An error will result if A is a multidimensional array.
Examples	<p>Consider the matrix:</p> <pre>A = 1 2 3 4</pre> <p>The statement</p> <pre>b = mat2str(A)</pre> <p>produces:</p> <pre>b = [1 2 ; 3 4]</pre> <p>where b is a string of 11 characters, including the square brackets, spaces, and a semicolon.</p> <p><code>eval (mat2str(A))</code> reproduces A.</p>
See Also	<code>int2str</code> , <code>sprintf</code> , <code>str2num</code>

Purpose	Controls the reflectance properties of surfaces and patches
Syntax	<pre>material shiny material dull material metal material ([ka kd ks]) material ([ka kd ks n]) material ([ka kd ks n sc]) material default</pre>
Description	<p><code>material</code> sets the lighting characteristics of surface and patch objects.</p> <p><code>material shiny</code> sets the reflectance properties so that the object has a high specular reflectance relative the diffuse and ambient light and the color of the specular light depends only on the color of the light source.</p> <p><code>material dull</code> sets the reflectance properties so that the object reflects more diffuse light, has no specular highlights, but the color of the reflected light depends only on the light source.</p> <p><code>material metal</code> sets the reflectance properties so that the object has a very high specular reflectance, very low ambient and diffuse reflectance, and the color of the reflected light depends on both the color of the light source and the color of the object.</p> <p><code>material ([ka kd ks])</code> sets the ambient/diffuse/specular strength of the objects.</p> <p><code>material ([ka kd ks n])</code> sets the ambient/diffuse/specular strength and specular exponent of the objects.</p> <p><code>material ([ka kd ks n sc])</code> sets the ambient/diffuse/specular strength, specular exponent, and specular color reflectance of the objects.</p> <p><code>material default</code> sets the ambient/diffuse/specular strength, specular exponent, and specular color reflectance of the objects to their defaults.</p>
Remarks	The <code>material</code> command sets the <code>AmbientStrength</code> , <code>DiffuseStrength</code> , <code>SpecularStrength</code> , <code>SpecularExponent</code> , and <code>SpecularColorReflectance</code>

material

properties of all surface and patch objects in the axes. There must be visible light objects in the axes for lighting to be enabled. Look at the `material.m` M-file to see the actual values set (enter the command: type `material`).

See Also

`light`, `lighting`, `patch`, `surface`

Purpose	Start MATLAB (UNIX systems only)
Syntax	<code>matlab [-h -help] [-n] [-arch -ext -arch/ext] [-c licensefile] [-display Xdisplay -nodisplay] [-nosplash] [-mwvisual visual_id] [-debug] [-nodesktop -nojvm] [-runtime] [-check_malloc] [-r MATLAB_command] [-Ddebugger [options]]</code>
Description	<p><code>matlab</code> is a Bourne shell script that starts the MATLAB executable. (In this document, <code>matlab</code> refers to this script; MATLAB refers to the application program). Before actually initiating the execution of MATLAB, this script configures the runtime environment by:</p> <ul style="list-style-type: none"> • Determining the MATLAB root directory • Determining the host machine architecture • Processing any command line options • Reading the MATLAB startup file, <code>.matlab5rc.sh</code> • Setting MATLAB environment variables <p>There are two ways in which you can control the way the <code>matlab</code> script works:</p> <ul style="list-style-type: none"> • By specifying command-line options • By assigning values in the MATLAB startup file <code>.matlab5rc.sh</code> <p>The <code>.matlab5rc.sh</code> shell script contains definitions for a number of variables that the <code>matlab</code> script uses. These variables are defined within the <code>matlab</code> script, but can be redefined in <code>.matlab6rc.sh</code>. When invoked, <code>matlab</code> looks for the first occurrence of <code>.matlab5rc.sh</code> in the current directory, in the home directory (<code>\$HOME</code>), and in the <code>\$MATLAB/bin</code> directory, where the template version of <code>.matlab6rc.sh</code> is located.</p> <p>You can edit the template file to redefine information used by the <code>matlab</code> script. If you do not want your changes applied system wide, copy the edited version of the script to your current or home directory. Ensure that you edit the section that applies to your machine architecture.</p>

The following table lists the variables defined in the `.matlab6rc.sh` file. See the comments in the `.matlab6rc.sh` file for more information about these variables.

Variable	Definition and Standard Assignment Behavior
ARCH	<p>The machine architecture.</p> <p>The value ARCH passed in with the <code>-arch</code> or <code>-arch/ext</code> argument to the script is tried first, then the value of the environment variable <code>MATLAB_ARCH</code> is tried next, and finally it is computed. The first one that gives a valid architecture is used.</p>
AUTOMOUNT_MAP	<p>Path prefix map for automounting.</p> <p>The value set in <code>.matlab6rc.sh</code> (initially by the installer) is used unless the value differs from that determined by the script. In which case the value in the environment is used.</p>
DISPLAY	<p>The hostname of the X Window display MATLAB uses for output.</p> <p>The value of Xdisplay passed with the <code>-display</code> argument to the script is used otherwise the value in the environment. DISPLAY is ignored by MATLAB if the <code>-nodisplay</code> argument is passed.</p>

Variable	Definition and Standard Assignment Behavior
LD_LIBRARY_PATH	<p>Final Load library path. The name LD_LIBRARY_PATH is platform dependent.</p> <p>The final value is normally a colon separated list of four sublists each of which could be empty. The first sublist is defined in .matlabrc.sh as LDPATH_PREFIX. The second sublist is computed in the script and includes directories inside the MATLAB root directory and relevant Java directories. The third sublist contains any nonempty value of LD_LIBRARY_PATH from the environment possibly augmented in .matlabrc.sh. The final sublist is defined in .matlabrc.sh as LDPATH_SUFFIX.</p>
LM_LICENSE_FILE	<p>The FLEXlm license variable.</p> <p>The value license file passed with the -c argument to the script is used, otherwise the value set in .matlabrc.sh. In general, the final value is a colon separated list of license files and/or port@host entries. The shipping .matlabrc.sh file starts out the value by prepending LM_LICENSE_FILE in the environment to a default license file.</p> <p>Later in the MATLAB script if the -c option is not used, the \$MATLAB/etc directory is searched for the files that start with license.dat.DEMO. These files are assumed to contain demo licenses and are added automatically to end of the current list.</p>

matlab

Variable	Definition and Standard Assignment Behavior
MATLAB	<p>The MATLAB root directory.</p> <p>The default computed by the script is used unless MATLABdefaul t is reset in . matl ab6rc. sh.</p> <p>Currently MATLABdefaul t is not reset in the shipping . matl ab6rc. sh.</p>
MATLAB_DEBUG	<p>Normally set to the name of debugger.</p> <p>The - Ddebugger argument passed in to the script sets this variable. Otherwise, a nonempty value in the environment is used.</p>
MATLAB_JAVA	<p>The path to the root of the Java Runtime Environment.</p> <p>The default set in the script is used unless MATLAB_JAVA is already set. Any nonempty value from . matl ab6rc. sh is used first then any nonempty value from the environment.</p> <p>Currently there is no value set in the shipping . matl ab6rc. sh so that environment alone is used.</p>
MATLAB_MEM_MGR	<p>Turns on MATLAB memory integrity checking.</p> <p>The - check_mal l oc argument passed in to the script sets this variable to ' debug' . Otherwise, a nonempty value set in . matl ab6rc. sh is used, or a nonempty value in the environment is used. If a nonempty value is not found, the variable is not exported to the environment.</p>

Variable	Definition and Standard Assignment Behavior
MATLABPATH	<p>The MATLAB search path.</p> <p>The final value is a colon separated list with the MATLABPATH from the environment prepended to a list of computed defaults.</p>
SHELL	<p>The shell to use when "!" or unix command is issued in MATLAB.</p> <p>This is taken from the environment unless SHELL is reset in .matlabrc.sh. Currently SHELL is not reset in the shipping .matlabrc.sh. If SHELL is empty or not defined then MATLAB uses /bin/sh internally.</p>
TOOLBOX	<p>Path of the toolbox directory.</p> <p>A nonempty value in the environment is used first. Otherwise, \$MATLAB/tool box, computed by the script is used, unless TOOLBOX is reset in .matlabrc.sh. Currently TOOLBOX is not reset in the shipping .matlabrc.sh.</p>

Variable	Definition and Standard Assignment Behavior
XAPPLRESDIR	The X application resource directory. A nonempty value in the environment is used first unless XAPPLRESDIR is reset in .matlabrc.sh. Otherwise, \$MATLAB/X11/app-defaults, computed by the script is used.
XKEYSYMDB	The X keysym database file. A nonempty value in the environment is used first unless XKEYSYMDB is reset in .matlabrc.sh. Otherwise, \$MATLAB/X11/app-defaults/XKeysymDB, computed by the script is used. The matlab script determines the path of the MATLAB root directory as one level up the directory tree from the location of the script. Information in the AUTOMOUNT_MAP variable is used to fix the path so that it is correct to force a mount. This may involve deleting part of the pathname from the front of the MATLAB root path. The MATLAB variable is then used to locate all files within the MATLAB directory tree.

The matlab script determines the path of the MATLAB root directory by looking up the directory tree from the \$MATLAB/bin directory (where the matlab script is located). The MATLAB variable is then used to locate all files within the MATLAB directory tree.

You can change the definition of MATLAB if, for example, you want to run a different version of MATLAB or if, for some reason, the path determined by the matlab script is not correct. (This can happen when certain types of automounting schemes are used by your system.)

AUTOMOUNT_MAP is used to modify the MATLAB root directory path. Whatever pathname that is assigned to AUTOMOUNT_MAP is deleted from the front of the MATLAB root path. (It is unlikely that you will need to use this option.)

Options

The following table describes matlab command line options.

Option	Function
-h -help	Display matlab command usage. MATLAB is not started when you specify this option.
-n	Display all the final values of the environment variables and arguments passed to the MATLAB executable as well as other diagnostic information. MATLAB is not started when you specify this option.
-arch	Run MATLAB assuming architecture arch.
-ext	Run the version of MATLAB with extension ext, if it exists.
-arch/ext	Run the version of MATLAB with extension ext, if it exists, assuming arch identifies the architecture.
-licensefile	Set the value of the LM_LICENSE_FILE environment variable to licensefile. licensefile can be a colon separated list of files or port@host entries, or both. For more information, see LM_LICENSE_FILE in the variable table.
-check_malloc	Set the value of the MATLAB_MEM_MGR environment variable to 'debug'. This turns on MATLAB memory integrity checking. For more information, see MATLAB_MEM_MGR in the variable table.

matlab

Option	Function
- di spl ay Xserver	Define the X display used for MATLAB output, Xserver has the form host name: di spl ay. For example, <code>matlab -di spl ay falstaff:0</code> causes MATLAB output to be displayed on the host named falstaff. This setting supersedes the value of the DI SPLAY environment variable and the value of the DISPLAY variable defined in <code>.matlab5rc.sh</code> .
- debug	Provide debugging information, especially for X-based problems. Note that you should use this option only in conjunction with a Technical Support Representative from The MathWorks, Inc.
- nospl ash	Do not display the splash screen during startup.
- nodesktop	Do not start the MATLAB desktop. Use the current window for commands. The Java Virtual Machine (JVM) will be started.
- noj vm	Shut off all Java support by not starting the Java Virtual Machine (JVM). In particular, the MATLAB desktop will not be started.

Option	Function
<code>-mwvisual visual_id</code>	The default X visual to use for figure windows.
<code>-Ddebugger [options]</code>	Start MATLAB with the specified debugger (e.g. dbx, gdb, dde, xdb, cvd). A full path can be specified for debugger. The options cover ONLY those that go after the executable to be debugged in the syntax of the actual debug command and for most debuggers this is very limited. To customize your debugging session use a startup file. See your debugger documentation for details. The MATLAB_DEBUG environment variable is set to the filename part of the debugger argument. For more information, see MATLAB_DEBUG in the variable table above.

See Also

[mex](#)

matlabrc

Purpose	MATLAB startup M-file for single user systems or system administrators
Description	At startup time, MATLAB automatically executes the master M-file <code>matlabrc.m</code> and, if it exists, <code>startup.m</code> . On multiuser or networked systems, <code>matlabrc.m</code> is reserved for use by the system manager. The file <code>matlabrc.m</code> invokes the file <code>startup.m</code> if it exists on MATLAB's search path. As an individual user, you can create a startup file in your own MATLAB directory. Use the startup file to define physical constants, engineering conversion factors, graphics defaults, or anything else you want predefined in your workspace.
Algorithm	Only <code>matlabrc</code> is actually invoked by MATLAB at startup. However, <code>matlabrc.m</code> contains the statements <pre>if exist('startup') == 2 startup end</pre> that invoke <code>startup.m</code> . Extend this process to create additional startup M-files, if required.
Remarks	You can also start MATLAB using options you define at the Command Window prompt or in your Windows shortcut for MATLAB.
Examples	Example – Turning Off the Figure Window Toolbar If you do not want the toolbar to appear in the figure window, remove the comment marks from the following line in the <code>matlabrc.m</code> file, or create a similar line in your own <code>startup.m</code> file. <code>% set(0, 'defaultfiguretoolbar', 'none')</code>
See Also	<code>quit</code> , <code>startup</code> “Startup Options” in “Starting and Quitting MATLAB”

Purpose	Return root directory of MATLAB installation
Syntax	<code>matlabroot</code> <code>rd = matlabroot</code>
Description	<code>matlabroot</code> returns the name of the directory in which the MATLAB software is installed. <code>rd = matlabroot</code> returns the name of the directory in which the MATLAB software is installed and assigns it to <code>rd</code> .
Examples	<code>fullfile(matlabroot, 'toolbox', 'matlab', 'general', '')</code> produces a full path to the <code>toolbox/matlab/general</code> directory that is correct for the platform it is executed on.

max

Purpose	Maximum elements of an array
Syntax	$C = \text{max}(A)$ $C = \text{max}(A, B)$ $C = \text{max}(A, [], \text{dim})$ $[C, I] = \text{max}(\dots)$
Description	$C = \text{max}(A)$ returns the largest elements along different dimensions of an array. If A is a vector, $\text{max}(A)$ returns the largest element in A. If A is a matrix, $\text{max}(A)$ treats the columns of A as vectors, returning a row vector containing the maximum element from each column. If A is a multidimensional array, $\text{max}(A)$ treats the values along the first non-singleton dimension as vectors, returning the maximum value of each vector. $C = \text{max}(A, B)$ returns an array the same size as A and B with the largest elements taken from A or B. $C = \text{max}(A, [], \text{dim})$ returns the largest elements along the dimension of A specified by scalar dim. For example, $\text{max}(A, [], 1)$ produces the maximum values along the first dimension (the rows) of A. $[C, I] = \text{max}(\dots)$ finds the indices of the maximum values of A, and returns them in output vector I. If there are several identical maximum values, the index of the first one found is returned.
Remarks	For complex input A, max returns the complex number with the largest modulus, computed with $\text{max}(\text{abs}(A))$. The max function ignores NaNs.
See Also	i snan, mean, medi an, mi n, sort

Purpose	Average or mean value of arrays
Syntax	$M = \text{mean}(A)$ $M = \text{mean}(A, \text{dim})$
Description	$M = \text{mean}(A)$ returns the mean values of the elements along different dimensions of an array. If A is a vector, $\text{mean}(A)$ returns the mean value of A. If A is a matrix, $\text{mean}(A)$ treats the columns of A as vectors, returning a row vector of mean values. If A is a multidimensional array, $\text{mean}(A)$ treats the values along the first non-singleton dimension as vectors, returning an array of mean values. $M = \text{mean}(A, \text{dim})$ returns the mean values for elements along the dimension of A specified by scalar dim.
Examples	<pre>A = [1 2 4 4; 3 4 6 6; 5 6 8 8; 5 6 8 8]; mean(A) ans = 3.5000 4.5000 6.5000 6.5000 mean(A, 2) ans = 2.7500 4.7500 6.7500 6.7500</pre>
See Also	corrcoef , cov , max , median , min , std

median

Purpose	Median value of arrays
Syntax	$M = \text{median}(A)$ $M = \text{median}(A, dim)$
Description	$M = \text{median}(A)$ returns the median values of the elements along different dimensions of an array. If A is a vector, $\text{median}(A)$ returns the median value of A . If A is a matrix, $\text{median}(A)$ treats the columns of A as vectors, returning a row vector of median values. If A is a multidimensional array, $\text{median}(A)$ treats the values along the first nonsingleton dimension as vectors, returning an array of median values. $M = \text{median}(A, dim)$ returns the median values for elements along the dimension of A specified by scalar dim .
Examples	<pre>A = [1 2 4 4; 3 4 6 6; 5 6 8 8; 5 6 8 8]; median(A) ans = 4 5 7 7 median(A, 2) ans = 3 5 7 7</pre>
See Also	corrcoef , cov , max , mean , min , std

Purpose	Help for memory limitations
Description	If the out of memory error message is encountered, there is no more room in memory for new variables. You must free up some space before you may proceed. One way to free up space is to use the clear function to remove some of the variables residing in memory. Another is to issue the pack command to compress data in memory. This opens up larger contiguous blocks of memory for you to use. Here are some additional system specific tips: Windows: Increase virtual memory by using System in the Control Panel. UNIX: Ask your system manager to increase your swap space.
See Also	clear, pack

menu

Purpose	Generate a menu of choices for user input
Syntax	<code>k = menu('mttitle', 'opt1', 'opt2', ..., 'optn')</code>
Description	<code>k = menu('mttitle', 'opt1', 'opt2', ..., 'optn')</code> displays the menu whose title is in the string variable <code>'mttitle'</code> and whose choices are string variables <code>'opt1'</code> , <code>'opt2'</code> , and so on. <code>menu</code> returns the value you entered.
Remarks	To call <code>menu</code> from another ui-object, set that object's <code>Interruptible</code> property to <code>'yes'</code> . For more information, see the <i>MATLAB Graphics Guide</i> .
Examples	<code>k = menu('Choose a color', 'Red', 'Green', 'Blue')</code> displays



After input is accepted, use `k` to control the color of a graph.

```
color = ['r', 'g', 'b']
plot(t, s, color(k))
```

See Also `input`, `uicontrol`

Purpose	Mesh plots
Syntax	<code>mesh(X, Y, Z)</code> <code>mesh(Z)</code> <code>mesh(..., C)</code> <code>mesh(..., '<i>PropertyName</i>', <i>PropertyValue</i>, ...)</code> <code>meshc(...)</code> <code>meshz(...)</code> <code>h = mesh(...)</code> <code>h = meshc(...)</code> <code>h = meshz(...)</code>
Description	<p><code>mesh</code>, <code>meshc</code>, and <code>meshz</code> create wireframe parametric surfaces specified by <code>X</code>, <code>Y</code>, and <code>Z</code>, with color specified by <code>C</code>.</p> <p><code>mesh(X, Y, Z)</code> draws a wireframe mesh with color determined by <code>Z</code>, so color is proportional to surface height. If <code>X</code> and <code>Y</code> are vectors, <code>length(X) = n</code> and <code>length(Y) = m</code>, where <code>[m, n] = size(Z)</code>. In this case, $(X(j), Y(i), Z(i, j))$ are the intersections of the wireframe grid lines; <code>X</code> and <code>Y</code> correspond to the columns and rows of <code>Z</code>, respectively. If <code>X</code> and <code>Y</code> are matrices, $(X(i, j), Y(i, j), Z(i, j))$ are the intersections of the wireframe grid lines.</p> <p><code>mesh(Z)</code> draws a wireframe mesh using <code>X = 1:n</code> and <code>Y = 1:m</code>, where <code>[m, n] = size(Z)</code>. The height, <code>Z</code>, is a single-valued function defined over a rectangular grid. Color is proportional to surface height.</p> <p><code>mesh(..., C)</code> draws a wireframe mesh with color determined by matrix <code>C</code>. MATLAB performs a linear transformation on the data in <code>C</code> to obtain colors from the current colormap. If <code>X</code>, <code>Y</code>, and <code>Z</code> are matrices, they must be the same size as <code>C</code>.</p> <p><code>mesh(..., '<i>PropertyName</i>', <i>PropertyValue</i>, ...)</code> sets the value of the specified surface property. Multiple property values can be set with a single statement.</p> <p><code>meshc(...)</code> draws a contour plot beneath the mesh.</p> <p><code>meshz(...)</code> draws a curtain plot (i.e., a reference plane) around the mesh.</p>

mesh, meshc, meshz

`h = mesh(...)`, `h = meshc(...)`, and `h = meshz(...)` return a handle to a surface graphics object.


Remarks

A mesh is drawn as a surface graphics object with the viewpoint specified by `view(3)`. The face color is the same as the background color (to simulate a wireframe with hidden-surface elimination), or none when drawing a standard see-through wireframe. The current colormap determines the edge color. The `hidden` command controls the simulation of hidden-surface elimination in the mesh, and the `shading` command controls the shading model.

Examples


Produce a combination mesh and contour plot of the peaks surface:

```
[X, Y] = meshgrid(-3: .125: 3);  
Z = peaks(X, Y);  
meshc(X, Y, Z);  
axis([-3 3 -3 3 -10 5])
```



Generate the curtain plot for the peaks function:

```
[X, Y] = meshgrid(-3: .125: 3);  
Z = peaks(X, Y);  
meshz(X, Y, Z)
```

meshz(X, Y, Z)**Algorithm**

The range of X, Y, and Z, or the current setting of the axes XLi mMode, YLi mMode, and ZLi mMode properties determine the axis limits. axi s sets these properties.

The range of C, or the current setting of the axes CLi m and CLi mMode properties (also set by the caxis s function), determine the color scaling. The scaled color values are used as indices into the current colormap.

The mesh rendering functions produce color values by mapping the z data values (or an explicit color array) onto the current colormap. MATLAB's default behavior computes the color limits automatically using the minimum and maximum data values (also set using caxis s auto). The minimum data value maps to the first color value in the colormap and the maximum data value maps to the last color value in the colormap. MATLAB performs a linear transformation on the intermediate values to map them to the current colormap.

meshc calls mesh, turns hold on, and then calls contour and positions the contour on the x-y plane. For additional control over the appearance of the

mesh, meshc, meshz

contours, you can issue these commands directly. You can combine other types of graphs in this manner, for example `surf` and `pcol` or `plots`.

`meshc` assumes that `X` and `Y` are monotonically increasing. If `X` or `Y` is irregularly spaced, `contour3` calculates contours using a regularly spaced contour grid, then transforms the data to `X` or `Y`.

See Also

`contour`, `hidden`, `meshgrid`, `surface`, `surf`, `surfc`, `surfl`, `waterfall`

The functions `axis`, `caxis`, `colormap`, `hold`, `shading`, and `view` all set graphics object properties that affect `mesh`, `meshc`, and `meshz`.

For a discussion of parametric surfaces plots, refer to `surf`.

Purpose Generate X and Y matrices for three-dimensional plots

Syntax

- [X, Y] = meshgrid(x, y)
- [X, Y] = meshgrid(x)
- [X, Y, Z] = meshgrid(x, y, z)

Description [X, Y] = meshgrid(x, y) transforms the domain specified by vectors x and y into arrays X and Y, which can be used to evaluate functions of two variables and three-dimensional mesh/surface plots. The rows of the output array X are copies of the vector x; columns of the output array Y are copies of the vector y.

[X, Y] = meshgrid(x) is the same as [X, Y] = meshgrid(x, x).

[X, Y, Z] = meshgrid(x, y, z) produces three-dimensional arrays used to evaluate functions of three variables and three-dimensional volumetric plots.

Remarks The meshgrid function is similar to ndgrid except that the order of the first two input and output arguments is switched. That is, the statement

[X, Y, Z] = meshgrid(x, y, z)

produces the same result as

[Y, X, Z] = ndgrid(y, x, z)

Because of this, meshgrid is better suited to problems in two- or three-dimensional Cartesian space, while ndgrid is better suited to multidimensional problems that aren't spatially based.

meshgrid is limited to two- or three-dimensional Cartesian space.

Examples [X, Y] = meshgrid(1:3, 10:14)

X =

1	2	3
1	2	3
1	2	3
1	2	3
1	2	3

meshgrid

Y =

10	10	10
11	11	11
12	12	12
13	13	13
14	14	14

See Also

[griddata](#), [mesh](#), [ndgrid](#), [slice](#), [surf](#)

Purpose	Display method names
Syntax	<pre>n = methods class_name n = methods class_name -full</pre>
Description	<p><code>n = methods(' class_name')</code> returns, in a cell array of strings, the names of all methods for the MATLAB or Java class with the name <code>class_name</code>.</p> <p><code>n = methods(' class_name', '-full')</code> returns, in a cell array of strings, the full description of the methods defined for the class, including inheritance information and, for Java methods, attributes and signatures. For any overloaded method, the returned array includes a description of each of its signatures. If <code>class_name</code> represents a MATLAB class, then inheritance information is returned only if that class has been instantiated.</p>
Examples	<p>To display a full description of all methods on Java object <code>j ava. awt. Di mensi on</code></p> <pre>methods j ava. awt. Di mensi on -full</pre> <p>Methods for class <code>j ava. awt. Di mensi on</code>:</p> <pre>Di mensi on() Di mensi on(j ava. awt. Di mensi on) Di mensi on(int, int) j ava. lang. Cl ass getClass() % Inherited from <code>j ava. lang. Obj ect</code> int hashCode() % Inherited from <code>j ava. lang. Obj ect</code> boolean equals(j ava. lang. Obj ect) j ava. lang. String toString() void notify() % Inherited from <code>j ava. lang. Obj ect</code> void notifyAll() % Inherited from <code>j ava. lang. Obj ect</code> void wait(long) throws <code>j ava. lang. InterruptedException</code> % Inherited from <code>j ava. lang. Obj ect</code> void wait(long, int) throws <code>j ava. lang. InterruptedException</code> % Inherited from <code>j ava. lang. Obj ect</code> void wait() throws <code>j ava. lang. InterruptedException</code> % Inherited from <code>j ava. lang. Obj ect</code> j ava. awt. Di mensi on getSize() void setSize(j ava. awt. Di mensi on) void setSize(int, int)</pre>

methods

See Also

`methodsview, help, what, which`

Purpose	Displays information on all methods implemented by a class.
Syntax	<code>methodsview package_name.class_name</code> <code>methodsview class_name</code>
Description	<code>methodsview package_name.class_name</code> displays information describing the Java class, <code>class_name</code> , that is available from the package of Java classes, <code>package_name</code> . <code>methodsview class_name</code> displays information describing the imported Java or MATLAB class, <code>class_name</code> .
	MATLAB creates a new window in response to the <code>methodsview</code> command. This window displays all of the methods defined in the specified class. For each of these methods, the following additional information is supplied:

- Name of the method
- Method type qualifiers (for example, `abstract` or `synchronized`)
- Data type returned by the method
- Arguments passed to the method
- Possible exceptions thrown
- Parent of the specified class

Examples	The following command lists information on all methods in the <code>java.awt.MenuItem</code> class.
	<code>methodsview java.awt.MenuItem</code>

methodsview

MATLAB displays this information in a new window, as shown below

Methods of class <code>java.awt.MenuItem</code>			
Qualifiers	Return Type	Name	Arguments
		MenuItem	()
		MenuItem	(<code>java.lang.String</code>)
		MenuItem	(<code>java.lang.String,java.awt.MenuShortcut</code>)
synchronized	void	addActionListener	(<code>java.awt.event.ActionListener</code>)
	void	addNotify	()
	void	deleteShortcut	()
synchronized	void	disable	()
	void	dispatchEvent	(<code>java.awt.AWTEvent</code>)
synchronized	void	enable	()
	void	enable	(<code>boolean</code>)
	boolean	equals	(<code>java.lang.Object</code>)
	<code>java.lang.String</code>	getActionCommand	()
	<code>java.lang.Class</code>	getClass	()
	<code>java.awt.Font</code>	getFont	()
	<code>java.lang.String</code>	getLabel	()
	<code>java.lang.String</code>	getName	()
	<code>java.awt.MenuContainer</code>	getParent	()
	<code>java.awt.peer.MenuComponentPeer</code>	getPeer	()
	<code>java.awt.MenuShortcut</code>	getShortcut	()
	int	hashCode	()
	boolean	isEnabled	()
	void	notify	()
	void	notifyAll	()

See Also

`methods`, `import`, `class`, `javaArray`

Purpose	Compile MEX-function from C or Fortran source code
Syntax	<code>mex options filenames</code>
Description	<p><code>mex options filenames</code> compiles a MEX-function from the C or Fortran source code files specified in <code>filenames</code>. All nonsource code <code>filenames</code> passed as arguments are passed to the linker without being compiled.</p> <p>All valid options are shown in the MEX Script Switches table. These options are available on all platforms except where noted.</p> <p>MEX's execution is affected both by command-line options and by an options file. The options file contains all compiler-specific information necessary to create a MEX-function. The default name for this options file, if none is specified with the <code>-f</code> option, is <code>mexopts.bat</code> (Windows) and <code>mexopts.sh</code> (UNIX).</p>

Note The MathWorks provides an option, `setup`, for the `mex` script that lets you set up a default options file on your system.

On UNIX, the options file is written in the Bourne shell script language. The `mex` script searches for the first occurrence of the options file called `mexopts.sh` in the following list:

- The current directory
- `$HOME/matlab`
- `<MATLAB>/bin`

`mex` uses the first occurrence of the options file it finds. If no options file is found, `mex` displays an error message. You can directly specify the name of the options file using the `-f` switch.

Any variable specified in the options file can be overridden at the command line by use of the `<name>=<def>` command-line argument. If `<def>` has spaces in it, then it should be wrapped in single quotes (e.g., `OPTFLAGS=' opt1 opt2'`). The definition can rely on other variables defined in the options file; in this case the variable referenced should have a prepended \$ (e.g., `OPTFLAGS='$OPTFLAGS opt2'`).

On Windows, the options file is written in the Perl script language. The default options file is placed in your user profile directory after you configure your system by running `mex -set up`. The `mex` script searches for the first occurrence of the options file called `mexopts.bat` in the following list:

- The current directory
- The user profile directory
- <MATLAB>\bin\win32\mexopts

`mex` uses the first occurrence of the options file it finds. If no options file is found, `mex` searches your machine for a supported C compiler and uses the factory default options file for that compiler. If multiple compilers are found, you are prompted to select one.

No arguments can have an embedded equal sign (=); thus, `-DF00` is valid, but `-DF00=BAR` is not.

See Also

`dbmex`, `mexext`, `inmem`

Purpose	Return the MEX-filename extension
Syntax	<code>ext = mexext</code>
Description	<code>ext = mexext</code> returns the filename extension for the current platform.
Examples	<pre>ext = mexext ext = dll</pre>
See Also	<code>mex</code>

mfilename

Purpose	The name of the currently running M-file
Syntax	<code>mfilename</code>
Description	<code>mfilename</code> returns a string containing the name of the most recently invoked M-file. When called from within an M-file, it returns the name of that M-file, allowing an M-file to determine its name, even if the filename has been changed. When called from the command line, <code>mfilename</code> returns an empty matrix.

Purpose	Minimum elements of an array
Syntax	$C = \text{min}(A)$ $C = \text{min}(A, B)$ $C = \text{min}(A, [], dim)$ $[C, I] = \text{min}(\dots)$
Description	<p>$C = \text{min}(A)$ returns the smallest elements along different dimensions of an array.</p> <p>If A is a vector, $\text{min}(A)$ returns the smallest element in A.</p> <p>If A is a matrix, $\text{min}(A)$ treats the columns of A as vectors, returning a row vector containing the minimum element from each column.</p> <p>If A is a multidimensional array, min operates along the first nonsingleton dimension.</p> <p>$C = \text{min}(A, B)$ returns an array the same size as A and B with the smallest elements taken from A or B.</p> <p>$C = \text{min}(A, [], dim)$ returns the smallest elements along the dimension of A specified by scalar dim. For example, $\text{min}(A, [], 1)$ produces the minimum values along the first dimension (the rows) of A.</p> <p>$[C, I] = \text{min}(\dots)$ finds the indices of the minimum values of A, and returns them in output vector I. If there are several identical minimum values, the index of the first one found is returned.</p>
Remarks	For complex input A, min returns the complex number with the smallest modulus, computed with $\text{min}(\text{abs}(A))$. The min function ignores NaNs.
See Also	max , mean , median , sort

minres

Purpose	Minimum Residual method
Syntax	<pre>x = minres(A, b) minres(A, b, tol) minres(A, b, tol, maxit) minres(A, b, tol, maxit, M) minres(A, b, tol, maxit, M1, M2) minres(A, b, tol, maxit, M1, M2, x0) minres(afun, b, tol, maxit, mfun, m2fun, x0, p1, p2, ...) [x, flag] = minres(A, b, ...) [x, flag, relres] = minres(A, b, ...) [x, flag, relres, iter] = minres(A, b, ...) [x, flag, relres, iter, resvec] = minres(A, b, ...) [x, flag, relres, iter, resvec, resveccg] = minres(A, b, ...)</pre>
Description	<p><code>x = minres(A, b)</code> attempts to find a minimum norm residual solution <code>x</code> to the system of linear equations $A^*x=b$. The n-by-n coefficient matrix <code>A</code> must be symmetric but need not be positive definite. The column vector <code>b</code> must have length n. <code>A</code> can be a function <code>afun</code> such that <code>afun(x)</code> returns A^*x.</p> <p>If <code>minres</code> converges, a message to that effect is displayed. If <code>minres</code> fails to converge after the maximum number of iterations or halts for any reason, a warning message is printed displaying the relative residual $\text{norm}(b - A^*x) / \text{norm}(b)$ and the iteration number at which the method stopped or failed.</p> <p><code>minres(A, b, tol)</code> specifies the tolerance of the method. If <code>tol</code> is <code>[]</code>, then <code>minres</code> uses the default, <code>1e-6</code>.</p> <p><code>minres(A, b, tol, maxit)</code> specifies the maximum number of iterations. If <code>maxit</code> is <code>[]</code>, then <code>minres</code> uses the default, <code>min(n, 20)</code>.</p> <p><code>minres(A, b, tol, maxit, M)</code> and <code>minres(A, b, tol, maxit, M1, M2)</code> use symmetric positive definite preconditioner <code>M</code> or $M = M1 * M2$ and effectively solve the system $\text{inv}(\sqrt(M)) * A^* \text{inv}(\sqrt(M)) * y = \text{inv}(\sqrt(M)) * b$ for <code>y</code> and then return <code>x = \text{inv}(\sqrt(M)) * y</code>. If <code>M</code> is <code>[]</code> then <code>minres</code> applies no preconditioner. <code>M</code> can be a function that returns $M \backslash x$.</p> <p><code>minres(A, b, tol, maxit, M1, M2, x0)</code> specifies the initial guess. If <code>x0</code> is <code>[]</code>, then <code>minres</code> uses the default, an all-zero vector.</p>

`mi nres(afun, b, tol, maxi t, m1fun, m2fun, x0, p1, p2, ...)` passes parameters `p1, p2, ...` to functions `afun(x, p1, p2, ...)`, `m1fun(x, p1, p2, ...)`, and `m2fun(x, p1, p2, ...)`.

`[x, flag] = mi nres(A, b, ...)` also returns a convergence flag.

Flag	Convergence
0	<code>mi nres</code> converged to the desired tolerance <code>tol</code> within <code>maxi t</code> iterations.
1	<code>mi nres</code> iterated <code>maxi t</code> times but did not converge.
2	Preconditioner <code>M</code> was ill-conditioned.
3	<code>mi nres</code> stagnated. (Two consecutive iterates were the same.)
4	One of the scalar quantities calculated during <code>mi nres</code> became too small or too large to continue computing.

Whenever `flag` is not 0, the solution `x` returned is that with minimal norm residual computed over all the iterations. No messages are displayed if the `flag` output is specified.

`[x, flag, rel res] = mi nres(A, b, ...)` also returns the relative residual `norm(b-A*x)/norm(b)`. If `flag` is 0, `rel res <= tol`.

`[x, flag, rel res, iter] = mi nres(A, b, ...)` also returns the iteration number at which `x` was computed, where `0 <= iter <= maxi t`.

`[x, flag, rel res, iter, resvec] = mi nres(A, b, ...)` also returns a vector of estimates of the `mi nres` residual norms at each iteration, including `norm(b-A*x0)`.

`[x, flag, rel res, iter, resvec, resveccg] = mi nres(A, b, ...)` also returns a vector of estimates of the Conjugate Gradients residual norms at each iteration.

Examples

Example 1.

```
n = 100; on = ones(n, 1);
```

minres

```
A = spdiags([-2*on 4*on -2*on], -1:1, n, n);
b = sum(A, 2);
tol = 1e-10;
maxit = 50;
M1 = spdiags(4*on, 0, n, n);

x = minres(A, b, tol, maxit, M1, [], []);
minres converged at iteration 49 to a solution with relative
residual 4.7e-014
```

Alternatively, use this matrix-vector product function

```
function y = afun(x, n)
y = 4 * x;
y(2:n) = y(2:n) - 2 * x(1:n-1);
y(1:n-1) = y(1:n-1) - 2 * x(2:n);
```

as input to minres.

```
x1 = minres(@afun, b, tol, maxit, M1, [], n);
```

Example 2.

Use a symmetric indefinite matrix that fails with pcg.

```
A = diag([20: -1: 1, -1: -1: -20]);
b = sum(A, 2); % The true solution is the vector of all ones.
x = pcg(A, b); % Errors out at the first iteration.
pcg stopped at iteration 1 without converging to the desired
tolerance 1e-006 because a scalar quantity became too small or
too large to continue computing.
The iterate returned (number 0) has relative residual 1
```

However, minres can handle the indefinite matrix A.

```
x = minres(A, b, 1e-6, 40);
minres converged at iteration 39 to a solution with relative
residual 1.3e-007
```

See Also

bicg, bicgstab, cgs, cholinc, gmres, lsqr, pcg, qmr, symmlq
@(function handle), / (slash),

References

- [1] Barrett, R., M. Berry, T. F. Chan, et al., *Templates for the Solution of Linear Systems: Building Blocks for Iterative Methods*, SIAM, Philadelphia, 1994.
- [2] Paige, C. C. and M. A., “Solution of Sparse Indefinite Systems of Linear Equations.” *SIAM J. Numer. Anal.*, Vol.12, 1975, pp. 617-629.

mislocked

Purpose	True if M-file cannot be cleared
Syntax	<code>mislocked</code> <code>mislocked(fun)</code>
Description	<code>mislocked</code> by itself is 1 if the currently running M-file is locked and 0 otherwise. <code>mislocked(fun)</code> is 1 if the function named <i>fun</i> is locked in memory and 0 otherwise. Locked M-files cannot be removed with the <code>clear</code> function.
See Also	<code>lock</code> , <code>unlock</code>

Purpose	Make new directory
Graphical Interface	As an alternative to the <code>mkdir</code> function, you can use the Current Directory browser to create new folders. To open it, select Current Directory from the View menu in the MATLAB desktop.
Syntax	<pre>mkdir dirname mkdir parentdir dirname status = mkdir(..., 'dirname') [status, msg] = mkdir(..., 'dirname')</pre>
Description	<p><code>mkdir dirname</code> creates the directory <code>dirname</code> in the current directory. It returns a status of 1 if the new directory is created successfully, 2 if it already exists. Otherwise, it returns 0.</p> <p><code>mkdir parentdir dirname</code> creates the directory <code>dirname</code> in the existing directory <code>parentdir</code>.</p> <p><code>status = mkdir(..., 'dirname')</code> returns <code>status</code> and also returns a nonempty error message string in <code>msg</code> when an error occurs.</p> <p><code>[status, msg] = mkdir(..., 'dirname')</code> returns <code>status</code> and also returns a nonempty error message string in <code>msg</code> when an error occurs.</p>
Examples	To create a subdirectory of <code>testdata</code> called <code>newdir</code> ,
	<pre>mkdir ..\testdata newdir</pre>
	This second attempt to create the same directory fails with an error message.
	<pre>[status, msg] = mkdir('..\testdata', 'newdir') status = 2 msg = Directory or file newdir already exists in ..\testdata</pre>
See Also	<code>copyfile</code> , <code>filebrowser</code>

mkpp

Purpose	Make a piecewise polynomial
Syntax	<pre>pp = mkpp(breaks, coefs) pp = mkpp(breaks, coefs, d)</pre>
Description	<p><code>pp = mkpp(breaks, coefs)</code> builds a piecewise polynomial <code>pp</code> from its <code>breaks</code> and coefficients. <code>breaks</code> is a vector of length $L+1$ with strictly increasing elements which represent the start and end of each of L intervals. <code>coefs</code> is an L-by-k matrix with each row <code>coefs(i, :)</code> containing the coefficients of the terms, from highest to lowest exponent, of the order k polynomial on the interval $[breaks(i), breaks(i+1)]$.</p> <p><code>pp = mkpp(breaks, coefs, d)</code> indicates that the piecewise polynomial <code>pp</code> is d-vector valued, i.e., the value of each of its coefficients is a vector of length d. <code>breaks</code> is an increasing vector of length $L+1$. <code>coefs</code> is a d-by-L-by-k array with <code>coefs(r, i, :)</code> containing the k coefficients of the ith polynomial piece of the rth component of the piecewise polynomial.</p> <p>Use <code>ppval</code> to evaluate the piecewise polynomial at specific points. Use <code>unmkpp</code> to extract details of the piecewise polynomial.</p> <p>Note. The <i>order</i> of a polynomial tells you the number of coefficients used in its description. A kth order polynomial has the form</p> $c_1 x^{k-1} + c_2 x^{k-2} + \dots + c_{k-1} x + c_k$ <p>It has k coefficients, some of which can be 0, and maximum exponent $k-1$. So the order of a polynomial is usually one greater than its degree. For example, a cubic polynomial is of order 4.</p>
Examples	The first plot shows the quadratic polynomial $1 - \left(\frac{x}{2} - 1\right)^2 = \frac{-x^2}{4} + x$ shifted to the interval [-8,-4]. The second plot shows its negative $\left(\frac{x}{2} - 1\right)^2 - 1 = \frac{x^2}{4} - x$

but shifted to the interval [-4,0].

The last plot shows a piecewise polynomial constructed by alternating these two quadratic pieces over four intervals. It also shows its first derivative, which was constructed after breaking the piecewise polynomial apart using `unmkpp`.


```

subplot(2, 2, 1)
cc = [- 1/4 1 0];
pp1 = mkpp([- 8 - 4], cc);
xx1 = - 8: 0. 1: - 4;
plot(xx1, ppval(pp1, xx1), 'k-')

subplot(2, 2, 2)
pp2 = mkpp([- 4 0], - cc);
xx2 = - 4: 0. 1: 0;
plot(xx2, ppval(pp2, xx2), 'k-')

subplot(2, 1, 2)
pp = mkpp([- 8 - 4 0 4 8], [cc; - cc; cc; - cc]);
xx = - 8: 0. 1: 8;
plot(xx, ppval(pp, xx), 'k-')
[breaks, coefs, l, k, d] = unmkpp(pp);
dpp = mkpp(breaks, repmat(k-1:-1:1, d*l, 1) .* coefs(:, 1:k-1), d);
hold on, plot(xx, ppval(dpp, xx), 'r-'), hold off

```



mkpp

See Also

[ppval](#), [spli ne](#), [unmkpp](#)

Purpose	Prevent M-file clearing
Syntax	<code>ml ock</code>
Description	<p><code>ml ock</code> locks the currently running M-file in memory so that subsequent <code>clear</code> functions do not remove it.</p> <p>Use the <code>munlock</code> function to return the M-file to its normal, clearable state.</p> <p>Locking an M-file in memory also prevents any persistent variables defined in the file from getting reinitialized.</p>
Examples	<p>The function <code>testfun</code> begins with an <code>ml ock</code> statement.</p> <pre>function testfun ml ock . . </pre> <p>When you execute this function, it becomes locked in memory. This can be checked using the <code>mislocked</code> function.</p> <pre>testfun mislocked('testfun') ans = 1</pre> <p>Using <code>unlock</code>, you unlock the <code>testfun</code> function in memory. Checking its status with <code>mislocked</code> shows that it is indeed unlocked at this point.</p> <pre>unlock('testfun') mislocked('testfun') ans = 0</pre>
See Also	<code>mislocked</code> , <code>unlock</code> , <code>persistent</code>

mod

Purpose	Modulus (signed remainder after division)
Syntax	$M = \text{mod}(X, Y)$
Definition	$\text{mod}(x, y)$ is $x \bmod y$.
Description	$M = \text{mod}(X, Y)$ returns the remainder $X - Y \cdot \lfloor X/Y \rfloor$ for nonzero Y , and returns X otherwise. $\text{mod}(X, Y)$ always differs from X by a multiple of Y .
Remarks	So long as operands X and Y are of the same sign, the function $\text{mod}(X, Y)$ returns the same result as does $\text{rem}(X, Y)$. However, for positive X and Y ,
	$\text{mod}(-x, y) = \text{rem}(-x, y) + y$
	The mod function is useful for congruence relationships: x and y are congruent (mod m) if and only if $\text{mod}(x, m) == \text{mod}(y, m)$.
Examples	$\text{mod}(13, 5)$ ans = 3 $\text{mod}([1:5], 3)$ ans = 1 2 0 1 2 $\text{mod}(\text{magic}(3), 3)$ ans = 2 1 0 0 2 1 1 0 2
Limitations	Arguments X and Y should be integers. Due to the inexact representation of floating-point numbers on a computer, real (or complex) inputs may lead to unexpected results.
See Also	rem

Purpose	Control paged output for Command Window
Syntax	<code>more off</code> <code>more on</code> <code>more(n)</code>
Description	<p><code>more off</code> disables paging of the output in the MATLAB Command Window.</p> <p><code>more on</code> enables paging of the output in the MATLAB Command Window.</p> <p><code>more(n)</code> displays n lines per page.</p> <p>To see the status of <code>more</code>, type <code>get(0, 'More')</code>. MATLAB returns either <code>on</code> or <code>off</code> indicating the <code>more</code> status. You can also set status for <code>more</code> by using <code>get(0, 'More', 'status')</code>, where '<code>status</code>' is either '<code>on</code>' or '<code>off</code>'.</p> <p>When you have enabled <code>more</code> and are examining output, you can do the following.</p>

Press the...	To...
Return key	Advance to the next line of output.
Space bar	Advance to the next page of output.
Q (for quit) key	Terminate display of the text.

By default, `more` is disabled. When enabled, `more` defaults to displaying 23 lines per page.

See Also	<code>diary</code>
-----------------	--------------------

move (activex)

Purpose Move and/or resize an ActiveX control in its parent window.

Syntax `move(h, pos)`

Arguments `h`
A MATLAB ActiveX control object.

`pos`
A position.

Returns The current position.

Description `move(h, position)` moves the control to a new position;
`position = move(h)` returns the current position.

Example This example moves the control.

```
h = actxcontrol ('MWSamp. mwsampctrl. 1');
move(h, [100 100 200 200]);
pos = move(h); % pos should be [100 100 200 200]
```

This example resizes the control to always fill the figure. Execute the following in MATLAB or in some M-file:

```
f = figure('Position', [100 100 200 200]);
h = actxcontrol ('MWSAMP. MwsampCtrl. 1', [0 0 200 200]);
set(f, 'ResizeFcn', 'resizectrl')
```

Create the script `resizectrl.m` that contains

```
% Get the new position and size of the figure window
fpos = get(gcbo, 'position');

% Resize the control accordingly
move(h, [0 0 fpos(3) fpos(4)]);
```

Purpose Move GUI figure to specified location on screen

Syntax

```
movegui (h, 'position')
movegui ('position')
movegui (h)
movegui
```

Description `movegui (h, 'position')` moves the figure identified by handle `h` to the specified screen location, preserving the figure's size. The `position` argument can be any of the following strings:

- north – top center edge of screen
- south – bottom center edge of screen
- east – right center edge of screen
- west – left center edge of screen
- northeast – top right corner of screen
- northwest – top left corner of screen
- southeast – bottom right corner of screen
- southwest – bottom left corner
- center – center of screen
- onscreen – nearest location with respect to current location that is on screen

The `position` argument can also be a two-element vector `[h, v]`, where depending on sign, `h` specifies the figure's offset from the left or right edge of the screen, and `v` specifies the figure's offset from the top or bottom of the screen, in pixels. The following table summarizes the possible values.

<code>h (for h >= 0)</code>	offset of left side from left edge of screen
<code>h (for h < 0)</code>	offset of right side from right edge of screen
<code>v (for v >= 0)</code>	offset of bottom edge from bottom of screen
<code>v (for v < 0)</code>	offset of top edge from top of screen

`movegui ('position')` move the callback figure (`gcbf`) or the current figure (`gcf`) to the specified position.

movegui

movegui (h) moves the figure identified by the handle h to the onscreen position.

movegui moves the callback figure (gcbf) or the current figure (gcf) to the onscreen position. This is useful as a string-based CreateFcn callback for a saved figure. It ensures the figure appears on screen when reloaded, regardless of its saved position.

Examples

This example demonstrates the usefulness of `movegui` to ensure that saved GUIs appear on screen when reloaded, regardless of the target computer's screen sizes and resolution. It creates a figure off the screen, assigns `movegui` as its CreateFcn callback, then saves and reloads the figure.

```
f = figure('Position', [10000, 10000, 400, 300]);
set(f, 'CreateFcn', 'movegui')
hgsave(f, 'onscreenfig')
close(f)
f2 = hload('onscreenfig');
```

See Also

[guide](#)
[Creating GUIs](#)

Purpose	Play recorded movie frames
Syntax	<code>movie(M)</code> <code>movie(M, n)</code> <code>movie(M, n, fps)</code> <code>movie(h, ...)</code> <code>movie(h, M, n, fps, loc)</code>
Description	<p><code>movie</code> plays the movie defined by a matrix whose columns are movie frames (usually produced by <code>getframe</code>).</p> <p><code>movie(M)</code> plays the movie in matrix <code>M</code> once.</p> <p><code>movie(M, n)</code> plays the movie <code>n</code> times. If <code>n</code> is negative, each cycle is shown forward then backward. If <code>n</code> is a vector, the first element is the number of times to play the movie, and the remaining elements comprise a list of frames to play in the movie. For example, if <code>M</code> has four frames then <code>n = [10 4 4 2 1]</code> plays the movie ten times, and the movie consists of frame 4 followed by frame 4 again, followed by frame 2 and finally frame 1.</p> <p><code>movie(M, n, fps)</code> plays the movie at <code>fps</code> frames per second. The default is 12 frames per second. Computers that cannot achieve the specified speed play as fast as possible.</p> <p><code>movie(h, ...)</code> plays the movie in the figure or axes identified by the handle <code>h</code>.</p> <p><code>movie(h, M, n, fps, loc)</code> specifies a four-element location vector, <code>[x y 0 0]</code>, where the lower-left corner of the movie frame is anchored (only the first two elements in the vector are used). The location is relative to the lower-left corner of the figure or axes specified by handle and in units of pixels, regardless of the object's <code>Units</code> property.</p>
Remarks	The movie function displays each frame as it loads the data into memory, and then plays the movie. This eliminates long delays with a blank screen when you load a memory-intensive movie. The movie's load cycle is not considered one of the movie repetitions.
Examples	Animate the <code>peaks</code> function as you scale the values of <code>Z</code> :

movie

```
Z = peaks; surf(Z);
axis tight
set(gca, 'nextplot', 'replacechildren');

% Record the movie
for j = 1:20
    surf(sin(2*pi*j/20)*Z, Z)
    F(j) = getframe;
end

% Play the movie twenty times
movie(F, 20)
```

See Also

[getframe](#), [frame2im](#), [im2frame](#)

Purpose	Create an Audio Video Interleaved (AVI) movie from MATLAB movie		
Syntax	<pre>movie2avi (mov, filename) movie2avi (mov, filename, param, value, param, value. . .)</pre>		
Description	<p><code>movie2avi (mov, filename)</code> creates the AVI movie <code>filename</code> from the MATLAB movie <code>mov</code>.</p> <p><code>movie2avi (mov, filename, param, value, param, value. . .)</code> creates the AVI movie <code>filename</code> from the MATLAB movie <code>MOV</code> using the specified parameter settings.</p>		
Parameter	Value	Default	
' colormap'	An m -by-3 matrix defining the colormap to be used for indexed AVI movies, where m must be no greater than 256 (236 if using Indeo compression).	There is no default colormap.	
' compression'	A text string specifying which compression codec to use.		
	On Windows: 'Indeo3' 'Indeo5' 'Cinepak' 'MSVC' 'RLE' 'None'	On Unix: 'None'	'Indeo3', on Windows. 'None' on Unix.
	To use a custom compression codec, specify the four-character code that identifies the codec (typically included in the codec documentation). The <code>addframe</code> function reports an error if it can not find the specified custom compressor.		

movie2avi

Parameter	Value	Default
'fps'	A scalar value specifying the speed of the AVI movie in frames per second (fps).	15 fps
'keyframe'	For compressors that support temporal compression, this is the number of key frames per second.	2 key frames per second.
'name'	A descriptive name for the video stream. This parameter must be no greater than 64 characters long.	The default is the filename.
'quality'	A number between 0 and 100. This parameter has no effect on uncompressed movies. Higher quality numbers result in higher video quality and larger file sizes. Lower quality numbers result in lower video quality and smaller file sizes.	75

See Also

`avifile`, `aviread`, `avinfo`, `movie`

Purpose	Allocate matrix for movie frames
Syntax	<code>M = moviein(n)</code> <code>M = moviein(n, h)</code> <code>M = moviein(n, h, rect)</code>
Description	<code>moviein</code> allocates an appropriately sized matrix for the <code>getframe</code> function. <code>M = moviein(n)</code> creates matrix <code>M</code> having <code>n</code> columns to store <code>n</code> frames of a movie based on the size of the current axes. <code>M = moviein(n, h)</code> specifies a handle for a valid figure or axes graphics object on which to base the memory requirement. You must use the same handle with <code>getframe</code> . If you want to capture the axis in the frames, specify <code>h</code> as the handle of the figure. <code>M = moviein(n, h, rect)</code> specifies the rectangular area from which to copy the bitmap, relative to the lower-left corner of the figure or axes graphics object identified by <code>h</code> . <code>rect = [left bottom width height]</code> , where <code>left</code> and <code>bottom</code> specify the lower-left corner of the rectangle, and <code>width</code> and <code>height</code> specify the dimensions of the rectangle. Components of <code>rect</code> are in pixel units. You must use the same handle and rectangle with <code>getframe</code> .
Remarks	<code>moviein</code> is no longer needed as of MATLAB Release 11 (5.3). In earlier versions, pre-allocating a movie increased performance, but there is no longer a need to do this.
See Also	<code>getframe</code> , <code>movie</code>

msgbox

Purpose	Display message box
Syntax	<pre>msgbox(message) msgbox(message, title) msgbox(message, title, 'icon') msgbox(message, title, 'custom', iconData, iconCmap) msgbox(..., 'createMode') h = msgbox(...)</pre>
Description	<p><code>msgbox(message)</code> creates a message box that automatically wraps <code>message</code> to fit an appropriately sized figure. <code>message</code> is a string vector, string matrix, or cell array.</p> <p><code>msgbox(message, title)</code> specifies the title of the message box.</p> <p><code>msgbox(message, title, 'icon')</code> specifies which icon to display in the message box. '<code>icon</code>' is '<code>'none'</code>', '<code>'error'</code>', '<code>'help'</code>', '<code>'warn'</code>', or '<code>'custom'</code>'. The default is '<code>'none'</code>'.</p> <p> Error Icon  Help Icon  Warning Icon</p> <p><code>msgbox(message, title, 'custom', iconData, iconCmap)</code> defines a customized icon. <code>iconData</code> contains image data defining the icon; <code>iconCmap</code> is the colormap used for the image.</p> <p><code>msgbox(..., 'createMode')</code> specifies whether the message box is modal or nonmodal, and if it is nonmodal, whether to replace another message box with the same title. Valid values for '<code>createMode</code>' are '<code>'modal'</code>', '<code>'non-modal'</code>', and '<code>'replace'</code>'.</p> <p><code>h = msgbox(...)</code> returns the handle of the box in <code>h</code>, which is a handle to a Figure graphics object.</p>

See Also [dialog](#), [errordlg](#), [inputdlg](#), [helpdlg](#), [questdlg](#), [textwrap](#), [warndlg](#)

Purpose	Convert mu-law audio signal to linear
Syntax	<code>y = mu2lin(mu)</code>
Description	<code>y = mu2lin(mu)</code> converts mu-law encoded 8-bit audio signals, stored as “flints” in the range $0 \leq \text{mu} \leq 255$, to linear signal amplitude in the range $-s < Y < s$ where $s = 32124/32768 \approx .9803$. The input <code>mu</code> is often obtained using <code>fread(..., 'uchar')</code> to read byte-encoded audio files. “Flints” are MATLAB’s integers - floating-point numbers whose values are integers.
See Also	<code>auread</code> , <code>lin2mu</code>

munlock

Purpose	Allow M-file clearing
Syntax	<code>munlock</code> <code>munlock fun</code> <code>munlock('fun')</code>
Description	<code>munlock</code> unlocks the currently running M-file in memory so that subsequent <code>clear</code> functions can remove it. <code>munlock fun</code> unlocks the M-file named <code>fun</code> from memory. By default, M-files are unlocked so that changes to the M-file are picked up. Calls to <code>unlock</code> are needed only to unlock M-files that have been locked with <code>lock</code> . <code>munlock('fun')</code> is the function form of <code>unlock</code> .
Examples	The function <code>testfun</code> begins with an <code>lock</code> statement. <pre>function testfun lock . .</pre> When you execute this function, it becomes locked in memory. This can be checked using the <code>mislocked</code> function. <pre>testfun mislocked testfun ans = 1</pre>
	Using <code>unlock</code> , you unlock the <code>testfun</code> function in memory. Checking its status with <code>mislocked</code> shows that it is indeed unlocked at this point. <pre>unlock testfun mislocked testfun ans = 0</pre>
See Also	<code>lock</code> , <code>mislocked</code> , <code>persistent</code>

Purpose	Not-a-Number
Syntax	NaN
Description	NaN returns the IEEE arithmetic representation for Not-a-Number (NaN). These result from operations which have undefined numerical results.
Examples	<p>These operations produce NaN:</p> <ul style="list-style-type: none"> Any arithmetic operation on a NaN, such as <code>sqrt(NaN)</code> Addition or subtraction, such as magnitude subtraction of infinities as <code>(+Inf) + (-Inf)</code> Multiplication, such as <code>0*Inf</code> Division, such as <code>0/0</code> and <code>Inf/Inf</code> Remainder, such as <code>rem(x, y)</code> where <code>y</code> is zero or <code>x</code> is infinity
Remarks	<p>Because two NaNs are not equal to each other, logical operations involving NaNs always return false, except <code>~=</code> (not equal). Consequently,</p> <pre> NaN ~= NaN ans = 1 NaN == NaN ans = 0 </pre> <p>and the NaNs in a vector are treated as different unique elements.</p> <pre> unique([1 1 NaN NaN]) ans = 1 NaN NaN </pre> <p>Use the <code>isnan</code> function to detect NaNs in an array.</p> <pre> isnan([1 1 NaN NaN]) ans = 0 0 1 1 </pre>
See Also	<code>Inf</code> , <code>isnan</code>

nargchk

Purpose	Check number of input arguments
Syntax	<code>msg = nargchk(low, high, number)</code>
Description	The <code>nargchk</code> function often is used inside an M-file to check that the correct number of arguments have been passed. <code>msg = nargchk(low, high, number)</code> returns an error message if <code>number</code> is less than <code>low</code> or greater than <code>high</code> . If <code>number</code> is between <code>low</code> and <code>high</code> (inclusive), <code>nargchk</code> returns an empty matrix.
Arguments	<p>Input arguments to <code>nargchk</code> are</p> <p><code>low, high</code> The minimum and maximum number of input arguments that should be passed.</p> <p><code>number</code> The number of arguments actually passed, as determined by the <code>nargin</code> function.</p>
Examples	<p>Given the function <code>foo</code>:</p> <pre>function f = foo(x, y, z) error(nargchk(2, 3, nargin))</pre> <p>Then typing <code>foo(1)</code> produces:</p> <p>Not enough input arguments.</p>
See Also	<code>nargin, nargout</code>

Purpose	Number of function arguments
Syntax	<pre>n = nargin n = nargin('fun') n = nargout n = nargout('fun')</pre>
Description	In the body of a function M-file, nargin and nargout indicate how many input or output arguments, respectively, a user has supplied. Outside the body of a function M-file, nargin and nargout indicate the number of input or output arguments, respectively, for a given function. The number of arguments is negative if the function has a variable number of arguments.
	nargin returns the number of input arguments specified for a function.
	nargin('fun') returns the number of declared inputs for the M-file function <i>fun</i> or -1 if the function has a variable of input arguments.
	nargout returns the number of output arguments specified for a function.
	nargout('fun') returns the number of declared outputs for the M-file function <i>fun</i> .
Examples	This example shows portions of the code for a function called myplot, which accepts an optional number of input and output arguments:
	<pre>function [x0, y0] = myplot(fname, lims, npts, angl, subdiv) % MYPLOT Plot a function. % MYPLOT(fname, lims, npts, angl, subdiv) % The first two input arguments are % required; the other three have default values. ... if nargin < 5, subdiv = 20; end if nargin < 4, angl = 10; end if nargin < 3, npts = 25; end ... if nargout == 0 plot(x, y) else x0 = x;</pre>

nargin, nargout

```
y0 = y;  
end
```

See Also

[inputname](#), [nargchk](#)

Purpose	Validate number of output arguments
Syntax	<code>msg = nargoutchk(low, high, n)</code>
Description	<code>msg = nargoutchk(low, high, n)</code> returns an appropriate error message if <code>n</code> is not between <code>low</code> and <code>high</code> . If the number of output arguments is within the specified range, <code>nargoutchk</code> returns an empty matrix.
Examples	You can use <code>nargoutchk</code> to determine if an M-file has been called with the correct number of output arguments. This example uses <code>nargout</code> to return the number of output arguments specified when the function was called. The function is designed to be called with one, two, or three output arguments. If called with no arguments or more than three arguments, <code>nargoutchk</code> returns an error message. <pre>function [s, varargout] = mysize(x) msg = nargoutchk(1, 3, nargout); if isempty(msg) nout = max(nargout, 1) - 1; s = size(x); for k=1:nout, varargout(k) = {s(k)}; end else disp(msg) end</pre>

See Also `inputname`, `nargchk`, `nargin`, `nargout`, `varargout`

nchoosek

Purpose	Binomial coefficient or all combinations																				
Syntax	$C = \text{nchoosek}(n, k)$ $C = \text{nchoosek}(v, k)$																				
Description	$C = \text{nchoosek}(n, k)$ where n and k are nonnegative integers, returns $\frac{n!}{(n-k)! k!}$. This is the number of combinations of n things taken k at a time. $C = \text{nchoosek}(v, k)$, where v is a row vector of length n , creates a matrix whose rows consist of all possible combinations of the n elements of v taken k at a time. Matrix C contains $\frac{n!}{(n-k)! k!}$ rows and k columns.																				
Examples	The command <code>nchoosek(2: 2: 10, 4)</code> returns the even numbers from two to ten, taken four at a time:																				
	<table><tr><td>2</td><td>4</td><td>6</td><td>8</td></tr><tr><td>2</td><td>4</td><td>6</td><td>10</td></tr><tr><td>2</td><td>4</td><td>8</td><td>10</td></tr><tr><td>2</td><td>6</td><td>8</td><td>10</td></tr><tr><td>4</td><td>6</td><td>8</td><td>10</td></tr></table>	2	4	6	8	2	4	6	10	2	4	8	10	2	6	8	10	4	6	8	10
2	4	6	8																		
2	4	6	10																		
2	4	8	10																		
2	6	8	10																		
4	6	8	10																		
Limitations	This function is only practical for situations where n is less than about 15.																				
See Also	<code>perms</code>																				

Purpose

Generate arrays for multidimensional functions and interpolation

Syntax

```
[X1, X2, X3, . . . ] = ndgrid(x1, x2, x3, . . . )
[X1, X2, . . . ] = ndgrid(x)
```

Description


$[X1, X2, X3, . . .] = \text{ndgrid}(x1, x2, x3, . . .)$ transforms the domain specified by vectors $x1, x2, x3, . . .$ into arrays $X1, X2, X3, . . .$ that can be used for the evaluation of functions of multiple variables and multidimensional interpolation. The i th dimension of the output array Xi are copies of elements of the vector xi .

$[X1, X2, . . .] = \text{ndgrid}(x)$ is the same as $[X1, X2, . . .] = \text{ndgrid}(x, x, . . .)$.

Examples

Evaluate the function $x_1 e^{-x_1^2 - x_2^2}$ over the range $-2 < x_1 < 2, -2 < x_2 < 2$.

```
[X1, X2] = ndgrid(-2:2:2, -2:2:2);
Z = X1 .* exp(-X1.^2 - X2.^2);
mesh(Z)
```



ndgrid

Remarks

The `ndgrid` function is like `meshgrid` except that the order of the first two input arguments are switched. That is, the statement

`[X1, X2, X3] = ndgrid(x1, x2, x3)`

produces the same result as

`[X2, X1, X3] = meshgrid(x2, x1, x3)`

Because of this, `ndgrid` is better suited to multidimensional problems that aren't spatially based, while `meshgrid` is better suited to problems in two- or three-dimensional Cartesian space.

See Also

`meshgrid`, `interp`

Purpose	Number of array dimensions
Syntax	<code>n = ndims(A)</code>
Description	<code>n = ndims(A)</code> returns the number of dimensions in the array A. The number of dimensions in an array is always greater than or equal to 2. Trailing singleton dimensions are ignored. A singleton dimension is any dimension for which <code>size(A, dim) = 1</code> .
Algorithm	<code>ndims(x)</code> is <code>length(size(x))</code> .
See Also	<code>size</code>

newplot

Purpose	Determine where to draw graphics objects
Syntax	<code>newplot</code> <code>h = newplot</code>
Description	<code>newplot</code> prepares a figure and axes for subsequent graphics commands. <code>h = newplot</code> prepares a figure and axes for subsequent graphics commands and returns a handle to the current axes.
Remarks	Use <code>newplot</code> at the beginning of high-level graphics M-files to determine which figure and axes to target for graphics output. Calling <code>newplot</code> can change the current figure and current axes. Basically, there are three options when drawing graphics in existing figures and axes: <ul style="list-style-type: none">• Add the new graphics without changing any properties or deleting any objects.• Delete all existing objects whose handles are not hidden before drawing the new objects.• Delete all existing objects regardless of whether or not their handles are hidden and reset most properties to their defaults before drawing the new objects (refer to the following table for specific information). The figure and axes <code>NextPlot</code> properties determine how <code>nextplot</code> behaves. The following two tables describe this behavior with various property values. First, <code>newplot</code> reads the current figure's <code>NextPlot</code> property and acts accordingly.

NextPlot	What Happens
<code>add</code>	Draw to the current figure without clearing any graphics objects already present.
<code>replacechildren</code>	Remove all child objects whose <code>HandleVisibility</code> property is set to <code>on</code> and reset figure <code>NextPlot</code> property to <code>add</code> . This clears the current figure and is equivalent to issuing the <code>clf</code> command.

NextPlot	What Happens
replace	<p>Remove all child objects (regardless of the setting of the Handl eVi si bi li ty property) and reset figure properties to their defaults, except:</p> <ul style="list-style-type: none"> • NextPl ot is reset to add regardless of user-defined defaults) • Posi ti on, Uni ts, PaperPosi ti on, and PaperUni ts are not reset <p>This clears and resets the current figure and is equivalent to issuing the cl f reset command.</p>

After newpl ot establishes which figure to draw in, it reads the current axes' NextPl ot property and acts accordingly.

NextPlot	Description
add	Draw into the current axes, retaining all graphics objects already present.
repl acechi l dren	Remove all child objects whose Handl eVi si bi li ty property is set to on, but do not reset axes properties. This clears the current axes like the cl a command.
replace	<p>Removes all child objects (regardless of the setting of the Handl eVi si bi li ty property) and resets axes properties to their defaults, except Posi ti on and Uni ts</p> <p>This clears and resets the current axes like the cl a reset command.</p>

See Also

[axes](#), [cl a](#), [cl f](#), [fi gure](#), [hol d](#), [i shold](#), [reset](#)

The NextPl ot property for figure and axes graphics objects.

nextpow2

Purpose	Next power of two
Syntax	<code>p = nextpow2(A)</code>
Description	<p><code>p = nextpow2(A)</code> returns the smallest power of two that is greater than or equal to the absolute value of <code>A</code>. (That is, <code>p</code> that satisfies $2^p \geq \text{abs}(A)$).</p> <p>This function is useful for optimizing FFT operations, which are most efficient when sequence length is an exact power of two.</p> <p>If <code>A</code> is non-scalar, <code>nextpow2</code> returns the smallest power of two greater than or equal to <code>length(A)</code>.</p>
Examples	<p>For any integer <code>n</code> in the range from 513 to 1024, <code>nextpow2(n)</code> is 10.</p> <p>For a 1-by-30 vector <code>A</code>, <code>length(A)</code> is 30 and <code>nextpow2(A)</code> is 5.</p>
See Also	<code>fft</code> , <code>log2</code> , <code>pow2</code>

Purpose	Nonnegative least squares
----------------	---------------------------

Note The nnls function was replaced by lsqnonneg in Release 11 (MATLAB 5.3). In Release 12 (MATLAB 6.0), nnls displays a warning message and calls lsqnonneg.

Syntax	$x = \text{nnls}(A, b)$ $x = \text{nnls}(A, b, tol)$ $[x, w] = \text{nnls}(A, b)$ $[x, w] = \text{nnls}(A, b, tol)$
---------------	--

Description	<p>$x = \text{nnls}(A, b)$ solves the system of equations $Ax = b$ in a least squares sense, subject to the constraint that the solution vector x has nonnegative elements $x_j \geq 0$, $j = 1, 2, \dots, n$. The solution x minimizes $\ (Ax - b)\$ subject to $x \geq 0$.</p> <p>$x = \text{nnls}(A, b, tol)$ solves the system of equations, and specifies a tolerance tol. By default, tol is: $\max(\text{size}(A)) * \text{norm}(A, 1) * \text{eps}$.</p> <p>$[x, w] = \text{nnls}(A, b)$ also returns the dual vector w, where $w_i \leq 0$ when $x_i = 0$ and $w_i \geq 0$ when $x_i > 0$.</p> <p>$[x, w] = \text{nnls}(A, b, tol)$ solves the system of equations, returns the dual vector w, and specifies a tolerance tol.</p>
--------------------	---

Examples	Compare the unconstrained least squares solution to the nnls solution for a 4-by-2 problem:
-----------------	---

$A =$

0.0372	0.2869
0.6861	0.7071
0.6233	0.6245
0.6344	0.6170

$b =$

0.8587
0.1781

nnls

```
0. 0747  
0. 8405
```

```
[A\b nnls(A, b)] =  
- 2. 5627      0  
3. 1108   0. 6929
```

```
[norm(A*(a\b) - b)  norm(A*nnls(a, b) - b)] =  
0. 6674  0. 9118
```

The solution from `nnls` does not fit as well, but has no negative components.

Algorithm

The `nnls` function uses the algorithm described in [1], Chapter 23. The algorithm starts with a set of possible basis vectors, computes the associated dual vector w , and selects the basis vector corresponding to the maximum value in w to swap out of the basis in exchange for another possible candidate, until $w \leq 0$.

See Also

\ Matrix left division (backslash)

References

[1] Lawson, C. L. and R. J. Hanson, *Solving Least Squares Problems*, Prentice-Hall, 1974, Chapter 23.

Purpose	Number of nonzero matrix elements
Syntax	<code>n = nnz(X)</code>
Description	<code>n = nnz(X)</code> returns the number of nonzero elements in matrix <code>X</code> . The density of a sparse matrix is <code>nnz(X) / prod(size(X))</code> .
Examples	The matrix <code>w = sparse(willkinson(21));</code> is a tridiagonal matrix with 20 nonzeros on each of three diagonals, so <code>nnz(w) = 60.</code>
See Also	<code>find, issa, nonzeros, nzmax, size, whos</code>

noanimate

Purpose	Change EraseMode of all objects to normal
Syntax	<code>noanimate(state, fig_handle)</code> <code>noanimate(state)</code>
Description	<code>noanimate(state, fig_handle)</code> sets the EraseMode of all image, line, patch surface, and text graphics object in the specified figure to normal . state can be the following strings: <ul style="list-style-type: none">• ' save' – set the values of the EraseMode properties to normal for all the appropriate objects in the designated figure.• ' restore' – restore the EraseMode properties to the previous values (i.e., the values before calling <code>noanimate</code> with the ' save' argument). <code>noanimate(state)</code> operates on the current figure. <code>noanimate</code> is useful if you want to print the figure to a Tiff or JPEG format.
See Also	<code>print</code>

Purpose Nonzero matrix elements

Syntax `s = nonzeros(A)`

Description `s = nonzeros(A)` returns a full column vector of the nonzero elements in `A`, ordered by columns.

This gives the `s`, but not the `i` and `j`, from `[i, j, s] = find(A)`. Generally,

`length(s) = nnz(A) <= nzmax(A) <= prod(size(A))`

See Also `find, issa, nnz, nzmax, size, whos`

norm

Purpose Vector and matrix norms

Syntax

```
n = norm(A)
n = norm(A, p)
```

Description The *norm* of a matrix is a scalar that gives some measure of the magnitude of the elements of the matrix. The *norm* function calculates several different types of matrix norms:

`n = norm(A)` returns the largest singular value of *A*, `max(svd(A))`.

`n = norm(A, p)` returns a different kind of norm, depending on the value of *p*.

If <i>p</i> is...	Then <i>norm</i> returns...
1	The 1-norm, or largest column sum of <i>A</i> , <code>max(sum(abs(A)))</code> .
2	The largest singular value (same as <code>norm(A)</code>).
<code>i nf</code>	The infinity norm, or largest row sum of <i>A</i> , <code>max(sum(abs(A')))</code> .
<code>' fro'</code>	The Frobenius-norm of matrix <i>A</i> , <code>sqrt(sum(diag(A' *A)))</code> .

When *A* is a vector, slightly different rules apply:

`norm(A, p)` Returns `sum(abs(A) . ^p)^(1/p)`, for any $1 \leq p \leq \infty$.

`norm(A)` Returns `norm(A, 2)`.

`norm(A, i nf)` Returns `max(abs(A))`.

`norm(A, -i nf)` Returns `min(abs(A))`.

Remarks To obtain the root-mean-square (RMS) value, use `norm(A) / sqrt(n)`. Note that `norm(A)`, where *A* is an *n*-element vector, is the length of *A*.

See Also `cond`, `conde`, `normest`, `rcond`, `svd`

Purpose	2-norm estimate
Syntax	<pre>nrm = normest(S) nrm = normest(S, tol) [nrm, count] = normest(...)</pre>
Description	This function is intended primarily for sparse matrices, although it works correctly and may be useful for large, full matrices as well. <code>nrm = normest(S)</code> returns an estimate of the 2-norm of the matrix <code>S</code> . <code>nrm = normest(S, tol)</code> uses relative error <code>tol</code> instead of the default tolerance <code>1.e-6</code> . The value of <code>tol</code> determines when the estimate is considered acceptable. <code>[nrm, count] = normest(...)</code> returns an estimate of the 2-norm and also gives the number of power iterations used.
Examples	The matrix <code>W = gallery('wilkinson', 101)</code> is a tridiagonal matrix. Its order, 101, is small enough that <code>norm(full(W))</code> , which involves <code>svd(full(W))</code> , is feasible. The computation takes 4.13 seconds (on one computer) and produces the exact norm, 50.7462. On the other hand, <code>normest(sparse(W))</code> requires only 1.56 seconds and produces the estimated norm, 50.7458.
Algorithm	The power iteration involves repeated multiplication by the matrix <code>S</code> and its transpose, <code>S'</code> . The iteration is carried out until two successive estimates agree to within the specified relative tolerance.
See Also	<code>cond</code> , <code>condest</code> , <code>norm</code> , <code>rcond</code> , <code>svd</code>

notebook

Purpose	Open an M-book in Microsoft Word (Windows only)
Syntax	<pre>notebook notebook(filename) notebook('-setup') notebook('-setup', wordver, wordloc, templateloc)</pre>
Description	<p>notebook by itself, launches Microsoft Word and creates a new M-book called Document 1.</p> <p>notebook(filename) launches Microsoft Word and opens the M-book filename.</p> <p>notebook('-setup') runs an interactive setup function for the Notebook. You are prompted for the version of Microsoft Word and the locations of several files.</p> <p>notebook('-setup', wordver, wordloc, templateloc) sets up the Notebook using the specified information.</p> <p>wordver version of Microsoft Word, either 95 or 97 wordloc directory containing winword.exe templateloc directory containing Microsoft Word template directory</p>
See Also	<p>“Using Notebook” in Using MATLAB</p>

Purpose	Current date and time
Syntax	<code>t = now</code>
Description	<code>t = now</code> returns the current date and time as a serial date number. To return the time only, use <code>rem(now, 1)</code> . To return the date only, use <code>floor(now)</code> .
Examples	<pre>t1 = now, t2 = rem(now, 1)</pre> <code>t1 =</code> <code>7.2908e+05</code> <code>t2 =</code> <code>0.4013</code>
See Also	<code>clock, date, datenum</code>

null

Purpose	Null space of a matrix
Syntax	<code>B = null(A)</code>
Description	<code>B = null(A)</code> returns an orthonormal basis for the null space of A.
Remarks	$B' * B = I$, $A * B$ has negligible elements, and (if B is not equal to the empty matrix) the number of columns of B is the nullity of A.
Example	<pre>A = 1 2 3 1 2 3 1 2 3 null(A) ans = -0.1559 0.9509 -0.7971 -0.2809 0.5834 -0.1297 null(A, 'r') ans = -2 -3 1 0 0 1</pre>
See Also	<code>orth</code> , <code>qr</code> , <code>svd</code>

Purpose	Convert a numeric array into a cell array
Syntax	<code>c = num2cell(A)</code> <code>c = num2cell(A, dims)</code>
Description	<code>c = num2cell(A)</code> converts the matrix A into a cell array by placing each element of A into a separate cell. Cell array c will be the same size as matrix A.
	<code>c = num2cell(A, dims)</code> converts the matrix A into a cell array by placing the dimensions specified by <code>dims</code> into separate cells. C will be the same size as A except that the dimensions matching <code>dims</code> will be 1.
Examples	The statement <code>num2cell(A, 2)</code> places the rows of A into separate cells. Similarly <code>num2cell(A, [1 3])</code> places the column-depth pages of A into separate cells.
See Also	<code>cat</code>

num2str

Purpose	Number to string conversion
Syntax	<pre>str = num2str(A) str = num2str(A, precision) str = num2str(A, format)</pre>
Description	<p>The <code>num2str</code> function converts numbers to their string representations. This function is useful for labeling and titling plots with numeric values.</p> <p><code>str = num2str(a)</code> converts array A into a string representation str with roughly four digits of precision and an exponent if required.</p> <p><code>str = num2str(a, precision)</code> converts the array A into a string representation str with maximum precision specified by <i>precision</i>. Argument <i>precision</i> specifies the number of digits the output string is to contain. The default is four.</p> <p><code>str = num2str(A, format)</code> converts array A using the supplied <i>format</i>. By default, this is '<code>%11.4g</code>', which signifies four significant digits in exponential or fixed-point notation, whichever is shorter. (See <code>fprintf</code> for format string details).</p>
Examples	<p><code>num2str(pi)</code> is 3.142.</p> <p><code>num2str(eps)</code> is 2.22e-16.</p> <p><code>num2str(magic(2))</code> produces the string matrix</p> <pre>1 3 4 2</pre>
See Also	<code>fprintf</code> , <code>int2str</code> , <code>sprintf</code>

Purpose Number of elements in array or subscripted array expression

Syntax `n = numel(A)`

`n = numel(A, varargin)`

Description `n = numel(A)` returns the the number of elements, `n`, in array `A`.

`n = numel(A, varargin)` returns the number of subscripted elements, `n`, in `A(index1, index2, ..., indexn)`, where `varargin` is a cell array whose elements are `index1, index2, ..., indexn`.

MATLAB implicitly calls the `numel` builtin function whenever an expression such as `A{index1, index2, ..., indexN}` or `A.fieldname` generates a comma-separated list.

`numel` works with the overloaded `subsref` and `subsasgn` functions. It computes the number of expected outputs (`nargout`) returned from `subsref`. It also computes the number of expected inputs (`nargin`) to be assigned using `subsasgn`. The `nargin` value for the overloaded `subsasgn` function consists of the variable being assigned to, the structure array of subscripts, and the value returned by `numel`.

As a class designer, you must ensure that the value of `n` returned by the builtin `numel` function is consistent with the class design for that object. If `n` is different from either the `nargout` for the overloaded `subsref` function or the `nargin` for the overloaded `subsasgn` function, then you need to overload `numel` to return a value of `n` that is consistent with the class' `subsref` and `subsasgn` functions. Otherwise, MATLAB produces errors when calling these functions.

Examples Create a 4-by-4-by-2 matrix. `numel` counts 32 elments in the matrix.

```
a = magic(4);
a(:, :, 2) = a'
```

```
a(:, :, 1) =
    16      2      3     13
      5     11     10      8
      9      7      6     12
      4     14     15      1
```

```
a(:, :, 2) =
```

numel

```
16      5      9      4
 2      11      7     14
 3      10      6     15
13      8     12      1
```

```
numel(a)
ans =
32
```

See Also

[nargin](#), [nargout](#), [prod](#), [size](#), [subsasgn](#), [subsref](#)

Purpose	Amount of storage allocated for nonzero matrix elements
Syntax	<code>n = nzmax(S)</code>
Description	<p><code>n = nzmax(S)</code> returns the amount of storage allocated for nonzero elements.</p> <p>If <code>S</code> is a sparse matrix... <code>nzmax(S)</code> is the number of storage locations allocated for the nonzero elements in <code>S</code>.</p> <p>If <code>S</code> is a full matrix... <code>nzmax(S) = prod(size(S))</code>.</p>
	Often, <code>nnz(S)</code> and <code>nzmax(S)</code> are the same. But if <code>S</code> is created by an operation which produces fill-in matrix elements, such as sparse matrix multiplication or sparse LU factorization, more storage may be allocated than is actually required, and <code>nzmax(S)</code> reflects this. Alternatively, <code>sparse(i, j, s, m, n, nzmax)</code> or its simpler form, <code>spalloc(m, n, nzmax)</code> , can set <code>nzmax</code> in anticipation of later fill-in.
See Also	<code>find, issa, nnz, nonzeros, size, whos</code>

ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb

Purpose	Solve initial value problems for ordinary differential equations (ODEs)
Syntax	<pre>[T, Y] = solver(odefun, tspan, y0) [T, Y] = solver(odefun, tspan, y0, options) [T, Y] = solver(odefun, tspan, y0, options, p1, p2...) [T, Y, TE, YE, IE] = solver(odefun, tspan, y0, options) sol = solver(odefun, [t0 tf], y0...)</pre> <p>where <code>solver</code> is one of <code>ode45</code>, <code>ode23</code>, <code>ode113</code>, <code>ode15s</code>, <code>ode23s</code>, <code>ode23t</code>, or <code>ode23tb</code>.</p>
Arguments	<p><code>odefun</code> A function that evaluates the right-hand side of the differential equations. All solvers solve systems of equations in the form $y' = f(t, y)$ or problems that involve a mass matrix, $M(t, y)y' = f(t, y)$. The <code>ode23s</code> solver can solve only equations with constant mass matrices. <code>ode15s</code> and <code>ode23t</code> can solve problems with a mass matrix that is singular, i.e., differential-algebraic equations (DAEs).</p> <p><code>tspan</code> A vector specifying the interval of integration, $[t_0, t_f]$. To obtain solutions at specific times (all increasing or all decreasing), use <code>tspan = [t_0, t_1, ..., t_f]</code>.</p> <p><code>y0</code> A vector of initial conditions.</p> <p><code>options</code> Optional integration argument created using the <code>odeset</code> function. See <code>odeset</code> for details.</p> <p><code>p1, p2...</code> Optional parameters to be passed to <code>odefun</code>.</p>
Description	<p><code>[T, Y] = solver(odefun, tspan, y0)</code> with <code>tspan = [t0 tf]</code> integrates the system of differential equations $y' = f(t, y)$ from time t_0 to t_f with initial conditions y_0. Function $f = \text{odefun}(t, y)$, for a scalar t and a column vector y, must return a column vector f corresponding to $f(t, y)$. Each row in the solution array Y corresponds to a time returned in column vector T. To obtain solutions at the specific times t_0, t_1, \dots, t_f (all increasing or all decreasing), use <code>tspan = [t0, t1, ..., tf]</code>.</p> <p><code>[T, Y] = solver(odefun, tspan, y0, options)</code> solves as above with default integration parameters replaced by property values specified in <code>options</code>, an</p>

argument created with the odeset function. Commonly used properties include a scalar relative error tolerance RelTol (1e-3 by default) and a vector of absolute error tolerances AbsTol (all components are 1e-6 by default). See odeset for details.

`[T, Y] = solver(odefun, tspan, y0, options, p1, p2...)` solves as above, passing the additional parameters `p1, p2...` to the function `odefun`, whenever it is called. Use `options = []` as a place holder if no options are set.

`[T, Y, TE, YE, IE] = solver(odefun, tspan, y0, options)` solves as above while also finding where functions of (t, y) , called event functions, are zero. For each event function, you specify whether the integration is to terminate at a zero and whether the direction of the zero crossing matters. This is done by setting the Events property to, say, @EVENTS, and creating a function `[value, isTerminal, direction] = EVENTS(t, y)`. For the i th event function:

- `value(i)` is the value of the function.
- `isTerminal(i) = 1` if the integration is to terminate at a zero of this event function and 0 otherwise.
- `direction(i) = 0` if all zeros are to be computed (the default), +1 if only the zeros where the event function increases, and -1 if only the zeros where the event function decreases.

Corresponding entries in `TE`, `YE`, and `IE` return, respectively, the time at which an event occurs, the solution at the time of the event, and the index i of the event function that vanishes.

`sol = solver(odefun, [t0 tf], y0...)` returns a structure that you can use with `deval` to evaluate the solution at any point on the interval $[t_0, t_f]$. You must pass `odefun` as a function handle. The structure `sol` always includes these fields:

<code>sol.x</code>	Steps chosen by the solver.
<code>sol.y</code>	Each column <code>sol.y(:, i)</code> contains the solution at <code>sol.x(i)</code> .
<code>sol.solver</code>	Solver name.

ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb

If you specify the Events option and events are detected, sol also includes these fields:

<code>sol . xe</code>	Points at which events, if any, occurred. <code>sol . xe(end)</code> contains the exact point of a terminal event, if any.
<code>sol . ye</code>	Solutions that correspond to events in <code>sol . xe</code> .
<code>sol . i e</code>	Indices into the vector returned by the function specified in the Event option. The values indicate which event has been detected.

If you specify an output function as the value of the OutputFcn property, the solver calls it with the computed solution after each time step. Four output functions are provided: `odeplot`, `odephas2`, `odephas3`, `odeprint`. When you call the solver with no output arguments, it calls the default `odeplot` to plot the solution as it is computed. `odephas2` and `odephas3` produce two- and three-dimensional phase plane plots, respectively. `odeprint` displays the solution components on the screen. By default, the ODE solver passes all components of the solution to the output function. You can pass only specific components by providing a vector of indices as the value of the OutputSel property. For example, if you call the solver with no output arguments and set the value of `OutputSel` to [1, 3], the solver plots solution components 1 and 3 as they are computed.

For the stiff solvers `ode15s`, `ode23s`, `ode23t`, and `ode23tb`, the Jacobian matrix $\partial f / \partial y$ is critical to reliability and efficiency. Use `odeset` to set `Jacobian` to `@FJAC` if `FJAC(T, Y)` returns the Jacobian $\partial f / \partial y$ or to the matrix $\partial f / \partial y$ if the Jacobian is constant. If the `Jacobian` property is not set (the default), $\partial f / \partial y$ is approximated by finite differences. Set the `Vectorized` property 'on' if the ODE function is coded so that `odefun(T,[Y1, Y2, ...])` returns `[odefun(T,Y1), odefun(T,Y2), ...]`. If $\partial f / \partial y$ is a sparse matrix, set the `JPattern` property to the sparsity pattern of $\partial f / \partial y$, i.e., a sparse matrix `S` with $S(i, j) = 1$ if the i th component of $f(t, y)$ depends on the j th component of y , and 0 otherwise.

The solvers of the ODE suite can solve problems of the form $M(t, y)y' = f(t, y)$, with time- and state-dependent mass matrix M . (The `ode23s` solver can solve only equations with constant mass matrices.) If a problem has a mass matrix, create a function `M = MASS(t, y)` that returns the

value of the mass matrix, and use `odeset` to set the `Mass` property to `@MASS`. If the mass matrix is constant, the matrix should be used as the value of the `Mass` property. Problems with state-dependent mass matrices are more difficult:

- If the mass matrix does not depend on the state variable y and the function `MASS` is to be called with one input argument, t , set the `MStateDependence` property to 'none'.
- If the mass matrix depends weakly on y , set `MStateDependence` to 'weak' (the default) and otherwise, to 'strong'. In either case, the function `MASS` is called with the two arguments (t,y) .

If there are many differential equations, it is important to exploit sparsity:

- Return a sparse $M(t, y)$.
- Supply the sparsity pattern of $\partial f / \partial y$ using the `JPattern` property or a sparse $\partial f / \partial y$ using the `Jacobi`an property.
- For strongly state-dependent $M(t, y)$, set `MvPattern` to a sparse matrix S with $S(i, j) = 1$ if for any k , the (i, k) component of $M(t, y)$ depends on component j of y , and 0 otherwise.

If the mass matrix M is singular, then $M(t, y)y' = f(t, y)$ is a differential algebraic equation. DAEs have solutions only when y_0 is consistent, that is, if there is a vector yp_0 such that $M(t_0, y_0)yp_0 = f(t_0, y_0)$. The `ode15s` and `ode23t` solvers can solve DAEs of index 1 provided that y_0 is sufficiently close to being consistent. If there is a mass matrix, you can use `odeset` to set the `MassSingular` property to 'yes', 'no', or 'maybe'. The default value of 'maybe' causes the solver to test whether the problem is a DAE. You can provide yp_0 as the value of the `InitialSlope` property. The default is the zero vector. If a problem is a DAE, and y_0 and yp_0 are not consistent, the solver treats them as guesses, attempts to compute consistent values that are close to the guesses, and continues to solve the problem. When solving DAEs, it is very advantageous to formulate the problem so that M is a diagonal matrix (a semi-explicit DAE).

ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb

Solver	Problem Type	Order of Accuracy	When to Use
ode45	Nonstiff	Medium	Most of the time. This should be the first solver you try.
ode23	Nonstiff	Low	If using crude error tolerances or solving moderately stiff problems.
ode113	Nonstiff	Low to high	If using stringent error tolerances or solving a computationally intensive ODE file.
ode15s	Stiff	Low to medium	If ode45 is slow because the problem is stiff.
ode23s	Stiff	Low	If using crude error tolerances to solve stiff systems and the mass matrix is constant.
ode23t	Moderately Stiff	Low	If the problem is only moderately stiff and you need a solution without numerical damping.
ode23tb	Stiff	Low	If using crude error tolerances to solve stiff systems.

The algorithms used in the ODE solvers vary according to order of accuracy [6] and the type of systems (stiff or nonstiff) they are designed to solve. See “Algorithms” on page 2-645 for more details.

Options

Different solvers accept different parameters in the options list. For more information, see `odeset` and “Improving ODE Solver Performance” in the “Mathematics” section of the MATLAB documentation.

Parameters	ode45	ode23	ode113	ode15s	ode23s	ode23t	ode23tb
RelTol, AbsTol, NormControl	✓	✓	✓	✓	✓	✓	✓
OutputFcns, OutputSel, Refine, Stats	✓	✓	✓	✓	✓	✓	✓

ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb

Parameters	ode45	ode23	ode113	ode15s	ode23s	ode23t	ode23tb
Events	✓	✓	✓	✓	✓	✓	✓
MaxStep, Initial Step	✓	✓	✓	✓	✓	✓	✓
Jacobi an, JPattern, Vectorized	—	—	—	✓	✓	✓	✓
Mass	✓	✓	✓	✓	✓	✓	✓
MStateDependence	✓	✓	✓	✓	—	✓	✓
MvPattern	—	—	—	✓	—	✓	✓
MassSingular	—	—	—	✓	—	✓	—
Initial Slope	—	—	—	✓	—	✓	—
MaxOrder, BDF	—	—	—	✓	—	—	—

Examples

Example 1. An example of a nonstiff system is the system of equations describing the motion of a rigid body without external forces.

$$\begin{aligned}y'_1 &= y_2 \ y_3 & y_1(0) &= 0 \\y'_2 &= -y_1 \ y_3 & y_2(0) &= 1 \\y'_3 &= -0.51 \ y_1 \ y_2 & y_3(0) &= 1\end{aligned}$$

To simulate this system, create a function `rigid` containing the equations

```
function dy = rigid(t, y)
dy = zeros(3, 1); % a column vector
dy(1) = y(2) * y(3);
dy(2) = -y(1) * y(3);
dy(3) = -0.51 * y(1) * y(2);
```


In this example we change the error tolerances using the `odeset` command and solve on a time interval [0 12] with an initial condition vector [0 1 1] at time 0.

```
options = odeset('RelTol', 1e-4, 'AbsTol', [1e-4 1e-4 1e-5]);
[T, Y] = ode45(@rigid, [0 12], [0 1 1], options);
```

ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb

Plotting the columns of the returned array Y versus T shows the solution

```
plot(T, Y(:, 1), '-.', T, Y(:, 2), '-.', T, Y(:, 3), '.')
```



Example 2. An example of a stiff system is provided by the van der Pol equations in relaxation oscillation. The limit cycle has portions where the solution components change slowly and the problem is quite stiff, alternating with regions of very sharp change where it is not stiff.

$$\begin{aligned}y'_1 &= y_2 & y_1(0) &= 0 \\y'_2 &= 1000(1 - y_1^2)y_2 - y_1 & y_2(0) &= 1\end{aligned}$$

To simulate this system, create a function vdp1000 containing the equations

```
function dy = vdp1000(t, y)
dy = zeros(2, 1); % a column vector
dy(1) = y(2);
dy(2) = 1000*(1 - y(1)^2)*y(2) - y(1);
```


ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb

For this problem, we will use the default relative and absolute tolerances (1e- 3 and 1e- 6, respectively) and solve on a time interval of [0 3000] with initial condition vector [2 0] at time 0.

```
[T, Y] = ode15s(@vdp1000, [0 3000], [2 0]);
```

Plotting the first column of the returned matrix Y versus T shows the solution

```
plot(T, Y(:, 1), '-o')
```



Algorithms

ode45 is based on an explicit Runge-Kutta (4,5) formula, the Dormand-Prince pair. It is a *one-step* solver – in computing $y(t_n)$, it needs only the solution at the immediately preceding time point, $y(t_{n-1})$. In general, ode45 is the best function to apply as a “first try” for most problems. [3]

ode23 is an implementation of an explicit Runge-Kutta (2,3) pair of Bogacki and Shampine. It may be more efficient than ode45 at crude tolerances and in the presence of moderate stiffness. Like ode45, ode23 is a one-step solver. [2]

ode113 is a variable order Adams-Basforth-Moulton PECE solver. It may be more efficient than ode45 at stringent tolerances and when the ODE file function is particularly expensive to evaluate. ode113 is a *multistep* solver – it

ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb

normally needs the solutions at several preceding time points to compute the current solution. [7]

The above algorithms are intended to solve nonstiff systems. If they appear to be unduly slow, try using one of the stiff solvers below.

ode15s is a variable order solver based on the numerical differentiation formulas (NDFs). Optionally, it uses the backward differentiation formulas (BDFs, also known as Gear's method) that are usually less efficient. Like ode113, ode15s is a multistep solver. Try ode15s when ode45 fails, or is very inefficient, and you suspect that the problem is stiff, or when solving a differential-algebraic problem. [9], [10]

ode23s is based on a modified Rosenbrock formula of order 2. Because it is a one-step solver, it may be more efficient than ode15s at crude tolerances. It can solve some kinds of stiff problems for which ode15s is not effective. [9]

ode23t is an implementation of the trapezoidal rule using a "free" interpolant. Use this solver if the problem is only moderately stiff and you need a solution without numerical damping. ode23t can solve DAEs. [10]

ode23tb is an implementation of TR-BDF2, an implicit Runge-Kutta formula with a first stage that is a trapezoidal rule step and a second stage that is a backward differentiation formula of order two. By construction, the same iteration matrix is used in evaluating both stages. Like ode23s, this solver may be more efficient than ode15s at crude tolerances. [8], [1]

See Also

deval , odeset , odeget , @ (function handle)

References

- [1] Bank, R. E., W. C. Coughran, Jr., W. Fichtner, E. Grosse, D. Rose, and R. Smith, "Transient Simulation of Silicon Devices and Circuits," *IEEE Trans. CAD*, 4 (1985), pp 436-451.
- [2] Bogacki, P. and L. F. Shampine, "A 3(2) pair of Runge-Kutta formulas," *Appl. Math. Letters*, Vol. 2, 1989, pp 1-9.
- [3] Dormand, J. R. and P. J. Prince, "A family of embedded Runge-Kutta formulae," *J. Comp. Appl. Math.*, Vol. 6, 1980, pp 19-26.
- [4] Forsythe, G. , M. Malcolm, and C. Moler, *Computer Methods for Mathematical Computations*, Prentice-Hall, New Jersey, 1977.

ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb

- [5] Kahaner, D. , C. Moler, and S. Nash, *Numerical Methods and Software*, Prentice-Hall, New Jersey, 1989.
- [6] Shampine, L. F. , *Numerical Solution of Ordinary Differential Equations*, Chapman & Hall, New York, 1994.
- [7] Shampine, L. F. and M. K. Gordon, *Computer Solution of Ordinary Differential Equations: the Initial Value Problem*, W. H. Freeman, San Francisco, 1975.
- [8] Shampine, L. F. and M. E. Hosea, "Analysis and Implementation of TR-BDF2," *Applied Numerical Mathematics 20*, 1996.
- [9] Shampine, L. F. and M. W. Reichelt, "The MATLAB ODE Suite," *SIAM Journal on Scientific Computing*, Vol. 18, 1997, pp 1-22.
- [10] Shampine, L. F., M. W. Reichelt, and J.A. Kierzenka, "Solving Index-1 DAEs in MATLAB and Simulink," *SIAM Review*, Vol. 41, 1999, pp 538-552.

odefile

Purpose	Define a differential equation problem for ordinary differential equation (ODE) solvers
----------------	---

Note This reference page describes the `odefile` and the syntax of the ODE solvers used in MATLAB, Version 5. MATLAB, Version 6, supports the `odefile` for backward compatibility, however the new solver syntax does not use an ODE file. New functionality is available only with the new syntax. For information about the new syntax, see `odeset` or any of the ODE solvers.

Description `odefile` is not a command or function. It is a help entry that describes how to create an M-file defining the system of equations to be solved. This definition is the first step in using any of MATLAB's ODE solvers. In MATLAB documentation, this M-file is referred to as an `odefile`, although you can give your M-file any name you like.

You can use the `odefile` M-file to define a system of differential equations in one of these forms

$$y' = f(t, y)$$

or

$$M(t, y)y' = f(t, y)v$$

where:

- t is a scalar independent variable, typically representing time.
- y is a vector of dependent variables.
- f is a function of t and y returning a column vector the same length as y .
- $M(t, y)$ is a time-and-state-dependent mass matrix.

The ODE file must accept the arguments t and y , although it does not have to use them. By default, the ODE file must return a column vector the same length as y .

All of the solvers of the ODE suite can solve $M(t, y)y' = f(t, y)$, except `ode23s`, which can only solve problems with constant mass matrices. The `ode15s` and

ode23t solvers can solve some differential-algebraic equations (DAEs) of the form $M(t)y' = f(t, y)$.

Beyond defining a system of differential equations, you can specify an entire initial value problem (IVP) within the ODE M-file, eliminating the need to supply time and initial value vectors at the command line (see Examples on page 2-651).

To Use the ODE File Template

- Enter the command `help odefile` to display the help entry.
- Cut and paste the ODE file text into a separate file.
- Edit the file to eliminate any cases not applicable to your IVP.
- Insert the appropriate information where indicated. The definition of the ODE system is required information.

```

switch flag
case '' % Return dy/dt = f(t, y).
    varargout{1} = f(t, y, p1, p2);
case 'init' % Return default [tspan, y0, options].
    [varargout{1:3}] = init(p1, p2);
case 'jacobian' % Return Jacobian matrix df/dy.
    varargout{1} = jacobian(t, y, p1, p2);
case 'j pattern' % Return sparsity pattern matrix S.
    varargout{1} = jpattern(t, y, p1, p2);
case 'mass' % Return mass matrix.
    varargout{1} = mass(t, y, p1, p2);
case 'events' % Return [value, isterminal, direction].
    [varargout{1:3}] = events(t, y, p1, p2);
otherwise
    error(['Unknown flag ''', flag, '''']);
end
%
function dydt = f(t, y, p1, p2)
    dydt = < Insert a function of t and/or y, p1, and p2 here. >
%
function [tspan, y0, options] = init(p1, p2)
    tspan = < Insert tspan here. >;
    y0 = < Insert y0 here. >;

```

```
options = < Insert options = odeset(...) or [] here. >;
% -----
function dfdy = j acobi an(t, y, p1, p2)
dfdy = < Insert Jacobian matrix here. >;
% -----
function S = j pattern(t, y, p1, p2)
S = < Insert Jacobian matrix sparsity pattern here. >;
% -----
function M = mass(t, y, p1, p2)
M = < Insert mass matrix here. >;
% -----
function [value, i stermin al, di recti on] = events(t, y, p1, p2)
value = < Insert event function vector here. >
i stermin al = < Insert logical ISTERMIN AL vector here. >;
di recti on = < Insert DIRECTION vector here. >;
```

Notes

- 1 The ODE file must accept *t* and *y* vectors from the ODE solvers and must return a column vector the same length as *y*. The optional input argument *flag* determines the type of output (mass matrix, Jacobian, etc.) returned by the ODE file.
- 2 The solvers repeatedly call the ODE file to evaluate the system of differential equations at various times. *This is required information* – you must define the ODE system to be solved.
- 3 The *switch* statement determines the type of output required, so that the ODE file can pass the appropriate information to the solver. (See notes 4 - 9.)
- 4 In the default *initial conditions ('init')* case, the ODE file returns basic information (time span, initial conditions, options) to the solver. If you omit this case, you must supply all the basic information on the command line.
- 5 In the '*j acobi an*' case, the ODE file returns a Jacobian matrix to the solver. You need only provide this case when you want to improve the performance of the stiff solvers *ode15s*, *ode23s*, *ode23t*, and *ode23tb*.
- 6 In the '*j pattern*' case, the ODE file returns the Jacobian sparsity pattern matrix to the solver. You need to provide this case only when you want to generate sparse Jacobian matrices numerically for a stiff solver.

- 7 In the 'mass' case, the ODE file returns a mass matrix to the solver. You need to provide this case only when you want to solve a system in the form $M(t, y)y' = f(t, y)$.
- 8 In the 'events' case, the ODE file returns to the solver the values that it needs to perform event location. When the Events property is set to on, the ODE solvers examine any elements of the event vector for transitions to, from, or through zero. If the corresponding element of the logical isTermination vector is set to 1, integration will halt when a zero-crossing is detected. The elements of the direction vector are -1, 1, or 0, specifying that the corresponding event must be decreasing, increasing, or that any crossing is to be detected.
- 9 An unrecognized flag generates an error.

Examples

The van der Pol equation, $y''_1 - \mu(1 - y_1^2)y' + y_1 = 0$, is equivalent to a system of coupled first-order differential equations.

$$\begin{aligned}y'_1 &= y_2 \\y'_2 &= \mu(1 - y_1^2)y_2 - y_1\end{aligned}$$

The M-file


```
function out1 = vdp1(t, y)
out1 = [y(2); (1-y(1)^2)*y(2) - y(1)];
```

defines this system of equations (with $\mu = 1$).

To solve the van der Pol system on the time interval [0 20] with initial values (at time 0) of $y(1) = 2$ and $y(2) = 0$, use

```
[t, y] = ode45('vdp1', [0 20], [2; 0]);
plot(t, y(:, 1), '-.', t, y(:, 2), '-.')
```

odefile



To specify the entire initial value problem (IVP) within the M-file, rewrite vdp1 as follows.

```
function [out1, out2, out3] = vdp1(t, y, flag)
if nargin < 3 | isempty(flag)
    out1 = [y(1).*(1-y(2).^2)-y(2); y(1)];
else
    switch(flag)
        case 'init' % Return tspan, y0, and options.
            out1 = [0 20];
            out2 = [2; 0];
            out3 = [];
        otherwise
            error(['Unknown request ''', flag, '''']);
        end
    end
```

You can now solve the IVP without entering any arguments from the command line.

```
[T, Y] = ode23('vdp1')
```

In this example the `ode23` function looks to the `vdp1` M-file to supply the missing arguments. Note that, once you've called `odeset` to define options, the calling syntax

```
[T, Y] = ode23('vdp1', [], [], options)
```

also works, and that any options supplied via the command line override corresponding options specified in the M-file (see `odeset`).

See Also

The MATLAB Version 5 help entries for the ODE solvers and their associated functions: `ode23`, `ode45`, `ode113`, `ode15s`, `ode23s`, `ode23t`, `ode23tb`, `odeget`, `odeset`

Type at the MATLAB command line: `more on`, `type function`, `more off`. The Version 5 help follows the Version 6 help.

odeget

Purpose	Extract properties from options structure created with odeset
Syntax	<pre>o = odeget(options, 'name') o = odeget(options, 'name', default)</pre>
Description	<p><code>o = odeget(options, 'name')</code> extracts the value of the property specified by string <code>'name'</code> from integrator options structure <code>options</code>, returning an empty matrix if the property value is not specified in <code>options</code>. It is only necessary to type the leading characters that uniquely identify the property name. Case is ignored for property names. The empty matrix <code>[]</code> is a valid <code>options</code> argument.</p> <p><code>o = odeget(options, 'name', default)</code> returns <code>o = default</code> if the named property is not specified in <code>options</code>.</p>
Example	<p>Having constructed an ODE options structure,</p> <pre>options = odeset('RelTol', 1e-4, 'AbsTol', [1e-3 2e-3 3e-3]);</pre> <p>you can view these property settings with <code>odeget</code>.</p> <pre>odeget(options, 'RelTol') ans = 1.0000e-04 odeget(options, 'AbsTol') ans = 0.0010 0.0020 0.0030</pre>

See Also

`odeset`

Purpose	Create or alter options structure for input to ordinary differential equation (ODE) solvers
Syntax	<pre>options = odeset('name1', value1, 'name2', value2, ...) options = odeset(olopts, 'name1', value1, ...) options = odeset(olopts, newopts) odeset</pre>
Description	The <code>odeset</code> function lets you adjust the integration parameters of the ODE solvers. The ODE solvers can integrate systems of differential equations of one of these forms
	$y' = f(t, y)$
	or
	$M(t, y)y' = f(t, y)$
	See below for information about the integration parameters.
	<code>options = odeset('name1', value1, 'name2', value2, ...)</code> creates an integrator options structure in which the named properties have the specified values. Any unspecified properties have default values. It is sufficient to type only the leading characters that uniquely identify a property name. Case is ignored for property names.
	<code>options = odeset(olopts, 'name1', value1, ...)</code> alters an existing options structure <code>olopts</code> .
	<code>options = odeset(olopts, newopts)</code> alters an existing options structure <code>olopts</code> by combining it with a new options structure <code>newopts</code> . Any new options not equal to the empty matrix overwrite corresponding options in <code>olopts</code> .
	<code>odeset</code> with no input arguments displays all property names as well as their possible and default values.
ODE Properties	The available properties depend on the ODE solver used. There are several categories of properties:
	<ul style="list-style-type: none"> • Error tolerance

- Solver output
- Jacobian matrix
- Event location
- Mass matrix and differential-algebraic equations (DAEs)
- Step size
- `ode15s`

Note This reference page describes the ODE properties for MATLAB, Version 6. The Version 5 properties are supported only for backward compatibility. For information on the Version 5 properties, type at the MATLAB command line: `more on`, `type odeset`, `more off`.

Error Tolerance Properties

Property	Value	Description
RelTol	Positive scalar {1e-3}	A relative error tolerance that applies to all components of the solution vector. The estimated error in each integration step satisfies $e(i) \leq \max(\text{RelTol} * \text{abs}(y(i)), \text{AbsTol}(i))$
AbsTol	Positive scalar or vector {1e-6}	The absolute error tolerance. If scalar, the tolerance applies to all components of the solution vector. Otherwise the tolerances apply to corresponding components.
NormControl	on {off}	Control error relative to norm of solution. Set this property on to request that the solvers control the error in each integration step with $\text{norm}(e) \leq \max(\text{RelTol} * \text{norm}(y), \text{AbsTol})$. By default the solvers use a more stringent component-wise error control.

Solver Output Properties

Property	Value	Description
OutputFcn	Function	Installable output function. The ODE solvers provide sample functions that you can use or modify:
	odeplot	Time series plotting (default)
	odephas2	Two-dimensional phase plane plotting
	odephas3	Three-dimensional phase plane plotting
	odeprint	Print solution as it is computed
		To create or modify an output function, see ODE Solver Output Properties in the “Differential Equations” section of the MATLAB documentation.
OutputSel	Vector of indices	Specifies the components of the solution vector that the solver passes to the output function.
Refine	Positive integer	Produces smoother output, increasing the number of output points by the specified factor. The default value is 1 in all solvers except ode45, where it is 4. Refine doesn't apply if <code>length(tspan) > 2</code> .
Stats	on {off}	Specifies whether the solver should display statistics about the computational cost of the integration.

odeset

Jacobian Matrix Properties (for ode15s, ode23s, ode23t, and ode23tb)

Property	Value	Description
Jacobi an	Function constant matrix	Jacobian function. Set this property to @FJac (if a function FJac(t, y) returns $\partial f / \partial y$) or to the constant value of $\partial f / \partial y$.
JPattern	Sparse matrix of {0,1}	Sparsity pattern. Set this property to a sparse matrix S with $S(i, j) = 1$ if component i of $f(t, y)$ depends on component j of y , and 0 otherwise.
Vectorized	on {off}	Vectorized ODE function. Set this property on to inform the stiff solver that the ODE function F is coded so that $F(t, [y_1 \ y_2 \ \dots])$ returns the vector $[F(t, y_1) \ F(t, y_2) \ \dots]$. That is, your ODE function can pass to the solver a whole array of column vectors at once. A stiff function calls your ODE function in a vectorized manner only if it is generating Jacobians numerically (the default behavior) and you have used odeset to set Vectorized to on.

Event Location Property

Property	Value	Description
Events	Function	Locate events. Set this property to @Events, where Events is the event function. See the ODE solvers for details.

Mass Matrix and DAE-Related Properties

Property	Value	Description
Mass	Constant matrix function	For problems $My' = f(t, y)$ set this property to the value of the constant mass matrix m . For problems $M(t, y)y' = f(t, y)$, set this property to @Mfun, where Mfun is a function that evaluates the mass matrix $M(t, y)$.
MStateDependence	none {weak} strong	Dependence of the mass matrix on y . Set this property to none for problems $M(t, y)y' = f(t, y)$. Both weak and strong indicate $M(t, y)$, but weak results in implicit solvers using approximations when solving algebraic equations. For use with all solvers except ode23s.
MvPattern	Sparse matrix	$\partial(M(t, y)v)/\partial y$ sparsity pattern. Set this property to a sparse matrix S with $S(i, j) = 1$ if for any k , the (i, k) component of $M(t, y)$ depends on component j of y , and 0 otherwise. For use with the ode15s, ode23t, and ode23tb solvers when MStateDependence is strong.
MassSingular	yes no {maybe}	Indicates whether the mass matrix is singular. The default value of 'maybe' causes the solver to test whether the problem is a DAE. For use with the ode15s and ode23t solvers.
InitialSlope	Vector	Consistent initial slope yp_0 , where yp_0 satisfies $M(t_0, y_0)yp_0 = f(t_0, y_0)$. For use with the ode15s and ode23t solvers when solving DAEs.

odeset

Step Size Properties

Property	Value	Description
MaxStep	Positive scalar	An upper bound on the magnitude of the step size that the solver uses. The default is one-tenth of the tspan interval.
Initial Step	Positive scalar	Suggested initial step size. The solver tries this first, but if too large an error results, the solver uses a smaller step size.

In addition there are two options that apply only to the ode15s solver.

ode15s Properties

Property	Value	Description
MaxOrder	1 2 3 4 {5}	The maximum order formula used.
BDF	on {off}	Set on to specify that ode15s should use the backward differentiation formulas (BDFs) instead of the default numerical differentiation formulas (NDFs).

See Also

`deval`, `odeget`, `ode45`, `ode23`, `ode23t`, `ode23tb`, `ode113`, `ode15s`, `ode23s`,
`@ (function handle)`

Purpose	Create an array of all ones
Syntax	$Y = \text{ones}(n)$ $Y = \text{ones}(m, n)$ $Y = \text{ones}([m\ n])$ $Y = \text{ones}(d_1, d_2, d_3, \dots)$ $Y = \text{ones}([d_1\ d_2\ d_3, \dots])$ $Y = \text{ones}(\text{size}(A))$
Description	$Y = \text{ones}(n)$ returns an n -by- n matrix of 1s. An error message appears if n is not a scalar. $Y = \text{ones}(m, n)$ or $Y = \text{ones}([m\ n])$ returns an m -by- n matrix of ones. $Y = \text{ones}(d_1, d_2, d_3, \dots)$ or $Y = \text{ones}([d_1\ d_2\ d_3, \dots])$ returns an array of 1s with dimensions d_1 -by- d_2 -by- d_3 -by-.... $Y = \text{ones}(\text{size}(A))$ returns an array of 1s that is the same size as A .
See Also	eye , rand , randn , zeros

open

Purpose	Open files based on extension
Syntax	<code>open(' name')</code>
Description	<code>open(' name')</code> opens the object specified by the string, <code>name</code> . The specific action taken upon opening depends on the type of object specified by <code>name</code> .

name	Action
Variable	Open array <code>name</code> in the Array Editor (the array must be numeric)
M-file (<code>name.m</code>)	Open M-file <code>name</code> in M-file Editor
Model (<code>name.mdl</code>)	Open model <code>name</code> in Simulink
MAT-file (<code>name.mat</code>)	Open MAT-file and store variables in a structure in the workspace
Figure file (*.fig)	Open figure in a figure window
P-file (<code>name.p</code>)	Open the corresponding M-file, <code>name.m</code> , if it exists, in the M-file Editor
HTML file (*.html)	Open HTML document in Help browser
Other extensions (<code>name.xxx</code>)	Open <code>name.xxx</code> by calling the helper function <code>openxxx</code> , where <code>openxxx</code> is a user-defined function

If more than one file with the specified filename, `name`, exists on the MATLAB path, then `open` opens the file returned by `which('name')`.

If the `name` specification does not include a file extension, then:

- 1 `open` checks to see if a variable by that name exists and, if it does, opens the variable in the Array Editor.
- 2 If no such variable exists, then `open` checks to see if there is a `.mdl` or `.m` file by that name on the path and, if there is, opens the file returned by `which('name')`.
- 3 If no such file exists, then `open` displays an error message.

You can create your own openxxx functions to set up handlers for new file types. `open('filename. xxx')` calls the openxxx function it finds on the path. For example, create a function, `openl og`, if you want a handler for opening files with file extension, `.log`.

Examples

Example 1 - Opening a File on the Path

To open the M-file, `copyfile.m`, type

```
open copyfile.m
```

MATLAB opens the `copyfile.m` file that resides in `toolbox\matlab\general`. If you have a `copyfile.m` file in a directory that is before `toolbox\matlab\general` on the MATLAB path, then `open` opens that file instead.

Example 2 - Opening a File Not on the Path

To open a file that is not on the MATLAB path, enter the complete file specification. If no such file is found, then MATLAB displays an error message.

```
open('D:\temp\data.mat')
```

Example 3 - Specifying a File Without a File Extension

When you specify a file without including its file extension, MATLAB determines which file to open for you. It does this by calling `which('filename')`.

In this example, `open matri xdemos` could open either an M-file or a Simulink model of the same name, since both exist on the path.

```
dir matri xdemos.*
```

```
matri xdemos.m      matri xdemos.mdl
```

As the call, `which('matri xdemos')`, returns the name of the Simulink model, `open` opens the `matri xdemos` model rather than the M-file of that name.

```
open matri xdemos      % Opens model matri xdemos.mdl
```

open

Example 4 - Opening a MAT File

This example opens a MAT-file containing MATLAB data and then keeps just one of the variables from that file. The others are overwritten when ans is reused by MATLAB.

```
% Open a MAT-file containing miscellaneous data.  
open D:\temp\data.mat
```

```
ans =
```

```
x: [3x2x2 double]  
y: {4x5 cell}  
k: 8  
spArray: [5x5 sparse]  
dblArray: [4x1 java.lang.Double[]]  
strArray: {2x5 cell}
```

```
% Keep the dblArray value by assigning it to a variable.  
dbl = ans dblArray
```

```
dbl =
```

```
java.lang.Double[][]:  
[ 5.7200] [ 6.7200] [ 7.7200]  
[10.4400] [11.4400] [12.4400]  
[15.1600] [16.1600] [17.1600]  
[19.8800] [20.8800] [21.8800]
```

Example 5 - Using a User-Defined Handler Function

If you create an M-file function called opencht to handle files with extension .cht, and then issue the command

```
open myfigure.cht
```

open will call your handler function with the following syntax.

```
opencht('myfigure.cht')
```

See Also

load, save, saveas, which, file_formats, path


Purpose	Open new copy or raise existing copy of saved figure
Syntax	<pre>openfig('filename.fig', 'new') openfig('filename.fig', 'reuse') openfig('filename.fig') figure_handle = openfig(...)</pre>
Description	<p>openfig is designed for use with GUI figures. Use this function to:</p> <ul style="list-style-type: none">• Open the FIG-file creating the GUI and ensure it is displayed on screen. This provides compatibility with different screen sizes and resolutions.• Control whether MATLAB displays one or multiple instances of the GUI at any given time.• Return the handle of the figure created, which is typically hidden for GUIs figures. <p>openfig('filename.fig', 'new') opens the figure contained in the FIG-file, <i>filename.fig</i>, and ensures it is visible and positioned completely on screen. You do not have to specify the full path to the FIG-file as long as it is on your MATLAB path. The .fig extension is optional.</p> <p>openfig('filename.fig', 'reuse') opens the figure contained in the FIG-file only if a copy is not currently open; otherwise openfig brings the existing copy forward, making sure it is still visible and completely on screen.</p> <p>openfig('filename.fig') is the same as openfig('filename.fig', 'new').</p> <p>figure_handle = openfig(...) returns the handle to the figure.</p>
Remarks	If the FIG-file contains an invisible figure, openfig returns its handle and leaves it invisible. The caller should make the figure visible when appropriate.
See Also	guide, guidelies, movegui, open, hgload, save

opengl

Purpose	Change automatic selection mode of OpenGL rendering
Syntax	<code>opengl <i>selection_mode</i></code>
Description	The OpenGL autoselection mode applies when the <code>RendererMode</code> of the figure is <code>auto</code> . Possible values for <i>selection_mode</i> are:
	<ul style="list-style-type: none">• <code>autoselect</code> allows OpenGL to be automatically selected if OpenGL is available and if there is graphics hardware on the host machine.• <code>neverselect</code> disables auto selection of OpenGL.• <code>advise</code> prints a message to the command window if OpenGL rendering is advised, but <code>RendererMode</code> is set to <code>manual</code>.
	<code>opengl</code> , by itself, returns the current auto selection state.
	<code>opengl info</code> prints information with the version and vendor of the OpenGL on your system.
	Note that the auto selection state only specifies that OpenGL should or not be considered for rendering, it does not explicitly set the rendering to OpenGL. This can be done by setting the <code>Renderer</code> property of figure to <code>OpenGL</code> . For example,

```
set(gcf, 'Renderer', 'OpenGL')
```

Purpose	Open workspace variable in the Array Editor for graphical editing
Graphical Interface	As an alternative to the openvar function, double-click on a variable in the Workspace browser.
Syntax	<code>openvar('name')</code>
Description	<code>openvar('name')</code> opens the workspace variable name in the Array Editor for graphical debugging. The array must be numeric.



See Also [load](#), [save](#), [workspace](#)

optimget

Purpose	Get optimization options structure parameter values
Syntax	<pre>val = optimget(options, 'param') val = optimget(options, 'param', default)</pre>
Description	<p><code>val = optimget(options, 'param')</code> returns the value of the specified parameter in the optimization options structure <code>options</code>. You need to type only enough leading characters to define the parameter name uniquely. Case is ignored for parameter names.</p> <p><code>val = optimget(options, 'param', default)</code> returns <code>default</code> if the specified parameter is not defined in the optimization options structure <code>options</code>. Note that this form of the function is used primarily by other optimization functions.</p>
Examples	<p>This statement returns the value of the <code>Display</code> optimization options parameter in the structure called <code>my_options</code>.</p> <pre>val = optimget(my_options, 'Display')</pre> <p>This statement returns the value of the <code>Display</code> optimization options parameter in the structure called <code>my_options</code> (as in the previous example) except that if the <code>Display</code> parameter is not defined, it returns the value '<code>final</code>'.</p> <pre>optnew = optimget(my_options, 'Display', 'final');</pre>
See Also	<code>optimset</code> , <code>fminbnd</code> , <code>fminsearch</code> , <code>fzero</code> , <code>lsqnonneg</code>

Purpose	Create or edit optimization options parameter structure
Syntax	<pre>options = optimset('param1', value1, 'param2', value2, ...) optimset options = optimset options = optimset(optimfun) options = optimset(ol dopts, 'param1', value1, ...) options = optimset(ol dopts, newopts)</pre>
Description	<p><code>options = optimset('param1', value1, 'param2', value2, ...)</code> creates an optimization options structure called <code>options</code>, in which the specified parameters (<code>param</code>) have specified values. Any unspecified parameters are set to <code>[]</code> (parameters with value <code>[]</code> indicate to use the default value for that parameter when <code>options</code> is passed to the optimization function). It is sufficient to type only enough leading characters to define the parameter name uniquely. Case is ignored for parameter names.</p> <p><code>optimset</code> with no input or output arguments displays a complete list of parameters with their valid values.</p> <p><code>options = optimset</code> (with no input arguments) creates an options structure <code>options</code> where all fields are set to <code>[]</code>.</p> <p><code>options = optimset(optimfun)</code> creates an options structure <code>options</code> with all parameter names and default values relevant to the optimization function <code>optimfun</code>.</p> <p><code>options = optimset(ol dopts, 'param1', value1, ...)</code> creates a copy of <code>ol dopts</code>, modifying the specified parameters with the specified values.</p> <p><code>options = optimset(ol dopts, newopts)</code> combines an existing options structure <code>ol dopts</code> with a new options structure <code>newopts</code>. Any parameters in <code>newopts</code> with nonempty values overwrite the corresponding old parameters in <code>ol dopts</code>.</p>

optimset

Parameters

Optimization parameters used by MATLAB functions and Optimization Toolbox functions:

Parameter	Value	Description
Display	'off' 'iter' 'final' 'notify'	Level of display. 'off' displays no output; 'iter' displays output at each iteration; 'final' displays just the final output; 'notify' displays output only if the function does not converge.
MaxFunEvals	positive integer	Maximum number of function evaluations allowed.
MaxIter	positive integer	Maximum number of iterations allowed.
TolFun	positive scalar	Termination tolerance on the function value.
TolX	positive scalar	Termination tolerance on x .

Optimization parameters used by Optimization Toolbox functions (for more information about individual parameters, see “Optimization Options Parameters” in the *Optimization Toolbox User’s Guide*, and the optimization functions that use these parameters).

Property	Value	Description
DerivativeCheck	'on' {'off'}	Compare user-supplied analytic derivatives (gradients or Jacobian) to finite differencing derivatives.
Diagnostics	'on' {'off'}	Print diagnostic information about the function to be minimized or solved.
DiffMaxChange	positive scalar {1e- 1}	Maximum change in variables for finite difference derivatives.

Property	Value	Description
DiffMinChange	positive scalar {1e-8}	Minimum change in variables for finite difference derivatives.
GoalsExactAchieve	positive scalar integer {0}	Number of goals to achieve exactly (do not over- or underachieve).
GradConstr	'on' {'off'}	Gradients for nonlinear constraints defined by the user.
GradObj	'on' {'off'}	Gradient(s) for objective function(s) defined by the user.
Hessian	'on' {'off'}	Hessian for the objective function defined by the user.
HessMult	function {[]}	Hessian multiply function defined by the user.
HessPattern	sparse matrix {sparse matrix of all ones}	Sparsity pattern of the Hessian for finite differencing. The size of the matrix is n-by-n, where n is the number of elements in x0, the starting point.
HessUpdate	{'bfgs' 'dfp' 'gillmurray' 'steepdesc'}	Quasi-Newton updating scheme.
Jacobian	'on' {'off'}	Jacobian for the objective function defined by the user.
JacobMult	function {[]}	Jacobian multiply function defined by the user.
JacobPattern	sparse matrix {sparse matrix of all ones}	Sparsity pattern of the Jacobian for finite differencing. The size of the matrix is m-by-n, where m is the number of values in the first argument returned by the user-specified function fun, and n is the number of elements in x0, the starting point.

optimset

Property	Value	Description
LargeScale	{'on'} 'off'	Use large-scale algorithm if possible.
LevenbergMarquardt	'on' {'off'}	Chooses Levenberg-Marquardt over Gauss-Newton algorithm.
LineSearchType	'cubic' {'quadcubic'}	Line search algorithm choice.
MaxPCGIter	positive integer	Maximum number of PCG iterations allowed. The default is the greater of 1 and $\text{floor}(n/2)$ where n is the number of elements in x_0 , the starting point.
MeritFunction	'singleobj' {'multiobj'}	Use goal attainment/minimax merit function (multiobjective) vs. fmincon (single objective).
MinAbsMax	positive scalar integer {0}	Number of $F(x)$ to minimize the worst case absolute values
PrecondBandWidth	positive integer {0} Inf	Upper bandwidth of preconditioner for PCG.
TolCon	positive scalar	Termination tolerance on the constraint violation.
TolPCG	positive scalar {0.1}	Termination tolerance on the PCG iteration.
TypicalX	vector of all ones	Typical x values. The length of the vector is equal to the number of elements in x_0 , the starting point.

Examples

This statement creates an optimization options structure called `options` in which the `Display` parameter is set to `'iter'` and the `TolFun` parameter is set to `1e-8`.

```
options = optimset('Display', 'iter', 'TolFun', 1e-8)
```

This statement makes a copy of the `options` structure called `options`, changing the value of the `TolX` parameter and storing new values in `optnew`.

```
optnew = optimset(options, 'TolX', 1e-4);
```

This statement returns an optimization options structure that contains all the parameter names and default values relevant to the function fminbnd.

```
optimset('fminbnd')
```

See Also

[optimget](#), [fminbnd](#), [fminsearch](#), [fzero](#), [lsqnonneg](#)

orient

Purpose	Set paper orientation for printed output
Syntax	<code>orient</code> <code>orient landscape</code> <code>orient portrait</code> <code>orient tall</code> <code>orient(<i>fig_handle</i>)</code> , <code>orient(<i>simulink_model</i>)</code> <code>orient(<i>fig_handle</i>, <i>orientation</i>)</code> , <code>orient(<i>simulink_model</i>, <i>orientation</i>)</code>
Description	<code>orient</code> returns a string with the current paper orientation, either <code>portrait</code> , <code>landscape</code> , or <code>tall</code> . <code>orient landscape</code> sets the paper orientation of the current figure to full-page landscape, orienting the longest page dimension horizontally. The figure is centered on the page and scaled to fit the page with a 0.25 inch border. <code>orient portrait</code> sets the paper orientation of the current figure to portrait, orienting the longest page dimension vertically. The <code>portrait</code> option returns the page orientation to MATLAB's default. (Note that the result of using the <code>portrait</code> option is affected by changes you make to figure properties. See the "Algorithm" section for more specific information.) <code>orient tall</code> maps the current figure to the entire page in portrait orientation, leaving a 0.25 inch border. <code>orient(<i>fig_handle</i>)</code> , <code>orient(<i>simulink_model</i>)</code> returns the current orientation of the specified figure or Simulink model. <code>orient(<i>fig_handle</i>, <i>orientation</i>)</code> , <code>orient(<i>simulink_model</i>, <i>orientation</i>)</code> sets the orientation for the specified figure or Simulink model to the specified orientation (<code>landscape</code> , <code>portrait</code> , or <code>tall</code>).
Algorithm	<code>orient</code> sets the <code>PaperOrientation</code> , <code>PaperPosition</code> , and <code>PaperUnits</code> properties of the current figure. Subsequent print operations use these properties. The result of using the <code>portrait</code> option can be affected by default property values as follows: <ul style="list-style-type: none">• If the current figure <code>PaperType</code> is the same as the default figure <code>PaperType</code> and the default figure <code>PaperOrientation</code> has been set to <code>landscape</code>, then

the `orient portrait` command uses the current values of `PaperOrientation` and `PaperPosition` to place the figure on the page.

- If the current figure `PaperType` is the same as the default figure `PaperType` and the default figure `PaperOrientation` has been set to `Landscape`, then the `orient portrait` command uses the default figure `PaperPosition` with the `x`, `y` and `width`, `height` values reversed (i.e., `[y,x,height,width]`) to position the figure on the page.
- If the current figure `PaperType` is different from the default figure `PaperType`, then the `orient portrait` command uses the current figure `PaperPosition` with the `x`, `y` and `width`, `height` values reversed (i.e., `[y,x,height,width]`) to position the figure on the page.

See Also

`print`, `set`

`PaperOrientation`, `PaperPosition`, `PaperSize`, `PaperType`, and `PaperUnits` properties of figure graphics objects.

orth

Purpose	Range space of a matrix
Syntax	<code>B = orth(A)</code>
Description	<code>B = orth(A)</code> returns an orthonormal basis for the range of A. The columns of B span the same space as the columns of A, and the columns of B are orthogonal, so that $B' * B = eye(rank(A))$. The number of columns of B is the rank of A.
See Also	<code>nul1</code> , <code>svd</code> , <code>rank</code>

Purpose	Default part of switch statement
Description	otherwise is part of the switch statement syntax, which allows for conditional execution. The statements following otherwise are executed only if none of the preceding case expressions (case_expr) match the switch expression (sw_expr).
Examples	The general form of the switch statement is:
	<pre>switch sw_expr case case_expr statement statement case { case_expr1, case_expr2, case_expr3} statement statement otherwise statement statement end</pre>

See switch for more details.

See Also [switch](#)

otherwise

Numerics

1-norm 2-628
2-norm (estimate of) 2-629

A

ActiveX

object methods
 get 2-226
 invoke 2-403
 load 2-516
 move 2-600

Adams-Basforth-Moulton ODE solver 2-645

aligning scattered data

 multi-dimensional 2-617
 two-dimensional 2-252

alpha channel 2-349

AlphaData

 image property 2-330

AlphaDataMapping

 image property 2-330

anti-diagonal 2-269

arguments, M-file

 checking number of input 2-612
 number of input 2-613
 number of output 2-613

array

 finding indices of 2-88
 maximum elements of 2-568
 mean elements of 2-569
 median elements of 2-570
 minimum elements of 2-587
 of all ones 2-661
 structure 2-34, 2-232
 swapping dimensions of 2-404

arrays

 detecting empty 2-413

opening 2-662
ASCII data
 reading from disk 2-514
audio
 signal conversion 2-489, 2-609
autoselection of OpenGL 2-63
average of array elements 2-569
axis crossing *See* zero of a function

B

BackingStore, Figure property 2-45

base two operations

 logarithm 2-522
 next power of two 2-622

big endian formats 2-128

binary

 data
 writing to file 2-184
 files
 reading 2-154
 mode for opened files 2-128

binary data

 reading from disk 2-514

bisection search 2-191

bit depth 2-351

 querying 2-343

 support

*<it>*See also index entries for individual file
 formats

 supported bit depths 2-351

BMP 2-342, 2-348, 2-355

 bit depths supported when writing 2-359

browser

 for help 2-291

BusyAction

- F**
- Figure property 2-46
 - Image property 2-330
 - Light property 2-482
 - Line property 2-497
- B**
- ButtonDownFcn
 - Figure property 2-46
 - Image property 2-331
 - Light property 2-482
 - Line property 2-497
- C**
- case
 - upper to lower 2-531
 - CData
 - Image property 2-331
 - CDatamapping
 - Image property 2-333
 - cell array
 - conversion to from numeric array 2-633
 - characters
 - conversion, in format specification string 2-142
 - escape, in format specification string 2-143
 - Children
 - Figure property 2-46
 - Image property 2-333
 - Light property 2-482
 - Line property 2-497
 - class, object *See* object classes
 - classes
 - field names 2-34
 - loaded 2-369
 - Clipping
 - Figure property 2-46
 - Image property 2-333
 - Light property 2-482
- L**
- Line property 2-497
- C**
- CloseRequestFcn, Figure property 2-46
 - closing
 - files 2-13
 - Color
 - Figure property 2-48
 - Light property 2-482
 - Line property 2-498
 - Colormap, Figure property 2-48
 - combinations of n elements 2-616
 - combs **2-616**
 - command syntax 2-288
 - Command Window
 - cursor position 2-309
 - commands
 - help for 2-288, 2-295
 - common elements *See* set operations, intersection
 - complex
 - logarithm 2-521, 2-523
 - numbers 2-313
 - See also* imaginary
 - contents.m file 2-288
 - conversion
 - hexadecimal to decimal 2-298
 - hexadecimal to double precision 2-299
 - integer to string 2-379
 - matrix to string 2-554
 - numeric array to cell array 2-633
 - numeric array to logical array 2-524
 - numeric array to string 2-634
 - uppercase to lowercase 2-531
 - conversion characters in format specification string 2-142
 - covariance
 - least squares solution and 2-533
 - CreateFcn
 - Figure property 2-49

Image property 2-334
Light property 2-483
Line property 2-498
creating your own MATLAB functions 2-177
cubic interpolation 2-386
 piecewise Hermite 2-381
cubic spline interpolation 2-381, 2-386, 2-389, 2-392
CurrentAxes 2-49
CurrentAxes, Figure property 2-49
CurrentCharacter, Figure property 2-49
CurrentMenu, Figure property (obsolete) 2-49
CurrentObject, Figure property 2-50
CurrentPoint
 Figure property 2-50
cursor images 2-351
cursor position 2-309

D

data

ASCII
 reading from disk 2-514
binary
 writing to file 2-184
formatted
 reading from files 2-166
 writing to file 2-141
formatting 2-141
isosurface from volume data 2-438
 reading binary from disk 2-514
data, aligning scattered
 multi-dimensional 2-617
 two-dimensional 2-252
debugging
 M-files 2-462
Del eteFcn

Figure property 2-51
Image property 2-334
Light property 2-483
Del eteFcn, line property 2-498
density
 of sparse matrix 2-625
Detect 2-405
detecting
 alphabetic characters 2-424
 empty arrays 2-413
 equal arrays 2-414
 finite numbers 2-416
 global variables 2-417
 infinite elements 2-420
 logical arrays 2-425
 members of a set 2-426
 NaNs 2-427
 objects of a given class 2-407
 prime numbers 2-442
 real numbers 2-443
 sparse matrix 2-447
diagonal
 anti- 2-269
dialog box
 help 2-293
 input 2-372
 list 2-512
 message 2-608
differential equation solvers
 defining an ODE problem 2-648
 ODE initial value problems 2-638
 adjusting parameters of 2-655
 extracting properties of 2-654
Diophantine equations 2-218
directories
 creating 2-593
 listing, on UNIX 2-532

directory
 root 2-567

discontinuous problems 2-126

display format 2-134

displaying output in Command Window 2-599

`Di thermap` 2-51

`Di thermap`, Figure property 2-51

`Di thermapMode`, Figure property 2-51

division
 by zero 2-363
 modulo 2-598

divisor
 greatest common 2-218

documentation
 displaying online 2-291

double click, detecting 2-65

`DoubleBuffer`, Figure property 2-52

dual vector 2-623

E

eigenvalue
 matrix logarithm and 2-527
 multiple 2-182

end caps for isosurfaces 2-430

end-of-file indicator 2-17

`EraseMode`
 Image property 2-334
 Line property 2-498

error
 catching 2-465
 roundoff *See* roundoff error

error message
 `Index into matrix is negative or zero`
 2-524
 retrieving last generated 2-465

errors

 in file input/output 2-18

escape characters in format specification string
 2-143

examples
 calculating isosurface normals 2-436
 isosurface end caps 2-430
 isosurfaces 2-439
 executing statements repeatedly 2-132

extension, filename
 `.m` 2-177

F

`factor` **2-11**

`factorial` **2-12**

factorization
 LU 2-540

factors, prime 2-11

`fclose` **2-13**

`fclose`
 serial port I/O 2-14

`feather` 2-15

`feof` **2-17**

`ferror` **2-18**

`feval` **2-19**

`fft` **2-21**

FFT *See* Fourier transform

`fft2` **2-25**

`fftn` **2-26**

`fftshift` **2-27**

FFTW 2-23

`fgetl` **2-28**

`fgetl`
 serial port I/O 2-29

`fgets` **2-31**

`fgets`
 serial port I/O 2-32

field names of a structure, obtaining 2-34
 fields, noncontiguous, inserting data into 2-184
fig files 2-151
figflag 2-35
Figure
 creating 2-36
 defining default properties 2-37
 properties 2-45
figure 2-36
 figure windows, displaying 2-91
figures
 opening 2-662
file
 extension, getting 2-78
 position indicator
 finding 2-173
 setting 2-172
 setting to start of file 2-165
file formats 2-348, 2-354
file size
 querying 2-343
filebrowser 2-71
filename
 building from parts 2-175
 parts 2-78
filename extension
 .m 2-177
filereparts 2-78, 2-95
files
 beginning of, rewinding to 2-165, 2-347
 closing 2-13
 end of, testing for 2-17
 errors in input or output 2-18
fig 2-151
 finding position within 2-173
 getting next line 2-28
 getting next line (with line terminator) 2-31
 MAT 2-515
 mode when opened 2-128
 opening 2-128, 2-662
 path, getting 2-78
 reading
 binary 2-154
 formatted 2-166
 reading image data from 2-348
 rewinding to beginning of 2-165, 2-347
 setting position within 2-172
 startup 2-566
 version, getting 2-78
 writing binary data to 2-184
 writing formatted data to 2-141
 writing image data to 2-354
 See also file
filesep 2-79
fill 2-80
fill3 2-82
filter 2-85
filter 2-85
filter2 2-87
find 2-88
findfis 2-91
finding
 indices of arrays 2-88
 zero of a function 2-189
 See also detecting
findobj 2-92
finite numbers
 detecting 2-416
FIR filter *See* **filter**
fitsinfo 2-96
fitsread 2-104
fix 2-106
FixedColors, Figure property 2-52
flints 2-609

fli pdim **2-107**
fli plr **2-108**
fli pud **2-109**
floor **2-111**
flops **2-112**
flow control
 for 2-132
 keyboard 2-462
 otherwise 2-677
fmin **2-114**
fminbnd **2-117**
fmins **2-120**
fminsearch 2-123
F-norm 2-628
fopen **2-127**
fopen
 serial port I/O 2- 130
for **2-132**
format
 precision when writing 2-154
 reading files 2-166
format **2-134**
formats
 big endian 2-128
 little endian 2-128
formatted data
 reading from file 2-166
 writing to file 2-141
Fourier transform
 algorithm, optimal performance of 2-23, 2-317,
 2-318, 2-622
 discrete, n-dimensional 2-26
 discrete, one-dimensional 2-21
 discrete, two-dimensional 2-25
 fast 2-21
 as method of interpolation 2-391
 inverse, n-dimensional 2-319
 inverse, one-dimensional 2-317
 inverse, two-dimensional 2-318
 shifting the zero-frequency component of 2-27
fplot 2-137
fprintf **2-141**
fprintf
 serial port I/O 2- 147
frame2im 2-150
frames for printing 2-151
fread **2-154**
fread
 serial port I/O 2- 159
freeserial 2- 163
freqspace **2-164**
freqspace **2-164**
frequency response
 desired response matrix
 frequency spacing 2-164
frequency vector 2-529
frewind **2-165**
fscanf **2-166**
fscanf
 serial port I/O 2- 169
fseek **2-172**
ftell **2-173**
full **2-174**
fullfile 2-175
function
 minimizing (several variables) 2-120
 minimizing (single variable) 2-114
function **2-177, 2-181**
function syntax 2-288
functions
 finding using keywords 2-530
 help for 2-288, 2-295
 in memory 2-369
funm **2-182**

fwrite **2-184**
fwrite
 serial port I/O 2- 185
fzero **2-189**

G
gallery **2-193**
gamma **2-213**
gamma function
 (defined) 2-213
 incomplete 2-213
 logarithm of 2-213
gammainc **2-213**
gammaln **2-213**
Gaussian elimination
 (as algorithm for solving linear equations) 2-399
 LU factorization and 2-540
gca 2-215
gcbo 2-217
gcd **2-218**
gcf 2-220
gco 2-221
get 2-224, **2-226**
get
 serial port I/O 2- 228
getenv **2-231**
getfield **2-232**
getframe 2-234
gnput 2-237
global **2-238**
global variable
 defining 2-238
gmres **2-240**
gplot 2-245
gradient **2-247**

gradient, numerical 2-247
graphics objects
 Figure 2-36
 getting properties 2-224
 Image 2-323
 Light 2-478
 Line 2-490
graymon 2-250
greatest common divisor 2-218
grid
 aligning data to a 2-252
grid 2-251
grid arrays
 for volumetric plots 2-577
 multi-dimensional 2-617
griddata **2-252**
griddata3 **2-255**
griddataan **2-256**
gsvd **2-258**
gtext 2-263

H
H1 line 2-289
hadamard **2-268**
Hadamard matrix 2-268
Handleability
 Figure property 2-53
 Image property 2-335
 Light property 2-483
 Line property 2-499
hankel **2-269**
Hankel matrix 2-269
HDF 2-342, 2-348, 2-355
 appending to when saving (*WriteMode*) 2-355
 bit depths supported when writing 2-359
 compression 2-355

reading with special `imread` syntax 2-351
setting JPEG quality when writing 2-355
hdf 2-270
hdfinfo 2-272
hdfread 2-279
help
 contents file 2-288
 creating for M-files 2-289
 keyword search in functions 2-530
 online 2-288
help 2-288
Help browser 2-291
Help Window 2-295
helpbrowser 2-291
helppdesk 2-292
helpdlg 2-293
helpwin 2-295
Hermite transformations, elementary 2-218
hess 2-296
Hessenberg form of a matrix 2-296
hex2dec 2-298
hex2num 2-299
hiddens 2-302
hilb 2-303
Hilbert matrix 2-303
 inverse 2-402
hist 2-304
histc 2-307
HistTest
 Figure property 2-54
 Image property 2-336
 Light property 2-484
 Line property 2-499
hold 2-308
home 2-309
horzcat 2-310
hsv2rgb 2-312

HTML browser
 in MATLAB 2-291
I
i 2-313
icon images 2-351
if 2-314
ifft 2-317
ifft2 2-318
ifftn 2-319
ifftshift 2-320
IIR filter *See* filter
imag 2-322
Image
 creating 2-323
 defining default properties 2-327
 properties 2-330
image 2-323
image types
 querying 2-343
images
 file formats 2-348, 2-354
 reading data from files 2-348
 returning information about 2-342
 writing to files 2-354
imagedesc 2-339
imaginary
 part of complex number 2-322
 parts of inverse FFT 2-317, 2-318
 unit ($\sqrt{-1}$) 2-313, 2-454
 See also complex
imfinfo
 returning file information 2-342
import 2-345
importdata 2-347
importing

Java class and package names 2-345
imread 2-348
imwrit**e** **2-354**, 2-354
incomplete
 gamma function (defined) 2-213
ind2sub **2-362**
Index **i**nto **m**atrix **i**s **n**egative or **z**ero (error
 message) 2-524
indexing
 logical 2-524
indicator of file position 2-165
indices, array
 finding 2-88
Inf **2-363**
inferior to **2-364**
infinite elements
 detecting 2-420
infinity 2-363
 norm 2-628
info **2-365**
information
 returning file information 2-342
inline **2-366**
inolygon **2-370**
input
 checking number of M-file arguments 2-612
 name of array passed as 2-374
 number of M-file arguments 2-613
 prompting users for 2-371, 2-572
input **2-371**
inputdlg 2-372
installation, root directory of 2-567
instrcalback 2-376
instrfind 2-377
int2str **2-379**
int8, **i**nt16, **i**nt32 **2-380**
interp**1** **2-381**
interp2 **2-386**
interp3 **2-389**
interpft **2-391**
interpn **2-392**
interpolation
 one-dimensional 2-381
 two-dimensional 2-386
 three-dimensional 2-389
 multidimensional 2-392
 cubic method 2-252, 2-381, 2-386, 2-389, 2-392
 cubic spline method 2-381
 FFT method 2-391
 linear method 2-381, 2-386
 nearest neighbor method 2-252, 2-381, 2-386,
 2-389, 2-392
 trilinear method 2-252, 2-389, 2-392
interpreter, MATLAB
 search algorithm of 2-178
interpstreamspeed 2-394
Interruptible
 Figure property 2-54
 Image property 2-336
 Light property 2-484
 Line property 2-500
intersect **2-398**
inv **2-399**
inverse
 Fourier transform 2-317, 2-318, 2-319
 Hilbert matrix 2-402
 of a matrix 2-399
InvertHardCopy, Figure property 2-54
invhilb **2-402**
invoke 2-403
ipermute **2-404**
is* **2-405**
isa **2-407**
iscell **2-410**

iscellstr **2-411**

ischar **2-412**

isempty **2-413**

isequal **2-414**

isfield **2-415**

isfinite **2-416**

isglobal **2-417**

ishandle **2-418**

ishold **2-419**

isnanf **2-420**

isletter **2-424**

islogical **2-425**

ismember **2-426**

isnan **2-427**

isnumeric **2-428**

isobject **2-429**

isocap **2-430**

isonormal **s** **2-436**

isosurface

calculate data from volume **2-438**

end caps **2-430**

vertex normals **2-436**

isosurface **2-438**

ispprime **2-442**

isreal **2-443**

isspace **2-446**

issparse **2-447**

isstruct **2-449**

isstudent **2-450**

isunifx **2-451**

isvali d **2-452**

isvarname **2-453**

J

j **2-454**

Java

class names **2-345**

objects **2-421**, **2-441**

Java import list

adding to **2-345**

java_method **2-176**, **2-455**, **2-458**, **2-581**

java_object **2-460**

javachk **2-456**

javax. comm **2-163**

JPEG files **2-342**, **2-348**, **2-355**

bit depths supported when writing **2-359**

parameters that can be set when writing **2-356**

JPEG quality

setting when writing a JPEG image **2-356**

setting when writing an HDF image **2-355**

K

K>> prompt **2-462**

keyboard **2-462**

keyboard mode **2-462**

KeyPressFcn, **Figure** property **2-55**

keyword search in functions **2-530**

kron **2-463**

Kronecker tensor product **2-463**

L

labeling

plots (with numeric values) **2-634**

largest array elements **2-568**

lasterr **2-465**

lastwarn **2-467**

Layout Editor

starting **2-266**

lcm **2-468**

least common multiple **2-468**

least squares

problem 2-533
problem, nonnegative 2-623
legend 2-469
legendre **2-473**
 Legendre functions
 (defined) 2-473
 Schmidt semi-normalized 2-473
length **2-475**
length
 serial port I/O 2-476
license 2-477
Light
 creating 2-478
 defining default properties 2-479
 properties 2-482
light 2-478
Light object
 positioning in spherical coordinates 2-487
lightangle 2-487
lighting 2-488
Line
 creating 2-490
 defining default properties 2-493
 properties 2-497
line 2-490
linear audio signal 2-489, 2-609
linear equation systems, methods for solving
 least squares 2-623
 matrix inversion (inaccuracy of) 2-399
linear interpolation 2-381, 2-386
linearly spaced vectors, creating 2-511
LineSpec 2-505
LineStyle
 Line property 2-501
LineWidth
 Line property 2-501
linspace **2-511**
listdlg 2-512
little endian formats 2-128
load **2-514, 2-516**
load
 serial port I/O 2-517
loadobj **2-519**
local variables 2-177, 2-238
locking M-files 2-597
log **2-521**
log10 [**log10**] **2-523**
log2 **2-522**
logarithm
 base ten 2-523
 base two 2-522
 complex 2-521, 2-523
 matrix (natural) 2-527
 natural 2-521
 of gamma function (natural) 2-213
 plotting 2-525
 logarithmically spaced vectors, creating 2-529
logical **2-524**
logical array
 converting numeric array to 2-524
 detecting 2-425
logical indexing 2-524
logical tests
 See also detecting
loglog 2-525
logm **2-527**
logspace **2-529**
lookfor 2-530
lower **2-531**
ls **2-532**
lscov **2-533**
lsqnonneg 2-534
lsqr **2-537**
lu **2-540**

LU factorization 2-540
storage requirements of (sparse) 2-637

l ui nc 2-544

M

magic 2-551
magic squares 2-551
Marker
Line property 2-501
MarkerEdgeColor
Line property 2-502
MarkerFaceColor
Line property 2-502
MarkerSize
Line property 2-502
mat2str 2-554
material 2-555
MAT-files 2-514
MATLAB
installation directory 2-567
startup 2-566
matlab 2-557
MATLAB interpreter
search algorithm of 2-178
matlab.mat 2-514
matlabrc 2-566
matlabroot 2-567
matrix
converting to formatted data file 2-141
detecting sparse 2-447
evaluating functions of 2-182
flipping left-right 2-108
flipping up-down 2-109
Hadamard 2-268
Hankel 2-269
Hessenberg form of 2-296

Hilbert 2-303
inverse 2-399
inverse Hilbert 2-402
magic squares 2-551
permutation 2-540
poorly conditioned 2-303
Rosser 2-208
specialized 2-193
test 2-193
unimodular 2-218
writing as binary data 2-184
writing formatted data to 2-166

matrix functions
evaluating 2-182

max 2-568
mean 2-569
median 2-570
median value of array elements 2-570
menu 2-572
menu (of user input choices) 2-572
MenuBar, Figure property 2-55
mesh 2-573
meshc 2-573
meshgrid 2-577
meshz 2-573
M-file
debugging 2-462
function 2-177
naming conventions 2-177
programming 2-177
script 2-177

M-files
locking (preventing clearing) 2-597
opening 2-662
unlocking (allowing clearing) 2-610

min 2-587
MinColormap, Figure property 2-55

minimizing, function
 of one variable 2-114
 of several variables 2-120
mi nres 2-588
mi sl ocked 2-592
mkdi r 2-593
mkpp 2-594
ml ock 2-597
mod 2-598
 models
 opening 2-662
 modulo arithmetic 2-598
more 2-599, 2-609
move 2-600
movi e 2-603
movi e2avi 2-605
movi ei n 2-607
msgbox 2-608
 mu-law encoded audio signals 2-489, 2-609
 multidimensional arrays
 interpolation of 2-392
 longest dimension of 2-475
 number of dimensions of 2-619
 rearranging dimensions of 2-404
 See also array
 multiple
 least common 2-468
 multistep ODE solver 2-645
munl ock 2-610

N
 Name, Figure property 2-56
 naming conventions
 M-file 2-177
NaN 2-611
 NaN
 detecting 2-427
NaN (Not-a-Number) 2-611
nargchk 2-612
nargin 2-613
nargout 2-613
ndgrid 2-617
ndims 2-619
 nearest neighbor interpolation 2-252, 2-381, 2-386
 Nelder-Mead simplex search 2-122
newplot 2-620
NextPlot
 Figure property 2-56
nextpow2 2-622
nmls 2-623
nnz 2-625
 no derivative method 2-125
 noncontiguous fields, inserting data into 2-184
 nonzero entries (in sparse matrix)
 allocated storage for 2-637
 number of 2-625
 vector of 2-627
nonzeros 2-627
norm
 1-norm 2-628
 2-norm (estimate of) 2-629
 F-norm 2-628
 infinity 2-628
 matrix 2-628
 vector 2-628
norm 2-628
 normal vectors, computing for volumes 2-436
normest 2-629
notebook 2-630
now 2-631
null 2-632
 null space 2-632
num2cell 2-633

num2str **2-634**
number
 of array dimensions 2-619
numbers
 detecting finite 2-416
 detecting infinity 2-420
 detecting NaN 2- 427
 detecting prime 2-442
 imaginary 2-322
 NaN 2-611
 plus infinity 2-363
NumberTitle, Figure property 2-56
numel **2-635**
numeric format 2-134
numeric precision
 format reading binary data 2-154
numerical differentiation formula ODE solvers
 2-646
nzmax **2-637**

O
object
 determining class of 2-407
object classes, list of predefined 2-407
objects
 Java 2-421, 2-441
ODE file template 2-649
ODE *See* differential equation solvers
ode113 **2-638**
ode15s **2-638**
ode23 **2-638**
ode23s **2-638**
ode23t **2-638**
ode23tb **2-638**
ode45 **2-638**
odefile **2-648**

odeget **2-654**
odeset **2-655**
off-screen figures, displaying 2-91
ones **2-661**
one-step ODE solver 2-645
online documentation, displaying 2-291
online help 2-288
open **2-662**
OpenGL 2-60
 autoselection criteria 2-63
opening files 2-128
openvar 2-667
operators
 relational 2-524
 symbols 2-288
optimget 2- 668
optimization parameters structure 2-668, 2-669
Optimization Toolbox 2-115, 2-121
optimset 2- 669
orient 2-674
orth **2-676**
otherwise **2-677**
output
 controlling display format 2-134
 in Command Window 2-599
 number of M-file arguments 2-613
overflow 2-363

P
paging
 of screen 2-290
paging in the Command Window 2-599
PaperOrientation, Figure property 2-56
PaperPosition, Figure property 2-56
PaperPositionMode, Figure property 2-57
PaperSize, Figure property 2-57

-
- PaperType, Figure property 2-57
 PaperUnits, Figure property 2-58
Parent
 Figure property 2-59
 Image property 2-336
 Light property 2-484
 Line property 2-503
Parlett's method (of evaluating matrix functions)
 2-183
path
 building from parts 2-175
PCX 2-342, 2-348, 2-355
 bit depths supported when writing 2-359
permutation
 matrix 2-540
plot, volumetric
 generating grid arrays for 2-577
plotting
 feather plots 2-15
 function plots 2-137
 histogram plots 2-304
 isosurfaces 2-438
 loglog plot 2-525
 mesh plot 2-573
PNG
 bit depths supported when writing 2-359
 reading with special `i` `mread` syntax 2-349
 writing options for 2-356
 alpha 2-358
 background color 2-358
 chromaticities 2-358
 gamma 2-358
 interlace type 2-357
 resolution 2-358
 significant bits 2-358
 transparency 2-357
Pointer, Figure property 2-59
PointerShapeCData, Figure property 2-59
PointerShapeHotSpot, Figure property 2-59
polygon
 detecting points inside 2-370
polynomial
 make piecewise 2-594
poorly conditioned
 matrix 2-303
Position
 Figure property 2-60
 Light property 2-484
position indicator in file 2-173
power
 of two, next 2-622
precision 2-134
 reading binary data writing 2-154
prime factors 2-11
 dependence of Fourier transform on 2-24, 2-25,
 2-26
prime numbers
 detecting 2-442
print frames 2-151
print frame **2-151**
PrintFrame Editor 2-151
printing
 borders 2-151
 with non-normal EraseMode 2-335, 2-499
 with print frames 2-153
product
 Kronecker tensor 2-463
K>> prompt 2-462
prompting users for input 2-371, 2-572
Property Inspector
 starting 2-375

Q

quotation mark

 inserting in a string 2-146

R

randn **2-364**

range space 2-676

reading

 binary files 2-154

 formatted data from file 2-166

readme files, displaying 2-365

rearranging arrays

 swapping dimensions 2-404

rearranging matrices

 flipping left-right 2-108

 flipping up-down 2-109

regularly spaced vectors, creating 2-511

relational operators 2-524

renderer

 OpenGL 2-60

 painters 2-60

 zbuffer 2-60

Renderer, Figure property 2-60

RendererMode, Figure property 2-62

repeatedly executing statements 2-132

Resize, Figure property 2-63

ResizeFcn, Figure property 2-64

rewinding files to beginning of 2-165, 2-347

RMS *See* root-mean-square

root directory 2-567

root-mean-square

 of vector 2-628

Rosenbrock banana function 2-121, 2-124

Rosenbrock ODE solver 2-646

Rosser matrix 2-208

round

 towards minus infinity 2-111

 towards zero 2-106

roundoff error

 evaluating matrix functions 2-182

 in inverse Hilbert matrix 2-402

Runge-Kutta ODE solvers 2-645

S

scattered data, aligning

 multi-dimensional 2-617

 two-dimensional 2-252

Schmidt semi-normalized Legendre functions

 2-473

screen, paging 2-290

scrolling screen 2-290

search, string 2-94

Select

 Figure property 2-65

 Image property 2-336

 Light property 2-485

 Line property 2-503

Select onHighLight

 Figure property 2-65

 Image property 2-337

 Light property 2-485

 Line property 2-503

SelectType, Figure property 2-65

set operations

 intersection 2-398

 membership 2-426

ShareColors, Figure property 2-66

simplex search 2-125

Simulink

 printing diagram with frames 2-151

singular value

 largest 2-628

-
- skipping bytes (during file I/O)** 2-184
smallest array elements 2-587
sparse matrix
 density of 2-625
 detecting 2-447
 finding indices of nonzero elements of 2-88
 number of nonzero elements in 2-625
 vector of nonzero elements 2-627
sparse storage
 criterion for using 2-174
special characters
 descriptions 2-288
spherical coordinates
 defining a Light position in 2-487
spline interpolation (cubic) 2-381, 2-386, 2-389, 2-392
Spline Toolbox 2-385
startup files 2-566
Stateflow
 printing diagram with frames 2-151
storage
 allocated for nonzero entries (sparse) 2-637
string
 converting matrix into 2-554, 2-634
 converting to lowercase 2-531
 searching for 2-94
strings
 inserting a quotation mark in 2-146
structure array
 field names of 2-34
 getting contents of field of 2-232
Style
 Light property 2-485
subfunction 2-177
surface normals, computing for volumes 2-436
symbols
 operators 2-288
syntax 2-288
syntaxes
 of M-file functions, defining 2-177
- T**
- table lookup** *See* **interpolation**
- Tag**
- Figure property** 2-66
 - Image property** 2-337
 - Light property** 2-485
 - Line property** 2-503
 - tensor, Kronecker product** 2-463
 - test matrices** 2-193
 - text mode for opened files** 2-128
 - TIFF** 2-342, 2-348, 2-355
 - bit depths supported when writing** 2-359
 - compression** 2-356
 - ImageDescription field** 2-356
 - parameters that can be set when writing** 2-356
 - reading with special `imread` syntax** 2-349
 - resolution** 2-356
 - writemode** 2-356
- Toolbox**
- Optimization** 2-115, 2-121
 - Spline** 2-385
- transform, Fourier**
- discrete, n-dimensional** 2-26
 - discrete, one-dimensional** 2-21
 - discrete, two-dimensional** 2-25
 - inverse, n-dimensional** 2-319
 - inverse, one-dimensional** 2-317
 - inverse, two-dimensional** 2-318
 - shifting the zero-frequency component of** 2-27
- transformation**
- elementary Hermite** 2-218
- transparency** 2-349

transparency chunk 2-349

tricubic interpolation 2-252

trilinear interpolation 2-252, 2-389, 2-392

Type

Figure property 2-66

Image property 2-337

Light property 2-485

Line property 2-503

U

UI ContextMenu

Figure property 2-67

Image property 2-337

Light property 2-485

Line property 2-503

uint8 2-380

unconstrained minimization 2-123

undefined numerical results 2-611

unimodular matrix 2-218

Units

Figure property 2-67

unlocking M-files 2-610

uppercase to lowercase 2-531

UserData

Figure property 2-67

Image property 2-337

Light property 2-485

Line property 2-503

V

variables

global 2-238

local 2-177, 2-238

name of passed 2-374

opening 2-662, 2-667

vector

dual 2-623

frequency 2-529

length of 2-475

vectors, creating

logarithmically spaced 2-529

regularly spaced 2-511

visible

Figure property 2-67

Image property 2-337

Light property 2-485

Line property 2-503

volumes

calculating isosurface data 2-438

computing isosurface normals 2-436

end caps 2-430

W

Web browser

displaying help in 2-291

white space characters, ASCII 2-446

WindowButtonDownFcn, Figure property 2-68

WindowButtonMotionFcn, Figure property 2-68

WindowButtonUpFcn, Figure property 2-68

WindowStyle, Figure property 2-68

workspace variables

reading from disk 2-514

writing

binary data to file 2-184

formatted data to file 2-141

X

XData

Image property 2-337

Line property 2-504

XDi spl ay, Figure property 2-69
XOR, printing 2-335, 2-499
XVi sual , Figure property 2-69
XVi sual Mode, Figure property 2-70
XWD 2-342, 2-348, 2-355
 bit depths supported when writing 2-359

Y

YData
 Image property 2-338
 Line property 2-504

Z

ZData
 Line property 2-504
zero of a function, finding 2-189
zero-padding
 while converting hexadecimal numbers 2-299