

LIVING DOCUMENT · UPDATED WITH EVERY CHANGE

VDB_Feature Implemented

Everything that has been built into VectoraDB so far — for each feature: **what it does**, **how it works**, **how to use it**, **how to test it**, and its honest **status**.

When a feature is added or changed, this document changes in the same commit.

Product: VectoraDB — serverless PostgreSQL with copy-on-write branching and a Schema Ledger

Last updated: 14 September 2026 · **Reflects:** `main @ 8b1856f` (release line v0.7.x)

License: AGPL-3.0 core · Apache-2.0 client SDKs

Source of truth: `docs/VDB_Feature_Implemented.html` → `make feature-doc` → this PDF

Supersedes: `docs/vectoradb-feature-reference` (25 Aug 2026, no longer maintained)

Method: every entry was taken from a read of the source code and git history, with file references.

Status reflects the code; "Working" means the code path is complete, not that it was re-run for this edition unless the Test baseline section says so.

Change log

Newest first. Every change to VectoraDB adds a row here.

Date	Feature(s)	What changed	Commit / PR
14 Sep 2026	Whole document	Document created. Inventory of every feature implemented as of <code>8b1856f</code> : install & setup, CLI, branching & storage, durability, security, gateway, auth, Schema Ledger, import, pipelines, APIs/SDKs/MCP, web console, CI & releases. Known issues and the test baseline recorded.	branch <code>docs/feature-implemented</code>

Test baseline

Recorded before any Schema Ledger 2.0 work starts, so later changes can be checked against it.

Suite	Result	Details
Go unit tests (<code>go test ./...</code> , host)	All pass	14 Sep 2026, go1.26.6 darwin/arm64, commit <code>8b1856f</code> . Packages with tests: <code>cmd/vdb</code> , <code>auth</code> , <code>branch</code> , <code>controlplane</code> , <code>daemon</code> , <code>host</code> , <code>proxy</code> . No test files: <code>agentapi</code> , <code>ledger</code> , <code>mcp</code> , <code>secrets</code> , <code>tlsutil</code> , <code>version</code> , <code>web</code> .
Integration (<code>make integration</code> , Lima VM)	Pending run	<code>\$1</code> and <code>\$5</code> call <code>http://localhost:8080 / :8088</code> while both servers serve TLS since <code>0bd52f3</code> ; those assertions are expected to fail until the test-only fix (<code>https + -k</code>) lands. Result to be recorded here.
Windows (Pester, <code>windows-ci.yml</code>)	In CI	Runs on every push/PR to main.

Feature index

Grouped by area. Badges: Working Partial Known issue

A · INSTALL & SETUP

A1	One-line installer (macOS / Linux)	Working
A2	Windows installer (install.ps1)	Partial
A3	<code>vdb setup</code> on macOS (Lima)	Working
A4	<code>vdb setup</code> on Windows (WSL2 + btrfs)	Partial
A5	Linux native	Working
A6	Command forwarding & file streaming	Working
A7	Always-latest engine binary	Working

B · CLI & SERVICES

B1	The <code>vdb</code> command set	Partial
B2	Background services (daemon)	Working

C · BRANCHING & STORAGE

C1	Storage drivers (ZFS / btrfs)	Working
C2	Branch lifecycle	Working
C3	Protection of <code>main</code>	Partial
C4	Private networking (no host ports)	Working
C5	Scale-to-zero & wake on connect	Working
C6	Storage quotas	Partial
C7	Capacity & status	Working
C8	Provisioning & image pull	Working

D · DURABILITY

D1	WAL archiving to object storage	Working
D2	Base backups	Working
D3	Point-in-time restore	Known issue
D4	HA standby & failover	Partial

E · SECURITY FOUNDATIONS

E1	Per-install generated secrets	Working
E2	TLS everywhere	Working
E3	Zero-signup local API key	Working

F · SQL GATEWAY

F1	Routing by database name	Working
F2	API-key authentication	Working
F3	Backend login (SCRAM)	Working
F4	Per-user Postgres login roles	Working
F5	Attribution session settings	Working
F6	Ctrl-C (CancelRequest) forwarding	Working
F7	Errors & insecure build tag	Working

G · ACCOUNTS & AUTH

G1	Auth store (SQLite)	Working
G2	Email & password users	Working
G3	API keys	Working
G4	Web sessions & signup control	Working
G5	OAuth (GitHub / Google)	Partial

H · SCHEMA LEDGER

H1	DDL recording	Working
H2	Hash chain, append-only, verify	Partial
H3	Attribution	Partial
H4	Destructive-DDL guardrail	Known issue
H5	Risk flags	Partial
H6	Ledger access (CLI/REST/MCP/UI/SDK)	Working
H7	<code>vdb ledger revert --to</code>	Known issue

I · IMPORT & MIGRATION

I1	From Postgres	Working
I2	From MySQL ≤5.7 / MariaDB	Working
I3	From MySQL 8.x	Working
I4	From MongoDB	Working
I5	From a .sql dump	Partial
I6	From JSON / NDJSON	Partial
I7	From CSV	Working
I8	Continuous replication & cutover	Partial
I9	Guard handling during import	Working
I10	Live progress (CLI & SSE)	Working
I11	Import REST endpoints	Working
I12	Web Import page	Working
I13	Exact identifier fidelity	Working

J · ETL PIPELINES (EXPERIMENTAL)

J1	Pipeline engine	Working
J2	Data-quality tests	Working
J3	Stored pipelines & run history	Working
J4	Pipeline editor (web)	Working

K · APIS, SDKS & AGENTS

K1	Control-plane REST API	Working
K2	OpenAPI spec	Partial
K3	Python SDK	Working
K4	TypeScript SDK	Working
K5	Agent Branch API	Partial
K6	MCP server	Partial

L · WEB CONSOLE

L1	Embedded single-origin UI	Working
L2	Login & signup	Working
L3	Dashboard	Working
L4	SQL console & browser	Working
L5	Ledger page	Partial
L6	API keys page	Working
L7	Landing, Guide & Docs pages	Partial

M · BUILD, CI & RELEASES

M1	Makefile targets	Working
M2	Linux CI	Working
M3	Windows CI	Working
M4	Releases & GHCR image	Working
M5	WSL distro / ZFS builds	Partial
M6	Postgres image	Working

Install & setup

A1 One-line installer (macOS / Linux)

Working

WHAT IT DOES	Installs the <code>vdb</code> binary with one command.
HOW IT WORKS	<code>deploy/install.sh</code> detects OS (darwin/linux) and arch (arm64/amd64), downloads <code>vdb-<os>-<arch></code> from the GitHub release, installs to <code>\$PREFIX/bin</code> (sudo only if needed). On macOS it also stages <code>vdb-linux-<arch></code> into <code>\$PREFIX/share/vectoradb</code> for the VM.
HOW TO USE	<code>curl -fsSL https://raw.githubusercontent.com/vectoradb/vectoraDB/main/deploy/install.sh sh</code> · <code>env VDB_VERSION</code> , <code>VDB_REPO</code> , <code>VDB_DIST</code> (local folder), <code>VDB_PREFIX</code> (default <code>/usr/local</code>).
HOW TO TEST	No automated test. Manual: <code>VDB_DIST=./dist VDB_PREFIX=\$HOME/.local sh deploy/install.sh</code> then <code>vdb version</code> .
STATUS & LIMITS	Working. Does not verify the published <code>SHA256SUMS</code> .
ADDED IN	<code>c9afda7</code> (PR #1); URLs repointed to the vectoradb org in <code>0b125f9</code> .

A2 Windows installer (install.ps1)

Partial

WHAT IT DOES	From a bare Windows machine to a running database with <code>irm ... iex</code> .
HOW IT WORKS	<code>deploy/install.ps1</code> Invoke-Install : (1) installs WSL (<code>wsl --install --no-distribution</code> , elevates if needed; registers a <code>RunOnce</code> resume across a reboot); (2) downloads <code>vdb-windows-amd64.exe</code> , <code>vdb-linux-amd64</code> , <code>vectoradb-docker-context.tar.gz</code> ; (3) downloads the Ubuntu noble WSL rootfs verified against Ubuntu's <code>SHA256SUMS</code> ; (4) adds the folder to <code>PATH</code> ; (5) runs <code>vdb setup</code> . Forces TLS 1.2, BOM-free ASCII.
HOW TO USE	PowerShell: <code>irm https://raw.githubusercontent.com/vectoradb/vectoraDB/main/deploy/install.ps1 iex</code> · <code>env VDB_VERSION</code> , <code>VDB_REPO</code> , <code>VDB_PREFIX</code> , <code>VDB_NO_SETUP</code> , <code>VDB_NO_ELEVATE</code> , <code>VDB_ROOTFS_URL</code> .
HOW TO TEST	Pester: <code>deploy/install.Tests.ps1</code> , <code>deploy/windows-install.Tests.ps1</code> (E2E group needs <code>VDB_TEST_E2E</code>); <code>windows-ci.yml</code> checks BOM/ASCII and PS 5.1 parsing.
STATUS & LIMITS	Works, but never downloads the prebuilt <code>vectoradb-distro.tar.gz</code> (every install takes the slower apt path) and does not verify VectoraDB's own assets against <code>SHA256SUMS</code> .
ADDED IN	<code>4fc8afb</code> (PR #1); one-command flow <code>0c71da9</code> , verified downloads <code>d0c1f26</code> (PR #7); resume fix <code>288c431</code> (PR #8).

A3 vdb setup on macOS (Lima)

Working

WHAT IT DOES	Creates/starts a Linux VM, installs Docker + ZFS, installs the engine and starts the stack.
HOW IT WORKS	<code>internal/host/host_darwin.go</code> <code>setupDarwin</code> : requires <code>limactl</code> ; refreshes the engine binary (A7); creates <code>template://ubuntu</code> VM if missing and runs <code>provisionGuest</code> (<code>zfsutils-linux docker.io</code>); always reinstalls the engine to <code>/usr/local/bin/vdb</code> in the VM; then forwards <code>start</code> .
HOW TO USE	<code>brew install lima && vdb setup</code> · <code>env VECTORADB_LIMA_INSTANCE</code> (default <code>vectoradb</code> , falls back to <code>default</code>), <code>VECTORADB_GUEST_BINARY</code> .
HOW TO TEST	No unit test for orchestration. Manual: <code>limactl delete -f vectoradb</code> ; <code>vdb setup</code> ; <code>vdb status</code> .
STATUS & LIMITS	Working. Provisioning only runs on VM creation (an interrupted VM isn't repaired). No image build context is staged, so if the GHCR pull fails an installed user can't fall back to a local build.
ADDED IN	<code>c9afda7</code> (PR #1); always-reinstall <code>77ef8ba</code> (PR #18).

A4 vdb setup on Windows (WSL2 + btrfs)

Partial

WHAT IT DOES	Imports a dedicated <code>vectoradb</code> WSL distro, provisions it and starts VectoraDB with quiet step-by-step output.
HOW IT WORKS	<code>host_windows.go</code> <code>setupWindows</code> : checks <code>wsl --status</code> ; refreshes the engine; <code>importDistro</code> (<code>wsl --import</code> , writes <code>/etc/wsl.conf</code> with <code>systemd</code>); <code>waitForSystemd</code> ; <code>provisionGuestWSL</code> on every run (Docker, btrfs, storage unit, preloaded images, image context, engine binary); <code>verifyBtrfs</code> ; quiet <code>start</code> with one retry; <code>finishSetup</code> . All guest output goes to <code>install.log</code> next to <code>vdb.exe</code> . A <code>vectoradb-storage.service</code> mounts the btrfs image before Docker at boot; <code>forwardStdin</code> waits for <code>systemd</code> on a cold distro.
HOW TO USE	<code>vdb setup</code> (run by <code>install.ps1</code>) · env <code>VECTORADB_WSL_DISTRO</code> , <code>VECTORADB_GUEST_BINARY</code> .
HOW TO TEST	Unit: <code>host_wsl_test.go</code> (TestResolveWSLDistro, TestWSLArgs, TestDecodeWSLList, TestWinPathToMnt, TestParseKernelRelease). Manual: <code>wsl --unregister vectoradb</code> ; <code>vdb setup</code> ; <code>vdb status</code> .
STATUS & LIMITS	Works. Preloaded Postgres image is tagged <code>vectoradb/postgres-walg:16</code> but the engine needs <code>ghcr.io/vectoradb/postgres-walg:16</code> , so preload is ineffective. The final summary prints a connection string without the API key or <code>sslmode</code> . The storage-unit error text still mentions ZFS.
ADDED IN	<code>4fc8afb</code> , <code>8305e5b</code> (PR #1); quiet flow <code>0c71da9</code> + prebuilt image <code>d0c1f26</code> (PR #7); btrfs <code>fc4a1b8</code> (PR #9); initdb race fix <code>cb6655c</code> (PR #21).

A5 Linux native

Working

WHAT IT DOES	On Linux the engine runs in-process; no VM.
HOW IT WORKS	<code>host_other.go</code> : <code>vdb setup</code> prints "Linux host — no VM needed. Run <code>vdb start</code> ". ZFS and Docker must be installed; <code>ensureDocker</code> / <code>ensureReady</code> give instructive errors.
HOW TO USE	<code>sudo vdb start</code>
HOW TO TEST	Integration suite runs on Linux (inside the Lima VM): <code>make integration</code> .
STATUS & LIMITS	Working.
ADDED IN	<code>4fc8afb</code> (PR #1).

A6 Command forwarding & host file streaming

Working

WHAT IT DOES	On macOS/Windows every engine command transparently runs inside the VM; <code>vdb import --from ./file</code> works for any file on the host.
HOW IT WORKS	<code>host.Maybe</code> (<code>host.go</code>) forwards unless on Linux, in the guest (<code>VECTORADB_IN_GUEST</code>) or a local command. macOS: <code>limactl shell ... env VECTORADB_IN_GUEST=1 vdb ...</code> (auto-starts the VM). Windows: <code>wsl.exe -d vectoradb -- env ... vdb ...</code> . <code>importLocalFile</code> rewrites a local file import to <code>--from - - -kind <ext> --srcname <name></code> and pipes the file over stdin.
HOW TO USE	Automatic. Env <code>VECTORADB_GUEST_BIN</code> .
HOW TO TEST	Unit: <code>TestImportLocalFile</code> , <code>TestWSLArgs</code> . Manual: <code>limactl stop vectoradb && vdb status</code> (VM auto-starts); import a CSV from the Desktop.
STATUS & LIMITS	Working. Only <code>import</code> streams files; <code>pipeline run spec.json</code> passes the path unchanged (must be readable in the VM).
ADDED IN	<code>c9afda7</code> , <code>4fc8afb</code> , <code>8305e5b</code> (PR #1); streaming <code>44cc05c</code> .

A7 Always-latest engine binary

Working

WHAT IT DOES	Re-running <code>vdb setup</code> installs the newest Linux engine rather than a stale bundled copy.
HOW IT WORKS	<code>refreshEngineBinary</code> (<code>host.go</code>) downloads <code>vdb-linux-<arch></code> from the latest (or pinned) release into <code>~/vectoradb/</code> with a 5-minute timeout, atomic rename and an ELF check; best-effort fallback to the installer's copy. <code>bundledLinuxBinary</code> prefers the cache.
HOW TO USE	Automatic. <code>VECTORADB_NO_REFRESH=1</code> skips it; <code>VDB_REPO</code> / <code>VDB_VERSION</code> override the source.
HOW TO TEST	Unit: <code>host_test.go</code> — <code>TestIsELF</code> , <code>TestBundledLinuxBinaryPrefersCache</code> , <code>TestRefreshEngineBinaryDisabled</code> , <code>TestDownloadFile</code> .
STATUS & LIMITS	Working. No checksum verification (ELF magic only).
ADDED IN	<code>77ef8ba</code> (PR #18).

CLI & services

B1 The vdb command set

Partial

WHAT IT DOES

One CLI for the whole product.

HOW IT WORKS

cmd/vdb/main.go : host.Maybe forwarding, then a command switch with hand-rolled flag parsing (addrFlag , durFlag , restoreArg).

HOW TO USE

Command	Purpose
vdb version · setup · start · stop · up · down · status · logs [svc] · psql	Lifecycle, status, logs, psql on main
vdb branch create list delete reset [--from p] suspend resume	Branches (C2)
vdb backup create list · vdb restore --to <ts latest>	Durability (D2, D3)
vdb ha enable status failover disable	HA (D4)
vdb ledger [branch] [--limit N] · ledger verify · ledger revert --to	Schema Ledger (H6, H7)
vdb import --from <src> [--as n] [--continuous] · vdb import-cutover <n>	Import (I*)
vdb pipeline run spec.json [--as n]	Pipelines (J1)
vdb user create · vdb apikey create list revoke	Accounts (G2, G3)
vdb gateway [--addr :6432] [--idle 2m] · vdb controlplane [--addr :8080] · vdb serve [--addr :8088] · vdb mcp	Run a service in the foreground

HOW TO TEST

Unit: cmd/vdb/main_test.go — TestAddrFlag, TestDurFlag, TestRestoreArg. Behaviour via scripts/integration_test.sh .

STATUS & LIMITS

vdb vm is listed as a local command (host.go) but has no implementation ("unknown command"). branch create has no --from .

ADDED IN

a7580f6 (initial); renamed vectoradb → vdb in c9afda7 .

B2 Background services (daemon)

Working

WHAT IT DOES	vdb start runs three detached TLS servers: control plane :8080 (REST + web UI), gateway :6432 (idle 2m), agent API :8088 .	
HOW IT WORKS	internal/daemon : re-executes the binary per service, logs to ~/.vectoradb/<name>.log , pidfile <name>.pid , Setsid detach; Stop sends SIGTERM then SIGKILL after ~3s.	
HOW TO USE	vdb start · vdb status · vdb logs gateway api controlplane · vdb stop	
HOW TO TEST	Unit: daemon_test.go TestStopTerminatesProcess. Integration §1 (stop/start).	
STATUS & LIMITS	Working. No health check or restart-on-crash.	
ADDED IN	a7580f6 .	

Branching & storage

C1 Storage drivers (ZFS / btrfs)

Working

WHAT IT DOES	Instant copy-on-write copies of a whole Postgres data directory. ZFS on macOS/Linux, btrfs on Windows.
HOW IT WORKS	<code>internal/branch/storage.go</code> : storage interface; <code>activeStorage()</code> picks by <code>VECTORADB_STORAGE</code> . ZFS: pool <code>vectoradb</code> on a file (<code>VECTORADB_ZPOOL_DEVICE</code> , size <code>VECTORADB_ZPOOL_SIZE =30G</code>), clone = <code>zfs snapshot ...@for-<dst> + zfs clone</code> . btrfs: loop image at <code>/vectoradb/branches</code> , clone = <code>btrfs subvolume snapshot</code> , new subvolumes get <code>chattr +C</code> (nodatacow).
HOW TO USE	Automatic (Windows launcher sets <code>VECTORADB_STORAGE=btrfs</code>).
HOW TO TEST	Integration §2 (branch isolation). Manual: <code>vdb branch create t1 && sudo zfs list -r vectoradb</code> .
STATUS & LIMITS	Working. ZFS <code>destroy</code> only removes the parent snapshot when the parent is <code>main</code> , so repeated <code>reset --from <non-main></code> may fail.
ADDED IN	ZFS <code>a7580f6</code> ; driver split + btrfs <code>fc4a1b8</code> , nodatacow <code>81ff8f8</code> (PR #9).

C2 Branch lifecycle

Working

WHAT IT DOES	Create, list, delete, reset (start over from parent), suspend and resume isolated full copies of the database.
HOW IT WORKS	<code>branch.go</code> : Create (CHECKPOINT parent, clone, chown, start container, <code>waitReady</code> over TCP), Delete , Reset (delete + create), List , Suspend (<code>docker stop</code>), Resume , Wake → <code>EnsureRunning</code> .
HOW TO USE	<code>vdb branch create qa . list . suspend qa . resume qa . reset qa [--from main] . delete qa ; REST POST/DELETE /api/branches</code> .
HOW TO TEST	Unit: <code>TestContainerName</code> . Integration §2 (isolation), §4 (suspend/resume). Manual: the command sequence above.
STATUS & LIMITS	Working. CLI create does no name validation (REST does).
ADDED IN	<code>a7580f6</code> ; reset <code>00e7eae</code> (PR #13); TCP readiness <code>cb6655c</code> (PR #21).

C3 Protection of `main`

Partial

WHAT IT DOES	Stops the primary from being deleted or reset by mistake.
HOW IT WORKS	Delete and Reset refuse <code>main</code> ; <code>EnsureRunning</code> never auto-starts <code>main</code> (avoids split-brain after failover); the reaper never suspends <code>main</code> , restore or standby; ZFS reservation keeps space for <code>main</code> (C6).
HOW TO USE	Automatic.
HOW TO TEST	Manual: <code>vdb branch delete main</code> → "refusing to delete the primary branch 'main'".
STATUS & LIMITS	Suspend has no guard: <code>vdb branch suspend main</code> stops the primary and the gateway will not wake it (only <code>vdb up</code>).
ADDED IN	<code>a7580f6</code> .

C4 Private networking (no host ports)

Working

WHAT IT DOES	Branch databases are reachable only through the gateway, not directly from the host or LAN.
HOW IT WORKS	Containers <code>vec-<name></code> join docker network <code>vectoradb</code> with no published ports; the gateway dials the container IP (<code>BackendAddr</code> → <code>containerIP</code> ; <code>main</code> via <code>PrimaryContainer()</code>). <code>VECTORADB_DEBUG_PORTS</code> re-publishes ports for debugging.
HOW TO USE	Automatic.
HOW TO TEST	Unit: <code>TestParsePublishedPort</code> , <code>TestDSN</code> . Manual: <code>docker ps</code> shows no <code>5432</code> mapping for <code>vec-*</code> .
STATUS & LIMITS	Working. Exceptions: <code>vec-restore</code> publishes <code>5433</code> , HA standby a random port, MinIO <code>9000/9001</code> .
ADDED IN	<code>797bc14</code> , <code>b664b56</code> (PR #11).

C5 Scale-to-zero & wake on connect

Working

WHAT IT DOES	Idle branches stop automatically; the next connection wakes them.
HOW IT WORKS	Gateway <code>reaper</code> (<code>proxy.go</code>) polls every idle/3 (5–30s) and suspends a branch only when <code>idle ≥ threshold</code> and <code>ActiveConnections = 0</code> . On connect, <code>EnsureRunning</code> routes, recreates or resumes the container and re-enables the guard (<code>reconcileGuard</code>).
HOW TO USE	<code>vdb gateway --idle 2m</code> (default via <code>vdb start</code>); <code>--idle 0</code> disables.
HOW TO TEST	Integration §7 (idle 8s: branch suspended, standby untouched). Manual: wait >2 min, then connect through the gateway.
STATUS & LIMITS	Working. Idle clocks are in memory (reset on gateway restart). Cold-start latency not measured.
ADDED IN	<code>a7580f6</code> .

C6 Storage quotas

Partial

WHAT IT DOES	Reserves space for <code>main</code> and optionally caps each branch.
HOW IT WORKS	<code>reserveMain</code> : <code>zfs set reservation</code> (default 2G) on every Init. <code>setBranchRefquota</code> : <code>zfs set refquota</code> on new branches when configured.
HOW TO USE	<code>VECTORADB_MAIN_RESERVATION=5G VECTORADB_BRANCH_REFQUOTA=20G vdb start</code> (<code>none</code> disables).
HOW TO TEST	Manual: <code>sudo zfs get reservation,refquota vectoradb/branches/main vectoradb/branches/qa</code> .
STATUS & LIMITS	ZFS only; per-branch cap is opt-in (default uncapped); not implemented on btrfs.
ADDED IN	<code>21f7259</code> (PR #12).

C7 Capacity & status

Working

WHAT IT DOES	Shows services, main health, backups, branches, storage used/available.
HOW IT WORKS	<code>Status</code> , <code>Branches</code> (state, used, referenced, connections), <code>StorageInfo</code> (<code>zfs list</code> / <code>btrfs filesystem usage</code>).
HOW TO USE	<code>vdb status</code> ; <code>GET /api/status</code> ; web Dashboard.
HOW TO TEST	Integration §1 (<code>mainReady</code>). Manual: <code>vdb status</code> .
STATUS & LIMITS	Working. On btrfs "used" is apparent size, not the copy-on-write delta.
ADDED IN	<code>a7580f6</code> ; <code>StorageInfo</code> <code>4b0be5c</code> .

C8 Provisioning & image pull

Working

WHAT IT DOES	<code>vdb up/start</code> prepares Docker, the storage pool and the Postgres image automatically.
HOW IT WORKS	<code>provision.go</code> : <code>ensureDocker</code> → <code>ensurePool</code> → <code>ensureImage</code> (inspect, else <code>docker pull ghcr.io/vectoradb/postgres-walg:16</code> , else <code>docker build</code> from <code>VECTORADB_IMAGE_CONTEXT</code> / <code>docker/postgres</code>).
HOW TO USE	Automatic.
HOW TO TEST	Manual: <code>sudo docker rmi ghcr.io/vectoradb/postgres-walg:16; vdb up</code> .
STATUS & LIMITS	Working; the pull needs the GHCR package to be public.
ADDED IN	<code>c9afda7</code> ; GHCR pull <code>aae9e20</code> (PR #12).

Durability

D1 WAL archiving to object storage

Working

WHAT IT DOES	Continuously ships main's write-ahead log to a local S3-compatible store, off the commit path.
HOW IT WORKS	<code>Up</code> starts MinIO (<code>minio/minio:latest</code> , generated credentials) and creates bucket <code>vectoradb-wal</code> ; main runs with <code>archive_mode=on</code> , <code>archive_command='wal-g wal-push %p'</code> , <code>archive_timeout=60</code> , <code>lz4</code> .
HOW TO USE	Automatic with <code>vdb start</code> . MinIO console at <code>:9001</code> .
HOW TO TEST	Integration §3. Manual: log in to MinIO with values from <code>~/.vectoradb/secrets.json</code> and see WAL files.
STATUS & LIMITS	Working. MinIO images unpinned; branches don't archive.
ADDED IN	<code>a7580f6</code> ; generated credentials <code>797bc14</code> .

D2 Base backups

Working

WHAT IT DOES	Takes and lists full base backups of main.
HOW IT WORKS	<code>Backup</code> : <code>docker exec vec-main wal-g backup-push</code> ; <code>BackupList</code> : <code>wal-g backup-list --detail</code> .
HOW TO USE	<code>vdb backup create</code> · <code>vdb backup list</code>
HOW TO TEST	Integration §3.
STATUS & LIMITS	Manual only (no schedule or retention). Always targets <code>vec-main</code> , even after an HA failover.
ADDED IN	<code>a7580f6</code> .

D3 Point-in-time restore

Known issue

WHAT IT DOES	Brings up a separate copy of main at a past timestamp (or latest) on port 5433.
HOW IT WORKS	<code>Restore</code> runs the image with <code>restore-entripoint.sh</code> : <code>wal-g backup-fetch LATEST</code> , <code>recovery_target_time</code> , <code>promote</code> ; <code>waitRecovered</code> polls up to 80s.
HOW TO USE	<code>vdb restore --to '2026-09-14 10:00:00+00'</code> or <code>--to latest</code>
HOW TO TEST	Integration §3 ("PITR restores 3 rows").
STATUS & LIMITS	Broken on fresh installs: <code>Restore</code> passes hardcoded <code>minioadmin</code> credentials (<code>branch.go</code> ~557) while MinIO runs on generated ones, so the backup fetch fails. Success message still shows <code>PGPASSWORD=vectoradb</code> . Always fetches the LATEST base backup, so a time before that backup can't be reached. Fix scheduled (Schema Ledger 2.0, Phase 1 H1).
ADDED IN	<code>a7580f6</code> ; broke with <code>797bc14</code> (PR #11).

D4 HA standby & failover

Partial

WHAT IT DOES	A single-VM demo of an asynchronous hot standby with manual failover.
HOW IT WORKS	<code>ha.go</code> : <code>HAEnable</code> (replication <code>hba</code> rule, <code>pg_basebackup -R</code> , start <code>vec-standby</code>); <code>HAFailover</code> (<code>pg_promote()</code>) , stop old primary, write <code>standby</code> to <code>~/.vectoradb/primary</code> so the gateway routes main to it); <code>HADisable</code> ; <code>HAStatus</code> .
HOW TO USE	<code>vdb ha enable</code> <code>status</code> <code>failover</code> <code>disable</code>
HOW TO TEST	Integration §6 (streaming replica, write after failover) and §7.
STATUS & LIMITS	Demo: no automatic detection, fencing or multi-host. Hazard: <code>vdb ha enable</code> after a failover wipes the live primary (<code>vec-standby</code>). After <code>ha disable</code> post-failover, main routes to a stopped <code>vec-main</code> until <code>vdb up</code> .
ADDED IN	<code>a7580f6</code> ; btrfs support <code>fc4a1b8</code> .

Security foundations

E1 Per-install generated secrets

Working

WHAT IT DOES	Every install gets its own Postgres and MinIO passwords — nothing hardcoded.
HOW IT WORKS	<code>internal/secrets : Load()</code> reads or creates <code>~/.vectoradb/secrets.json</code> (0600, atomic write) with crypto/rand values (<code>pg_password</code> , <code>minio_user</code> , <code>minio_password</code>); env overrides are applied but never written. Used by the engine, gateway backend login and role password sync.
HOW TO USE	Automatic. Env <code>VECTORADB_PG_PASSWORD</code> , <code>VECTORADB_MINIO_USER</code> , <code>VECTORADB_MINIO_PASSWORD</code> .
HOW TO TEST	Indirect (TestDSN isolates HOME). Manual: <code>cat ~/.vectoradb/secrets.json</code> in the VM.
STATUS & LIMITS	Working, except PITR ignores it (D3). Process-local caching only.
ADDED IN	797bc14 (PR #11).

E2 TLS everywhere

Working

WHAT IT DOES	Gateway, control plane and agent API all serve TLS with zero setup; clients can use <code>sslmode=require</code> .
HOW IT WORKS	<code>internal/tlsutil : EnsureCert</code> uses <code>VECTORADB_TLS_CERT / _KEY</code> or generates a self-signed ECDSA P-256 cert (10 years, SAN localhost/127.0.0.1/::1) under <code>~/.vectoradb/tls</code> with a cross-process file lock; min TLS 1.2. Gateway answers SSLRequest with 'S' and upgrades; GSS gets 'N'.
HOW TO USE	<code>psql "postgresql://vectoradb:<key>@localhost:6432/main?sslmode=require"</code> ; <code>curl -k https://localhost:8080/api/status</code> .
HOW TO TEST	Unit: <code>TestReadStartupSkipsSSL</code> , <code>TestReadStartupUpgradesTLS</code> . Manual: <code>openssl s_client -connect localhost:8080</code> .
STATUS & LIMITS	Working. TLS is optional at the gateway (a <code>sslmode=disable</code> client still connects, sending its key in cleartext). Servers fall back to plain HTTP if the cert can't load.
ADDED IN	0bd52f3 ; file lock b664b56 (PR #11).

E3 Zero-signup local API key

Working

WHAT IT DOES	The first <code>vdb start</code> prints a working connection string with an API key already inside.
HOW IT WORKS	<code>bootstrapLocalKey (main.go): reuse api_key=</code> from <code>~/.vectoradb/config</code> , else if no users exist create <code>local@vectoradb</code> + key setup and save it (0600). Never fails start.
HOW TO USE	<code>vdb start</code> and read the banner.
HOW TO TEST	Manual: fresh HOME, <code>vdb start</code> , <code>cat ~/.vectoradb/config</code> .
STATUS & LIMITS	Working. Key stored in plaintext by design; on Windows the setup summary doesn't show it.
ADDED IN	dcc32ab (PR #11).

SQL gateway

F1 Routing by database name

Working

WHAT IT DOES	One Postgres endpoint (:6432); the database name you connect to is the branch.
HOW IT WORKS	<code>proxy.Serve</code> → <code>handle</code> : reads the <code>StartupMessage</code> (protocol 3.0, ≤1 MiB), <code>EnsureRunning(target)</code> , rewrites <code>database</code> → <code>vectoradb</code> and <code>user</code> → login role, then relays bytes both ways. No <code>dbname</code> → <code>main</code> .
HOW TO USE	<code>psql "postgresql://vectoradb:<key>@localhost:6432/qa?sslmode=require"</code>
HOW TO TEST	Unit: <code>TestBuildParseStartupRoundtrip</code> . Integration §1, §6.
STATUS & LIMITS	Working. No pooling or rate limiting.
ADDED IN	<code>a7580f6</code> .

F2 API-key authentication

Working

WHAT IT DOES	Every client must use a <code>vdb_</code> API key as its Postgres password.
HOW IT WORKS	<code>requestClientPassword</code> asks for a cleartext password (inside TLS), <code>VerifyKey</code> checks it; bad key → <code>28P01 invalid API key</code> . <code>AuthenticationOk</code> is sent only after the backend login succeeds.
HOW TO USE	<code>PGPASSWORD=vdb_... psql "postgresql://vectoradb@localhost:6432/main?sslmode=require"</code>
HOW TO TEST	Integration §1 (bad key rejected, key accepted).
STATUS & LIMITS	Working.
ADDED IN	<code>e42e792</code> ; auth store <code>235ff41</code> .

F3 Backend login (SCRAM)

Working

WHAT IT DOES	The gateway logs in to the branch itself, so clients never see the database password.
HOW IT WORKS	<code>backendAuth</code> (<code>auth.go</code>) supports cleartext, md5 and SCRAM-SHA-256 using the per-install password; failures → <code>08006</code> .
HOW TO USE	Automatic.
HOW TO TEST	Exercised by integration §1, §6, §8 (no unit test for SCRAM).
STATUS & LIMITS	Working.
ADDED IN	<code>e42e792</code> .

F4 Per-user Postgres login roles

Working

WHAT IT DOES	Each user logs in as a role named after their email, so the ledger's actor (<code>session_user</code>) can't be forged; permissions stay those of non-superuser <code>vdbclient</code> (RLS and GRANTS apply).
HOW IT WORKS	<code>loginUser</code> → <code>branch.EnsureUserRole</code> : <code>CREATE ROLE <email> LOGIN NOSUPERUSER ... IN ROLE vdbclient</code> , <code>ALTER ROLE ... SET role = vdbclient</code> ; cached per process; falls back to <code>vdbclient</code> on error.
HOW TO USE	Automatic. Check with <code>select session_user, current_user;</code> → <code><email></code> , <code>vdbclient</code> .
HOW TO TEST	Manual query above (no automated test).
STATUS & LIMITS	Working. Roles share the per-install password (the gateway authenticates the user, not Postgres).
ADDED IN	<code>96c8c31</code> (role split <code>aad84e4</code>).

F5 Attribution session settings

Working

WHAT IT DOES	Tags every session with who, what kind, which branch and a session id for the Schema Ledger.
HOW IT WORKS	<code>ledgerOptions</code> appends <code>-c vdb.actor=<email> vdb.actor_kind=human agent vdb.branch=vdb.session=<random> ; agent</code> when the branch name starts with <code>agent-</code> .
HOW TO USE	Automatic. <code>SHOW vdb.actor;</code>
HOW TO TEST	Integration §8 (DDL attributed to the human key).
STATUS & LIMITS	Working; <code>actor_kind</code> , <code>branch</code> , <code>session</code> are ordinary settings a client could change (the actor itself comes from F4).
ADDED IN	<code>e42e792</code> .

F6 Ctrl-C (CancelRequest) forwarding

Working

WHAT IT DOES	Pressing Ctrl-C in psql cancels a running query through the gateway.
HOW IT WORKS	<code>relayStartupCaptureKey</code> records <code>BackendKeyData</code> (<code>pid:secret</code> → backend address); <code>forwardCancel</code> replays a cancel packet to the right backend.
HOW TO USE	<code>select pg_sleep(60);</code> then Ctrl-C → "canceling statement due to user request".
HOW TO TEST	Unit: <code>TestReadStartupHandlesCancel</code> . Manual as above.
STATUS & LIMITS	Working; the key map lives in one gateway process.
ADDED IN	<code>4758737</code> / <code>4cccbd6</code> (PR #17).

F7 Errors & insecure build tag

Working

WHAT IT DOES	Failures reach clients as real Postgres errors; the no-auth bypass can't exist in release builds.
HOW IT WORKS	<code>sendError</code> writes FATAL <code>ErrorResponses</code> (<code>28P01</code> , <code>3D000</code> branch missing, <code>08006</code>). <code>VECTORADB_GATEWAY_NOAUTH</code> only works in binaries built with <code>-tags insecure</code> .
HOW TO USE	Connect to a missing branch → <code>FATAL: branch "x" does not exist</code> .
HOW TO TEST	Unit: <code>TestSendError</code> .
STATUS & LIMITS	Working.
ADDED IN	<code>a7580f6</code> ; insecure tag <code>1884445</code> (PR #12).

Accounts & auth

G1 Auth store (SQLite)

Working

WHAT IT DOES	Stores users, API keys, sessions, OAuth identities, pipelines and runs for a single-tenant install.
HOW IT WORKS	<code>internal/auth</code> : <code>OpenFromEnv</code> (<code>VECTORADB_DB</code> , default <code>~/vectoradb/vectoradb.db</code> in the VM), pure-Go SQLite with WAL + <code>busy_timeout</code> so all three services share it.
HOW TO USE	Automatic.
HOW TO TEST	Unit: <code>TestVerifyKeyConcurrent</code> .
STATUS & LIMITS	Working. Every signed-in user can see every branch (no RBAC).
ADDED IN	<code>235ff41</code> (PR #1); WAL <code>c2dd024</code> .

G2 Email & password users

Working

WHAT IT DOES	Create an account and log in with email + password.
HOW IT WORKS	<code>CreateUser</code> (lower-cased email, bcrypt), <code>Login</code> (generic "invalid credentials"); 8-char minimum enforced in the CLI and <code>/auth/register</code> .
HOW TO USE	<code>vdb user create you@x.com</code> ; <code>POST /auth/register</code> , <code>POST /auth/login</code> .
HOW TO TEST	Unit: <code>TestPasswordLogin</code> . Integration §1.
STATUS & LIMITS	Working. No password change/reset, user list or delete.
ADDED IN	<code>235ff41</code> .

G3 API keys

Working

WHAT IT DOES	Non-interactive credentials for REST (Bearer / <code>X-API-Key</code>) and the gateway.
HOW IT WORKS	Secret <code>vdb_</code> + 24 random bytes; only the sha256 is stored; shown once; per-user list/revoke; <code>last_used</code> updated at most once a minute.
HOW TO USE	<code>vdb apikey create <email> [name]</code> · <code>list</code> · <code>revoke</code> ; <code>GET/POST /api/keys</code> , <code>DELETE /api/keys/{id}</code> ; web Keys page.
HOW TO TEST	Unit: <code>TestAPIKeys</code> . Integration §1.
STATUS & LIMITS	Working. Revoking an unknown id still returns success.
ADDED IN	<code>235ff41</code> .

G4 Web sessions & signup control

Working

WHAT IT DOES	Browser login sessions; self-signup can be closed.
HOW IT WORKS	30-day session token in <code>HttpOnly</code> cookie <code>vdb_session</code> ; <code>Authn</code> accepts cookie, Bearer or <code>X-API-Key</code> . <code>VECTORADB_SIGNUP=closed</code> makes register return 403; <code>GET /auth/providers</code> tells the UI what's available.
HOW TO USE	<code>/auth/login</code> , <code>/auth/logout</code> , <code>/auth/me</code> ; <code>VECTORADB_SIGNUP=closed</code> <code>vdb start</code> .
HOW TO TEST	Unit: <code>TestSessions</code> . Manual: <code>curl -k https://localhost:8080/auth/providers</code> .
STATUS & LIMITS	Working. Signup is open by default: anyone who can reach <code>:8080</code> can register.
ADDED IN	<code>235ff41</code> .

G5 OAuth (GitHub / Google)

Partial

WHAT IT DOES	"Continue with GitHub / Google" sign-in.
HOW IT WORKS	<code>oauth.go</code> : state cookie, code exchange, identity fetch, <code>upsertOAuth</code> links by email; redirects to <code>VECTORADB_WEB_ORIGIN/dashboard</code> .
HOW TO USE	Set <code>VECTORADB_GITHUB_CLIENT_ID/_SECRET</code> or <code>VECTORADB_GOOGLE_CLIENT_ID/_SECRET</code> , plus <code>VECTORADB_PUBLIC_URL=https://localhost:8080</code> and <code>VECTORADB_WEB_ORIGIN=https://localhost:8080</code> .
HOW TO TEST	No automated test. Manual: register an OAuth app with callback <code>https://localhost:8080/auth/oauth/github/callback</code> .
STATUS & LIMITS	Defaults are stale (<code>http://localhost:8080</code> , <code>http://localhost:5173</code>), so it only works with both URLs set explicitly. Untested.
ADDED IN	<code>235ff41</code> .

Schema Ledger

The ledger lives inside each branch database (`vdb.schema_ledger`), installed into `main` by `InstallLedger` during `Init` and inherited by every branch through the copy-on-write clone. Source: `internal/ledger/ledger.sql`.

H1 DDL recording

Working

WHAT IT DOES	Records every schema change — who, with which tool, on which branch, the statement, its status and risk.
HOW IT WORKS	Event triggers: <code>ddl_command_end</code> → <code>log_ddl_end</code> (one row per object, incl. GRANT/REVOKE and function DDL); <code>sql_drop</code> → <code>log_ddl_drop</code> . Skips objects in schema <code>vdb</code> , COMMENT, CREATE EXTENSION, event triggers, CREATE SCHEMA, sequences and <code>_pkey</code> indexes. Columns: id, at, actor, actor_kind, tool, session, branch, command_tag, object_type, object_identity, statement, status, risk, prev_hash, row_hash.
HOW TO USE	Automatic for all clients (gateway, console, psql, ORMs, imports).
HOW TO TEST	Integration §8 ("ledger captures DDL, attributed to the human key").
STATUS & LIMITS	Working. Not captured: DML, role/database/tablespace changes (Postgres doesn't fire event triggers for those); some dropped object types (triggers, policies, extensions).
ADDED IN	<code>e42e792</code> ; GRANT/REVOKE/function DDL <code>db9dc0c</code> (PR #13).

H2 Hash chain, append-only & verify

Partial

WHAT IT DOES	Makes the ledger tamper-evident: rows can't be edited/deleted normally, and any break in the chain is detected.
HOW IT WORKS	<code>chain_row</code> BEFORE INSERT sets <code>row_hash = sha256(prev_hash id at(UTC) ... risk)</code> under <code>pg_advisory_xact_lock</code> . <code>vdb_append_only</code> / <code>vdb_no_truncate</code> triggers + REVOKE block UPDATE/DELETE/TRUNCATE. <code>LedgerVerify</code> recomputes every hash and link.
HOW TO USE	<code>vdb ledger verify [branch]</code> ; GET <code>/api/branches/{name}/ledger/verify</code> ; MCP <code>verify_ledger</code> ; SDK <code>verify_ledger()</code> .
HOW TO TEST	Integration §8 (plain DELETE blocked; 0 broken rows). Manual: <code>vdb ledger verify</code> → "ledger intact — N rows...".
STATUS & LIMITS	A superuser can bypass the triggers (<code>session_replication_role=replica</code>). Verify can't detect deletion of the newest rows or a wiped table (no external anchor). <code>vdb.policy</code> is not covered. No verify button in the web UI. (Schema Ledger 2.0 Phase 3 adds anchored checkpoints.)
ADDED IN	<code>db9dc0c</code> , <code>d14d9a1</code> (PR #13).

H3 Attribution

Partial

WHAT IT DOES	Records who made each change and whether it was a human or an agent.
HOW IT WORKS	<code>vdb._ctx</code> : actor = <code>session_user</code> (per-user role, F4) unless the login is <code>vectoradb</code> / <code>vdbclient</code> , then the <code>vdb.actor</code> setting; kind = <code>vdb.actor_kind</code> ; tool = <code>application_name</code> ; session = <code>vdb.session</code> or backend pid. Console sets actor to the signed-in email; agent branches get <code>vdb.actor='agent-<id>'</code> database defaults.
HOW TO USE	Automatic.
HOW TO TEST	Integration §8 (actor_kind = human).
STATUS & LIMITS	Non-forgable for gateway users. Agent API returns a superuser DSN and MCP <code>run_sql</code> runs as superuser (actor NULL on main) — scheduled fix Phase 1 H3. Tool/kind/session are client-settable.
ADDED IN	<code>e42e792</code> ; non-forgable <code>96c8c31</code> (PR #16).

H4 Destructive-DDL guardrail

Known issue

WHAT IT DOES	Refuses <code>DROP TABLE</code> and <code>DROP SCHEMA</code> before they run, and still records the attempt.
HOW IT WORKS	<code>ddl_command_start</code> → <code>guard_ddl_start</code> looks up <code>vdb.policy</code> (seeded <code>DROP TABLE/SCHEMA</code> → block) and raises <code>insufficient_privilege</code> ; a <code>dblink</code> insert records status <code>BLOCKED</code> in its own transaction so it survives the rollback. Imports/pipelines disable the trigger temporarily (I9).
HOW TO USE	Automatic: <code>DROP TABLE t;</code> → "VectoraDB guardrail: DROP TABLE is blocked by policy".
HOW TO TEST	Integration §8 (DROP blocked; BLOCKED row recorded).
STATUS & LIMITS	Override is ungated: any client can <code>SET vdb.allow_destructive=on</code> , and using it isn't recorded. Only <code>block</code> actions work (<code>flag</code> / <code>allow</code> do nothing); no CLI/API/UI to manage policy. Fix scheduled (Phase 1 H2).
ADDED IN	e42e792 .

H5 Risk flags

Partial

WHAT IT DOES	Marks risky changes so they stand out.
HOW IT WORKS	Regexes on the query text set status <code>FLAGGED</code> with risk <code>type-change</code> , <code>drop-column</code> or <code>security-definer</code> ; drops get risk <code>drop</code> , blocked attempts <code>policy</code> .
HOW TO USE	Automatic; filter with <code>?risk=</code> / <code>?status=FLAGGED</code> .
HOW TO TEST	No automated test. Manual: <code>ALTER TABLE t ALTER COLUMN x TYPE text;</code> then <code>vdb ledger</code> .
STATUS & LIMITS	Text matching only (whole query, not per command); no dependency analysis.
ADDED IN	e42e792 ; security-definer db9dc0c .

H6 Ledger access (CLI / REST / MCP / UI / SDK)

Working

WHAT IT DOES	Read the ledger from anywhere.
HOW IT WORKS	CLI <code>ledger</code> (psql table, default 50 rows). REST <code>GET /api/branches/{name}/ledger</code> with filters <code>actor</code> , <code>table</code> , <code>risk</code> , <code>status</code> , <code>kind</code> , <code>since</code> , <code>until</code> , <code>limit</code> (≤ 2000), <code>offset</code> . MCP <code>changes</code> . Web Ledger page (L5). SDK <code>ledger()</code> .
HOW TO USE	<code>vdb ledger qa --limit 20</code> ; <code>curl -k -H "Authorization: Bearer \$KEY" "https://localhost:8080/api/branches/main/ledger?status=BLOCKED"</code>
HOW TO TEST	No automated test of the endpoints; manual curl above.
STATUS & LIMITS	Working. Any signed-in user can read any branch's ledger. No export format.
ADDED IN	e42e792 ; MCP d62c676 (PR #14).

H7 vdb ledger revert --to

Known issue

WHAT IT DOES	Despite the name, it does not revert a branch: it runs PITR of <code>main</code> into a throwaway container on port 5433.
HOW IT WORKS	Calls <code>branch.Restore(ts)</code> (D3). No branch argument.
HOW TO USE	<code>vdb ledger revert --to '<timestamp>'</code>
HOW TO TEST	Same as D3.
STATUS & LIMITS	Inherits the D3 credential bug; name overstates behaviour. Kept unchanged; Schema Ledger 2.0 Phase 4 adds a real "branch from before this entry".
ADDED IN	e42e792 .

Import & migration

Every import lands in a **new branch** (a copy-on-write clone of `main` whose `public` schema is wiped first), so a failed import never touches `main`. An import with 0 tables fails loudly. Code: `internal/branch/import.go`. Only the MongoDB path has end-to-end automated coverage (integration §9–10).

I1 From Postgres

Working

WHAT IT DOES	Copies a Postgres (or compatible) database, schema and data, into a new branch.
HOW IT WORKS	<code>loadPostgres : pg_dump <dsn> --no-owner --no-acl --no-comments psql</code> inside the target container.
HOW TO USE	<code>vdb import --from postgres://u:pw@host:5432/db [--as name] ; REST POST /api/import ; web Import.</code>
HOW TO TEST	Manual: start <code>postgres:16</code> on network <code>vectoradb</code> with a 2-row table, import, <code>SELECT count(*) = 2.</code>
STATUS & LIMITS	Working; no automated test; depends on <code>pg_dump</code> version compatibility.
ADDED IN	<code>44cc05c</code> .

I2 From MySQL ≤5.7 / MariaDB

Working

WHAT IT DOES	Migrates MySQL/MariaDB with type mapping.
HOW IT WORKS	<code>loadMySQL</code> builds a local <code>pgloader</code> image on first use and runs <code>pgloader <dsn> postgresql://...@vec-<target> ;</code> success judged by table count.
HOW TO USE	<code>vdb import --from mysql://u:pw@host:3306/db --as legacy (or mariadb://)</code>
HOW TO TEST	Manual: <code>mariadb:11</code> container with a table, import, query rows.
STATUS & LIMITS	Working; no automated test.
ADDED IN	<code>b842a28</code> ; hardening <code>c929eb5</code> .

I3 From MySQL 8.x

Working

WHAT IT DOES	Imports MySQL 8+ (whose auth <code>pgloader</code> can't handle).
HOW IT WORKS	<code>mysqlNeedsNative</code> detects ≥8; <code>loadMySQLNative</code> generates <code>CREATE TABLE</code> from <code>information_schema</code> (type map: <code>json</code> → <code>jsonb</code> , <code>decimal</code> kept, else <code>text</code>) and streams <code>mysqldump --no-create-info INSERTs</code> ; per-table progress.
HOW TO USE	<code>vdb import --from mysql://root:pw@host:3306/db --as m8</code>
HOW TO TEST	Manual: <code>mysql:8</code> with <code>json</code> + <code>decimal</code> columns; check <code>information_schema.columns</code> .
STATUS & LIMITS	Working; no automated test. Only columns, NOT NULL and PK are carried over (no other indexes, FKs or defaults).
ADDED IN	<code>c929eb5</code> .

I4 From MongoDB

Working

WHAT IT DOES	Turns each collection into a typed Postgres table with the exact collection name.
HOW IT WORKS	<code>loadMongo</code> : list collections with <code>mongosh</code> , export each as NDJSON (ObjectId → hex, Date → ISO), then load via the JSON path (I6).
HOW TO USE	<code>vdb import --from mongodb://host/db --as events</code>
HOW TO TEST	Integration §9, §10. Manual: <code>mongo:7</code> with a nested document; <code>\d</code> shows <code>jsonb</code> for objects, numeric for numbers.
STATUS & LIMITS	Working (the only import path with end-to-end tests).
ADDED IN	<code>b842a28</code> ; relational tables <code>f2c964e</code> .

I5 From a .sql dump

Partial

WHAT IT DOES	Runs a SQL dump into a new branch.
HOW IT WORKS	<code>loadSQL</code> pipes the file into <code>psql</code> in the container; branch named <code>import-<file></code> .
HOW TO USE	<code>vdb import --from ./dump.sql</code> ; <code>POST /api/import/file</code> ; web Import.
HOW TO TEST	Manual: dump with one table → branch <code>import-d</code> has it.
STATUS & LIMITS	Runs <code>psql</code> without <code>ON_ERROR_STOP</code> , so failing statements inside the dump don't fail the import. No automated test.
ADDED IN	44cc05c .

I6 From JSON / NDJSON

Partial

WHAT IT DOES	Loads a JSON array or NDJSON into a table with columns inferred from top-level keys.
HOW IT WORKS	<code>loadJSON</code> stages documents as <code>jsonb</code> , then <code>relationalizeJSON</code> picks a type per key (<code>_id</code> text; string→text; number→numeric; boolean; nested/mixed→ <code>jsonb</code>), column order <code>_id</code> then alphabetical.
HOW TO USE	<code>vdb import --from ./people.ndjson</code>
HOW TO TEST	Unit: <code>TestJSONColumn</code> , <code>TestSQLIdent</code> . Integration §10.
STATUS & LIMITS	A JSON array import silently stops at the first element it can't decode.
ADDED IN	44cc05c ; relationalization f2c964e .

I7 From CSV

Working

WHAT IT DOES	Loads a CSV into a table (one text column per header).
HOW IT WORKS	<code>loadCSV</code> : header → <code>CREATE TABLE</code> , rows → <code>\copy ... FORMAT csv</code> .
HOW TO USE	<code>vdb import --from ./people.csv</code>
HOW TO TEST	Manual: <code>printf 'id,Name\n1,a\n' > p.csv</code> , import, <code>SELECT "Name" FROM p</code> .
STATUS & LIMITS	All columns are text; a header containing a newline won't parse.
ADDED IN	44cc05c .

I8 Continuous replication & cutover

Partial

WHAT IT DOES	Copies a Postgres source's schema and keeps streaming changes for a zero-downtime switch; cutover stops replication.
HOW IT WORKS	<code>ImportContinuousTo</code> : schema-only dump, <code>CREATE PUBLICATION vdb_pub</code> on source (best effort), <code>CREATE SUBSCRIPTION vdb_sub</code> on target. <code>ImportCutover</code> drops the subscription.
HOW TO USE	<code>vdb import --from postgres://... --continuous --as live</code> then <code>vdb import-cutover live</code> . Web checkbox for postgres sources.
HOW TO TEST	Manual: source with <code>wal_level=logical</code> ; insert on source, see it on target (<code>pg_stat_subscription</code>).
STATUS & LIMITS	Cutover is CLI-only (no REST/web). No automated test. Fixed publication/subscription names.
ADDED IN	b842a28 .

I9 Guard handling during import

Working

WHAT IT DOES	Lets bulk loads run DDL the guardrail would block, while the ledger keeps recording — and can't leave a branch unguarded after a crash.
HOW IT WORKS	<code>setGuard</code> disables/enables <code>vdb_guard_start</code> around the load (deferred); loaders set <code>vdb.allow_destructive=on</code> ; <code>reconcileGuard</code> re-enables the guard whenever <code>EnsureRunning</code> restarts a branch.
HOW TO USE	Automatic.
HOW TO TEST	Manual: stop the engine mid-import, <code>vdb branch resume <target></code> , <code>SELECT evtenabled FROM pg_event_trigger WHERE evtname='vdb_guard_start' → 0</code> .
STATUS & LIMITS	Working.
ADDED IN	<code>b842a28</code> ; crash-safe <code>1884445</code> (PR #12).

I10 Live progress (CLI & SSE)

Working

WHAT IT DOES	Shows a live migration log and, where the source supports it, a progress bar.
HOW IT WORKS	<code>Progress{Log, Step}</code> ; the control plane streams Server-Sent Events <code>log</code> , <code>progress</code> , <code>done</code> , <code>error</code> . Step events from MySQL 8 (per table), MongoDB (per collection), pipeline models.
HOW TO USE	<code>curl -N -k -H "Authorization: Bearer \$KEY" -H 'Content-Type: application/json' -d '{"source":"mongodb://mongo-src/shop"}' https://localhost:8080/api/import</code>
HOW TO TEST	Manual curl above; watch <code>event: log / event: progress</code> .
STATUS & LIMITS	psql subprocess output goes to engine logs, not SSE.
ADDED IN	<code>f2c964e</code> .

I11 Import REST endpoints

Working

WHAT IT DOES	API entry points for imports (auth required).
HOW IT WORKS	<code>POST /api/import</code> body <code>{source, target, continuous}</code> — connection strings only (postgres, mysql, mariadb, mongodb). <code>POST /api/import/file</code> multipart <code>file</code> + <code>target</code> , kind from extension. Both stream SSE.
HOW TO USE	<code>curl -N -k -H "Authorization: Bearer \$KEY" -F file=@people.csv -F target=ppl https://localhost:8080/api/import/file</code>
HOW TO TEST	Manual curl; without a key → 401.
STATUS & LIMITS	Working. Target name not validated against the branch-name rule; OpenAPI documents the wrong field names (K2).
ADDED IN	<code>44cc05c</code> , <code>b842a28</code> .

I12 Web Import page

Working

WHAT IT DOES	"Migrate a database" form with a live migration console.
HOW IT WORKS	<code>web/src/pages/Import.tsx</code> : connection-string panel (continuous checkbox for postgres), file upload (<code>.sql.csv.json.ndjson.jsonl</code>), SSE console with progress, result with links to Console and Ledger.
HOW TO USE	<code>https://localhost:8080/import</code>
HOW TO TEST	Manual: upload a CSV and check the result panel.
STATUS & LIMITS	Footer mentions SQLite imports via the CLI, but no SQLite loader exists.
ADDED IN	<code>44cc05c</code> ; console <code>f2c964e</code> (PR #3).

I13 Exact identifier fidelity

Working

WHAT IT DOES	Source names like <code>leaseAiChats</code> or <code>userId</code> keep their exact case.
HOW IT WORKS	<code>sqlIdent</code> quotes and truncates to 63 bytes (tables, columns); <code>sanitizeIdent</code> only for branch names.
HOW TO USE	Automatic; quote camelCase in SQL: <code>SELECT "userId" ...</code>
HOW TO TEST	Unit: TestSQLIdent. Integration §10.
STATUS & LIMITS	Working.
ADDED IN	<code>f2c964e</code> .

ETL pipelines (experimental)

J1 Pipeline engine

Working

WHAT IT DOES	dbt-style extract → land raw → transform with SQL models → quality tests, into a fresh branch.
HOW IT WORKS	<code>RunPipeline (pipeline.go)</code> : delete + re-create the target branch, import the source, rename <code>public</code> → <code>raw</code> , run each model in order as <code>CREATE TABLE VIEW public."name" AS ... with {{ ref('m') }} / {{ source('t') }}</code> templating, then tests.
HOW TO USE	<code>vdb pipeline run spec.json [--as name]</code> (default <code>pl-<file></code> ; exit 1 on test failure).
HOW TO TEST	Unit: <code>TestRenderSQL</code> , <code>TestTestQuery</code> . Integration §9.
STATUS & LIMITS	No dependency graph (listed order), no incremental models, no scheduling. A run destroys any existing branch with the target name.
ADDED IN	<code>f2c964e</code> .

J2 Data-quality tests

Working

WHAT IT DOES	Assertions after transform: <code>not_null</code> , <code>unique</code> , <code>accepted_values</code> , <code>row_count_min</code> , <code>custom</code> .
HOW IT WORKS	<code>testQuery</code> builds a "count violating rows" query; a test passes when the count is 0. Failures mark the run failed but keep the data.
HOW TO USE	<code>"tests": [{"type":"unique","model":"stg","column":"city"}]</code>
HOW TO TEST	Unit: <code>TestTestQuery</code> . Integration §9 (failing <code>row_count_min</code> → exit 1, data kept).
STATUS & LIMITS	Working.
ADDED IN	<code>f2c964e</code> .

J3 Stored pipelines & run history

Working

WHAT IT DOES	Save pipelines per user, run them over the API, keep run history.
HOW IT WORKS	SQLite tables <code>pipelines</code> , <code>pipeline_runs</code> ; routes <code>GET/POST /api/pipelines</code> , <code>GET/PUT/DELETE /api/pipelines/{id}</code> , <code>GET .../runs</code> (last 50), <code>POST .../run</code> (SSE).
HOW TO USE	<code>curl -k -H "Authorization: Bearer \$KEY" -d '{"name":"shop etl","spec":{"...}}' https://localhost:8080/api/pipelines</code>
HOW TO TEST	Manual: create, run, <code>GET .../runs</code> shows <code>success</code> .
STATUS & LIMITS	No endpoint to read a run's log; a run whose process dies stays <code>running</code> .
ADDED IN	<code>f2c964e</code> .

J4 Pipeline editor (web)

Working

WHAT IT DOES	Create, edit, run and inspect pipelines in the browser.
HOW IT WORKS	<code>Pipelines.tsx</code> (list) and <code>PipelineEditor.tsx</code> (source, model cards, test cards, Load example, Save, Run with streaming console, run history).
HOW TO USE	<code>https://localhost:8080/pipelines</code> → New pipeline → Load example → Save → Run.
HOW TO TEST	Manual with the integration §9 Mongo data.
STATUS & LIMITS	Delete on the list has no confirmation.
ADDED IN	<code>f2c964e</code> .

APIs, SDKs & agents

K1 Control-plane REST API

Working

WHAT IT DOES

JSON management API over HTTPS on `:8080` (also serves the web UI).

HOW IT WORKS

`internal/controlplane/server.go`; `store.Authn` on `/api/*`; CORS for configured/localhost origins.

Routes	Purpose
<code>POST /auth/register login logout</code> , <code>GET /auth/me providers</code> , <code>GET /auth/oauth/{p}/{callback}</code>	Accounts (public)
<code>GET /api/openapi.yaml</code>	Spec (public)
<code>GET /api/status</code>	Health, branches, agents, HA, storage
<code>GET POST /api/branches</code> , <code>DELETE /api/branches/{n}</code> , <code>POST .../suspend resume</code>	Branches
<code>POST /api/branches/{n}/query</code>	SQL as <code>vdbclient</code> , 10s, ≤1000 rows, attributed to the user
<code>GET /api/branches/{n}/ledger</code> , <code>.../ledger/verify</code>	Schema Ledger
<code>POST /api/import</code> , <code>/api/import/file</code>	Import (SSE)
<code>/api/pipelines...</code>	Pipelines
<code>GET POST /api/keys</code> , <code>DELETE /api/keys/{id}</code>	API keys

HOW TO USE

`curl -k -H "Authorization: Bearer $KEY" https://localhost:8080/api/status`

HOW TO TEST

Unit: `TestNameValidation`. Integration §1 (uses plain http — test fix pending).

STATUS & LIMITS

Working. Not versioned (`/api/`, not `/api/v1/`).

ADDED IN

`a7580f6`; `TLS 0bd52f3`.

K2 OpenAPI spec

Partial

WHAT IT DOES

Machine-readable API description for client generators.

HOW IT WORKS

`openapi.yaml` (OpenAPI 3.1) embedded and served at `/api/openapi.yaml`; also documents agent routes.

HOW TO USE

`curl -k https://localhost:8080/api/openapi.yaml`

HOW TO TEST

Manual fetch.

STATUS & LIMITS

Out of date: `/api/import` documented as `{from, as}` (code reads `{source, target, continuous}`); create endpoints documented as 200 (code 201); `ledger since/until`, `/auth/*` and upload fields missing.

ADDED IN

`52b1fc5` / `cc5cbd7` (PR #15).

K3 Python SDK `vectoradb`

Working

WHAT IT DOES

Dependency-free client for the control plane (Apache-2.0).

HOW IT WORKS

`clients/python/vectoradb`: `VectoraDB(api_key, base_url, verify_tls)`; `status`, `branches`, `create_branch`, `delete_branch`, `suspend`, `resume`, `query`, `ledger`, `verify_ledger`.

HOW TO USE

`pip install ./clients/python`; `db = VectoraDB(api_key="vdb_...", verify_tls=False)`; `db.query("qa", "select 1")`

HOW TO TEST

No tests; manual snippet.

STATUS & LIMITS

Not on PyPI; no `import/pipeline/key/agent` methods.

ADDED IN

`52b1fc5`.

K4 TypeScript SDK @vectoradb/client

Working

WHAT IT DOES	The same client for Node and browsers (Apache-2.0).
HOW IT WORKS	<code>clients/typescript/src/index.ts</code> : <code>new VectoraDB(apiKey, baseUrl)</code> ; same methods (<code>createBranch</code> , <code>verifyLedger</code> , ...) using <code>fetch</code> .
HOW TO USE	<code>cd clients/typescript && npm install && npm run build</code> ; local self-signed cert needs <code>NODE_TLS_REJECT_UNAUTHORIZED=0</code> .
HOW TO TEST	No tests; manual Node script.
STATUS & LIMITS	Not published to npm.
ADDED IN	52b1fc5.

K5 Agent Branch API

Partial

WHAT IT DOES	A disposable database per AI agent over HTTPS on <code>:8088</code> .
HOW IT WORKS	<code>internal/agentapi</code> : <code>GET /healthz</code> (public), <code>GET /agents</code> , <code>POST /agents/{id}/branch</code> (creates <code>agent-<id></code> , returns DSN), <code>DELETE /agents/{id}/branch</code> . Cap <code>VECTORADB_AGENT_MAX</code> (50); TTL reaping with <code>VECTORADB_AGENT_TTL</code> .
HOW TO USE	<code>curl -k -H "Authorization: Bearer \$KEY" -X POST https://localhost:8088/agents/alice/branch</code>
HOW TO TEST	Integration §5 (uses plain http — test fix pending).
STATUS & LIMITS	DSN uses the superuser <code>vectoradb</code> and the container IP, so it only works inside the VM and bypasses the gateway (fix scheduled: Phase 1 H3). Cap and TTL count only running containers.
ADDED IN	a7580f6; cap/TTL e720c4e (PR #12).

K6 MCP server

Partial

WHAT IT DOES	Lets agent frameworks manage agent branches, run SQL and read/verify the ledger via the Model Context Protocol.
HOW IT WORKS	<code>internal/mcp</code> : JSON-RPC 2.0 over stdio (<code>initialize</code> , <code>tools/list</code> , <code>tools/call</code>). Tools: <code>create_branch</code> , <code>list_branches</code> , <code>delete_branch</code> , <code>run_sql</code> , <code>changes</code> , <code>verify_ledger</code> .
HOW TO USE	Configure an MCP client to launch command <code>vdb</code> with args <code>["mcp"]</code> .
HOW TO TEST	No tests. Manual: pipe <code>initialize</code> , <code>tools/list</code> , <code>tools/call run_sql</code> JSON lines into <code>vdb mcp</code> .
STATUS & LIMITS	<code>run_sql</code> runs as superuser with no actor (fix scheduled: Phase 1 H3). No auth (local privileges). No client config snippet in docs.
ADDED IN	d62c676 / ed5a379 (PR #14).

Web console

L1 Embedded single-origin UI

Working

WHAT IT DOES	The engine serves the React app itself at <code>https://localhost:8080</code> — no separate web server.
HOW IT WORKS	<code>web/embed.go</code> (<code>//go:build embedui</code>) embeds <code>web/dist</code> ; <code>serveUI</code> falls back to <code>index.html</code> . <code>make web-build</code> builds with same-origin API URLs; Linux release binaries use <code>-tags embedui</code> . <code>make web-dev</code> is deprecated (hot-reload only).
HOW TO USE	<code>vdb start</code> → open <code>https://localhost:8080</code> (accept the self-signed cert).
HOW TO TEST	Manual: open <code>/dashboard</code> directly and refresh.
STATUS & LIMITS	Working. <code>make web-dev</code> defaults to <code>http://localhost:8080</code> and needs <code>VITE_API_URL=https://localhost:8080</code> .
ADDED IN	4927095 ; React app 84741df .

L2 Login & signup

Working

WHAT IT DOES	Log in / sign up tabs, OAuth buttons when configured, redirect to Dashboard.
HOW IT WORKS	<code>/login</code> ; <code>RequireAuth</code> guards private routes; API client redirects to <code>/login</code> on 401.
HOW TO USE	<code>https://localhost:8080/login</code>
HOW TO TEST	Manual sign-up and logout.
STATUS & LIMITS	Working (OAuth caveat G5).
ADDED IN	235ff41 .

L3 Dashboard

Working

WHAT IT DOES	Live tiles (primary, branches, agent DBs, gateway, replica, storage) and a branch table with create, suspend, resume, delete and a copyable connection string.
HOW IT WORKS	Polls <code>/api/status</code> and <code>/api/branches</code> every 3s; offline banner when the API is unreachable.
HOW TO USE	<code>https://localhost:8080/dashboard</code>
HOW TO TEST	Manual: create a branch and see it appear.
STATUS & LIMITS	Working.
ADDED IN	84741df .

L4 SQL console & browser

Working

WHAT IT DOES	Schema sidebar, row browser (100/page), structure and index tabs, SQL editor (Cmd/Ctrl+Enter), row-as-JSON.
HOW IT WORKS	<code>Console.tsx</code> → <code>POST /api/branches/{name}/query</code> ; DDL attributed to the signed-in user.
HOW TO USE	<code>https://localhost:8080/console</code>
HOW TO TEST	Manual: <code>select 1</code> ; create a table and see it in the Ledger page.
STATUS & LIMITS	Working. 10s timeout, 1000-row cap.
ADDED IN	84741df .

L5 Ledger page

Partial

WHAT IT DOES	Browse the Schema Ledger per branch.
HOW IT WORKS	<code>Ledger.tsx</code> : branch, status (APPLIED/FLAGGED/BLOCKED), kind (human/agent) and actor filters; infinite scroll 25 rows at a time; columns Time, Actor, Tool, Change, Status.
HOW TO USE	<code>https://localhost:8080/ledger</code>
HOW TO TEST	Manual after a CREATE TABLE in the console.
STATUS & LIMITS	No table/risk/date filters (API supports them; README claims them), no verify button, statement/session not shown.
ADDED IN	<code>e42e792</code> .

L6 API keys page

Working

WHAT IT DOES	Create (shown once, copy button), list and revoke API keys.
HOW IT WORKS	<code>/keys</code> → <code>/api/keys</code> .
HOW TO USE	<code>https://localhost:8080/keys</code>
HOW TO TEST	Manual create + revoke.
STATUS & LIMITS	Working.
ADDED IN	<code>235ff41</code> .

L7 Landing, Guide & Docs pages

Partial

WHAT IT DOES	Public landing page, a developer guide (install, connect, CRUD, branches, agents, PDF download) and a docs page (CLI, REST, env tables with live status buttons).
HOW IT WORKS	<code>Landing.tsx</code> , <code>Guide.tsx</code> , <code>Docs.tsx</code> .
HOW TO USE	<code>https://localhost:8080/</code> , <code>/guide</code> , <code>/docs</code>
HOW TO TEST	Manual.
STATUS & LIMITS	Stale in places: Guide recommends <code>make web-dev</code> , omits <code>sslmode</code> , uses http for the agent API; Docs says <code>http://localhost:8080</code> and omits MCP, ledger, import and pipeline routes.
ADDED IN	<code>84741df</code> , <code>e9210fb</code> .

Build, CI & releases

M1 Makefile targets

Working

WHAT IT DOES	One place to build, test and release.
HOW IT WORKS	<code>build</code> , <code>vet</code> , <code>fmt</code> , <code>test</code> , <code>vm-build</code> (Lima, embedui), <code>integration</code> (Lima), <code>web-build</code> , <code>web-dev</code> (deprecated), <code>release</code> (5 binaries + docker context), <code>release-linux</code> , <code>wsl-distro</code> , <code>wsl-zfs</code> , <code>feature-doc</code> (renders this PDF).
HOW TO USE	<code>make test</code> · <code>make integration</code> · <code>make release VERSION=x.y.z</code> · <code>make feature-doc</code>
HOW TO TEST	CI runs build/vet/test/gofmt.
STATUS & LIMITS	Working. <code>release</code> prints an outdated ZFS-bundle note.
ADDED IN	<code>a7580f6</code> ; <code>feature-doc</code> added with this document.

M2 Linux CI

Working

WHAT IT DOES	Every push to main and every PR is built and tested on Linux.
HOW IT WORKS	<code>.github/workflows/ci.yml</code> : <code>go build</code> , <code>go vet</code> , <code>go test</code> , gofmt check.
HOW TO USE	Automatic on PRs.
HOW TO TEST	Open a PR and check the Actions tab.
STATUS & LIMITS	The integration suite does not run in CI (needs a VM).
ADDED IN	<code>797bc14</code> (PR #11).

M3 Windows CI

Working

WHAT IT DOES	Tests the Windows build and installer on every push/PR.
HOW IT WORKS	<code>windows-ci.yml</code> : <code>build/vet/test</code> , cross-compile, Pester (both files), <code>install.ps1</code> encoding + PS 5.1 parse; Linux job checks <code>make release assets</code> .
HOW TO USE	Automatic.
HOW TO TEST	Actions tab.
STATUS & LIMITS	No end-to-end WSL install test (needs nested virtualisation).
ADDED IN	<code>4fc8afb</code> (PR #1).

M4 Releases & GHCR image

Working

WHAT IT DOES	A <code>v*</code> tag publishes binaries, checksums and a multi-arch Postgres image.
HOW IT WORKS	<code>release.yml</code> : <code>make release</code> , verify assets, create (pre)release, <code>SHA256SUMS</code> , upload; image job builds <code>docker/postgres</code> for amd64+arm64 and pushes <code>ghcr.io/vectoradb/postgres-walg:16</code> and <code><tag></code> .
HOW TO USE	Push a tag <code>vX.Y.Z</code> (or run manually with a tag).
HOW TO TEST	Check the release page assets and <code>docker pull ghcr.io/vectoradb/postgres-walg:16</code> .
STATUS & LIMITS	Working. GHCR package must be made public manually the first time.
ADDED IN	<code>8cafdb6</code> (PR #2); image job <code>aae9e20</code> (PR #12).

M5 WSL distro & ZFS builds

Partial

WHAT IT DOES	Builds a prebuilt WSL distro image; legacy ZFS module bundle for WSL kernels.
HOW IT WORKS	<code>wsl-distro.yml</code> / <code>make wsl-distro</code> (Ubuntu + Docker + btrfs + engine + saved images); <code>wsl-zfs.yml</code> / <code>make wsl-zfs</code> (OpenZFS for the WSL kernel).
HOW TO USE	Tag push (distro) or manual dispatch.
HOW TO TEST	Actions artifacts.
STATUS & LIMITS	The distro output isn't downloaded by the installer and its preloaded image has the wrong tag; ZFS bundle is legacy (Windows uses btrfs).
ADDED IN	<code>d0c1f26</code> (PR #7); <code>8305e5b</code> (PR #1).

M6 Postgres image

Working

WHAT IT DOES	Stock Postgres 16 plus wal-g for archiving, backups and PITR.
HOW IT WORKS	<code>docker/postgres/Dockerfile</code> : <code>FROM postgres:16-bookworm</code> , <code>wal-g v3.0.9</code> , <code>restore-entrypoint.sh</code> .
HOW TO USE	Pulled automatically (C8).
HOW TO TEST	<code>docker run --rm ghcr.io/vectoradb/postgres-walg:16 wal-g --version</code>
STATUS & LIMITS	Working. No extensions added (pgvector is not included).
ADDED IN	<code>a7580f6</code> ; GHCR name <code>aae9e20</code> .

Test matrix

Every automated test and the feature it covers. Run: `make test` (unit, host) · `make integration` (Lima VM) · Pester via `windows-ci.yml`.

Test file	Tests	Covers
<code>cmd/vdb/main_test.go</code>	<code>TestAddrFlag</code> , <code>TestDurFlag</code> , <code>TestRestoreArg</code>	B1
<code>internal/auth/auth_test.go</code>	<code>TestPasswordLogin</code> , <code>TestAPIKeys</code> , <code>TestVerifyKeyConcurrent</code> , <code>TestSessions</code>	G1–G4
<code>internal/branch/branch_test.go</code>	<code>TestParsePublishedPort</code> , <code>TestDSN</code> , <code>TestAgentBranchName</code> , <code>TestContainerName</code>	C2, C4, K5
<code>internal/branch/pipeline_test.go</code>	<code>TestSQLIdent</code> , <code>TestRenderSQL</code> , <code>TestTestQuery</code> , <code>TestJSONColumn</code>	I6, I13, J1, J2
<code>internal/controlplane/server_test.go</code>	<code>TestNameValidation</code>	K1
<code>internal/daemon/daemon_test.go</code>	<code>TestStopTerminatesProcess</code>	B2
<code>internal/host/host_test.go</code>	<code>TestIsELF</code> , <code>TestBundledLinuxBinaryPrefersCache</code> , <code>TestRefreshEngineBinaryDisabled</code> , <code>TestDownloadFile</code>	A7
<code>internal/host/host_wsl_test.go</code>	<code>TestResolveWSLDistro</code> , <code>TestWSLArgs</code> , <code>TestDecodeWSLList</code> , <code>TestWinPathToMnt</code> , <code>TestParseKernelRelease</code> , <code>TestImportLocalFile</code>	A4, A6
<code>internal/proxy/proxy_test.go</code>	<code>TestBuildParseStartupRoundtrip</code> , <code>TestReadStartupSkipsSSL</code> , <code>TestReadStartupUpgradesTLS</code> , <code>TestReadStartupHandlesCancel</code> , <code>TestSendError</code>	F1, E2, F6, F7
<code>deploy/install.Tests.ps1</code> , <code>deploy/windows-install.Tests.ps1</code>	Arch/asset URLs, PATH, encoding, WSL independence, elevation/reboot probes, checksum verification, E2E (opt-in)	A2

Integration section (<code>scripts/integration_test.sh</code>)	Assertions	Covers
\$1 Fresh start + auth	unauthenticated API → 401; main ready; gateway rejects bad key; accepts API key	B2, G2, G3, F2, K1
\$2 Branch isolation	branch sees its row; main doesn't have the table	C1, C2
\$3 Time-travel / PITR	backup + <code>restore --to latest</code> → 3 rows	D1–D3
\$4 Suspend / resume	exited after suspend; running after resume	C2
\$5 Agent branch API	POST returns DSN; table created and read	K5
\$6 HA	1 streaming replica; write via gateway after failover	D4, F1
\$7 Reaper regression	standby still running; idle branch exited	C3, C5
\$8 Schema ledger	DDL attributed human; DROP blocked; BLOCKED recorded; DELETE blocked; chain intact	H1–H4
\$9 ETL pipeline	exit 0; raw tables; staged values; failing test → exit 1 with data kept	I4, J1, J2
\$10 Schema fidelity	exact <code>userId</code> column; nested → jsonb; model query returns 1 row	I4, I6, I13

Not covered by any automated test: MCP server, agent API handlers, OAuth, REST ledger/import/pipeline handlers, SDKs, web UI, per-user roles, SCRAM, storage quotas, non-Mongo imports.

Known issues

Found while building this inventory. Recorded, not fixed — each fix changes existing behaviour and needs explicit approval, except the three marked "scheduled".

1. **PITR restore broken on fresh installs** — hardcoded `minioadmin` credentials in `Restore`. *Scheduled: Schema Ledger 2.0 Phase 1 (H1)*. (D3, H7)
2. **Destructive-DDL override ungated** — any client can `SET vdb.allow_destructive=on`; its use isn't recorded. *Scheduled: Phase 1 (H2)*. (H4)
3. **Agents and MCP run as superuser** — Agent API DSN and MCP `run_sql` use `vectoradb`, so they can bypass the guard and append-only protection. *Scheduled: Phase 1 (H3)*. (K5, K6, H3)
4. Integration §1 and §5 call `http://` endpoints that now serve TLS (test-only fix planned).
5. `vdb branch suspend main` stops the primary and the gateway won't wake it. (C3)
6. `vdb ha enable` after a failover deletes the live primary (`vec-standby`); post-failover `ha disable` routes main to a stopped container. (D4)
7. `backup / restore` always target `vec-main`, even after a failover; PITR always fetches the LATEST base backup. (D2, D3)
8. Ledger verify can't detect deletion of the newest rows or a wiped table; a superuser can bypass the triggers. (H2)
9. `vdb ledger revert --to` doesn't revert a branch. (H7)
10. README documents `vdb branch diff` (doesn't exist) and ledger UI filters by table/risk (not in the UI). (L5)
11. OpenAPI spec disagrees with the code (import fields, status codes, missing params/routes). (K2)
12. `.sql` imports don't stop on error; JSON array imports stop silently at the first bad element; web Import mentions SQLite (no loader). (I5, I6, I12)
13. Continuous-import cutover is CLI-only. (I8)
14. Agent cap and TTL reaper only count running containers; agent DSN only reachable inside the VM. (K5)
15. OAuth defaults point at `http://localhost:8080` / `http://localhost:5173`. (G5)
16. `vdb vm` is listed as a command but not implemented. (B1)
17. Windows installer never downloads the prebuilt distro; its preloaded image tag doesn't match the engine's image name; setup summary omits the API key. (A2, A4, M5)
18. Web Guide/Docs pages are stale in places. (L7)
19. Storage quotas are ZFS-only and per-branch caps are opt-in. (C6)
20. The Postgres image has no pgvector. (M6)