



Soybean R0 and R0
Plant Production in
Controlled
Environments

**Bayer Russia Biotechnology Conference** 

**July 2023** 





### Soybean Production in Controlled Environments: Agenda

Topic 1	Overview of Soybean Production	
Topic 2	Soybean Non-R0 Plants for Seed Harvest	
Topic 3	Soybean R0 Plants for Seed Harvest	
Topic 4	Summary	




### Overview of Soybean Production: Williams 82 Germplasm

- Non-R0 (Inbred) production from verified seed source if used for transformation
- Non-R0 must be grown separate from all other soy to maintain purity
- Non-R0 plants may be used for cotyledon harvest or next generation seed production

V-Stage

- R0 soy production from transformed plantlets that pass molecular screening Days After Planting
- R0 plantlets are develop more slowly than Non-R0 plants
- R0 population is more diverse than Non-R0 population





### Environmental Control Parameters: Climate & Fertigation

- During rapid growth phase target even environment and increasing water/nutrients
- Plant growth slows with reproductive development
- As plant senescence (pod fill) occurs, target cooler and drier environment with less water/nutrients

Climate Controls	Vegetative	Reproductive	Range of Control Values
Average Daily Setpoint Temperature	Lower	Higher	26 – 28° C: higher temperatures at higher light levels
Day-Night Temperature Difference	Smaller	Larger	0 – 6° C
Start time for heating in the morning	Earlier	Later	4 hours before sunrise to sunrise
Afternoon temperature increase	None or small	Larger	0 – 2.5° C
Start Time for Day-Night Temperature Decrease	Earlier	Later	2 hours before to 2 hours after sunset
Speed of Day-Night Temperature Decrease	Slower	Faster	0 - 4° C per hour
Humidity deficit	Decrease	Increase	8 - 15 mB
Vapor Pressure Deficit	Lower	Higher	0.8 – 1.5 kPa
CO <sub>2</sub> enrichment	More	Less	350 – 1500 ppm: Higher CO <sub>2</sub> at higher light levels

Watering Controls	Vegetative	Reproductive	Range of Control Values
EC Growing Medium	Decrease	Increase	1.8 - 4.5 EC
EC Irrigation Water	Decrease	Increase	1.0 - 1.5 EC
Substrate Water Content	Increase	Decrease	45 - 65%
Day-Night Water Content Decrease	Decrease	Increase	2 - 10% (5 - 15% with Rockwool)
Irrigation cycle length and frequency	Short and Higher	Long and Lower	50 - 150 ml per dripper
Start time first irrigation	Earlier	Later	1 - 3 hours after sunrise/lights on
Stop time last irrigation	Later	Earlier	3 - 5 hours before sunset/lights off



### Soybean Non-R0 Plant Production: Williams 82 Germplasm

#### Items of Special Interest

- All atypical plants should be discarded immediately
- Soybean are photoperiodic plants.
  - Reproductive transition driven by night lengths above 12 hours for Williams 82.
  - Facilities must be able to exclude all light during induction
  - Amount of vegetative growth before induction drives yield potential.
- Williams 82 germplasm target induction at V6-V8 to deliver > 300 seed per plant











## Soybean Non-R0 Plant Production: Pre-Induction



Seed planted and Germinated in peat based media

28.3/24.4 C (83/76 F) D/N 16 hour photoperiod Fertilizer upon emergence with 15-5-15 at 1,000 µS



Transplanting

V3-V4 Transplant soybean 21 DAP Pot filled with peat based media Watered in with fertilizer 15-5-15 at 1,000 µS







Production

29.4/22.8 C (85/73 F) D/N
16 hour photoperiod
Fertilizer 15-5-15 at 1,000 µS
Wet/Dry cycles until well established roots
then even moisture
Induction at V6-V8



## Soybean Non-R0 Plant Production: Pre-Induction

Suggested watering schedule with peat-based media

- 400 ml per minute with weighted emitters
- Wet/Dry cycles after transplant to promote root development
- Even moisture after well rooted

Time (DAP)	Approx. developmental stage	Approx. Irrigation Time	Days
_			Every Third Day
5	VE	Sub-irrigation	(ETD)
10	VC	Sub-irrigation Sub-irrigation	Every Other Day (EOD)
10	VC	Sub-imgation	(LOD)
12	V1.	Sub-irrigation	Every day (ED)
15	V2	Sub-irrigation	Every day (ED)
18	V3	Sub-irrigation	Every day (ED)
21	V4 - Transplant	Hand water at Transplant	As needed
23	V5	30 sec, one time (8 am)	Every day (ED)
25 - 27	V6 – Start short-day Induction – Reduce light to 10-12 hours once plants reach V6 – V8	45 sec, one time (8 am)	Every day (ED)
30	V7 - Start short-day Induction – Reduce light to 10-12 hours once plants reach V6 – V8	30 sec, two times (8 am, 4 pm)	Every day (ED)
32	V8 - Start short-day Induction – Reduce light to 10-12 hours once plants reach V6 – V8	45 sec, two times (8 am, 4 pm)	



## Soybean Non-R0 Plant Production: Post-Induction







Production

29.4/22.8 C (85/73 F) D/N
12 hour photoperiod
Fertilizer 15-5-15 at 1,000 μS
Wet/Dry cycles until well
established roots then even
moisture
Induction at V6-V8

Dry Down

29.4/22.8 C (85/73 F) D/N 12 hour photoperiod Fertilizer 15-5-15 at 1,000 μS R6 (Pod yellowing) reduce water until 3-5% brown pods then irrigation off Harvest

29.4/22.8 C (85/73 F) D/N 12 hour photoperiod 5-10 days after irrigation off Pods open when squeezed



## Soybean Non-R0 Plant Production: Post-Induction

Suggested watering schedule with peat-based media

- 400 ml per minute with weighted emitters
- Even moisture after well rooted
- Lower water frequency as seed matures to promote drying

Time			
(DAP)	Approx. developmental stage	Approx. Irrigation Time	Days
	V8 - Start short-day Induction – Reduce light to 10-12		
32	hours once plants reach V6 – V8	45 sec, two times (8 am, 4 pm)	Every day (ED)
		30 sec, three times (8 am, 12	
35	V9	pm, 4 pm)	Every day (ED)
		45 sec, three times (8 am, 12	
38	R1	pm, 4 pm)	Every day (ED)
		30 sec, four times (7 am, 11 am,	
42	R2	2 pm, 6 pm)	Every day (ED)
		45 sec, four times (7 am, 11 am,	
45	R3	2 pm, 6 pm)	Every day (ED)
		45 sec, four times (7 am, 11 am,	
50	R4	2 pm, 6 pm)	Every day (ED)
		45 sec, four times (7 am, 11 am,	
<u> 55 – 58</u>	R5	2 pm, 6 pm)	Every day (ED)
		45 sec, three - four times (7 am,	
72	R6 – Begin to reduce irrigation	11 am, 2 pm, 6 pm)	Every day (ED)
		45 sec, three times (8 am, 12	
79	R 6.5	pm, 4 pm)	Every day (ED)
87 - 90	R7	45 sec, two times (8 am, 4 pm)	Every day (ED)
00		45 " (0 )	
93	R7	45 sec, one times (8 am)	Every day (ED)
05			
95	R7 - Cut Stem, Stop Irrigation	None	Every day (ED)
100 – 105	DO De in a	News	(FD)
100 – 105	R8 - Drying	None	Every day (ED)
107 -110	Do Day Boody to Throok	None	Event dev (ED)
107-110	R8, Dry - Ready to Thresh	None	Every day (ED)




## Soybean Non-R0 Plant Production: Mature Seed Path





29.4/22.8 C (85/73 F) D/N 12 hour photoperiod 5-10 days after irrigation off Pods open when squeezed









### Soybean Non-R0 Plant Summary: Williams 82 Germplasm

- R0 plants should be isolated from all other soybean plantings if seed will be used for cotyledon harvest or future transformation
- Environmental management early in crop cycle impacts later developmental stages
  - Atypical phenotypes should be removed as soon as detected
  - Williams 82 is sensitive to overwatering during lag and rapid growth phase
  - Williams 82 is sensitive to excessive salts in media. Avoid high EC levels.
- Soybeans are photoperiodic
  - > 12 hour photoperiod = vegetative for Williams 82
  - < 12 hour photoperiod = reproductive for Williams 82</li>
- Short-day induction (10 to 12 hour photoperiod) is necessary for flowering
  - Vegetative growth before induction determines final seed yield
- Seed not used for cotyledon harvest may be advanced to next generation for future use.
  - Must maintain isolation throughout life cycle to ensure Williams 82 purity



### Soybean R0 Plant Production: Williams 82 Germplasm

#### Items of Special Interest

- All atypical plants should be discarded immediately
- Soybean are photoperiodic plants.
  - Reproductive transition driven by night lengths above 12 hours for Williams 82.
  - Facilities must be able to exclude all light during induction
  - Amount of vegetative growth before induction drives yield potential.
- Williams 82 germplasm target induction for R0 plants at V6 to deliver ≈ 200 seed per plant







## Soybean R0 Plant Production: Pre-Induction





R0 events in peat-based plug



R0 Plug Acclimation



Selection

28.3/24.4 C (83/76 F) D/N 16 hour photoperiod Mist + Domes + Shade for first 8 days after plugging Fertilizer upon plugging with 15-5-15 at 1,000 µS



## Soybean R0 Plant Production: Pre-Induction

Suggested watering schedule with peat-based media

- Slow transition from tissue culture to greenhouse
- Day 1-8 mist, shade, and domes as needed especially in summer
- Sub-irrigation with 15-5-15 at 1,000 μS
- Frequency varies by plant size and season

Frequency
very 15 min, 30-
every 15 min,
every 15 min
Day (ED) as
е



### Soybean R0 Plant Production: Pre-Induction Acclimation





Molecular Selection

28.3/24.4 C (83/76 F) D/N 16 hour photoperiod Fertilizer 15-5-15 at 1,000 μS



V3-V5 Transplant soybean ≈ 28 days after plugging Pot filled with peat based media Watered in with fertilizer 15-5-15 at 1,000 µS

**Transplanting** 



29.4/22.8 C (85/73 F) D/N 16 hour photoperiod Fertilizer 15-5-15 at 1,000 μS Wet/Dry cycles early then even moisture Induction at V6

Production




# Soybean R0 Plant Production: Pre-Induction Production Suggested watering schedule with peat-based media

- 400 ml per minute with weighted emitters
- Wet/Dry cycles after transplant to promote root development
- Even moisture after well rooted

Time (DAP)	Approx. developmental stage	Approx. Irrigation Time	Days
28	V4 +	Hand Irrigation at Transplant	Every day (ED)
35 - 42		20-25 sec, one time (8 am)	Every Other Day (EOD)
43 - 49	V6 – Reduce light to 12 hours per day. Induction started.	30 sec, one time (8 am)	Every day (ED)
50 - 56		30 sec, two times (8 am, 4 pm)	Every day (ED)



## Soybean R0 Plant Production: Post-Induction






29.4/22.8 C (85/73 F) D/N 16 hour photoperiod Fertilizer 15-5-15 at 1,000 µS Wet/Dry cycles early then even moisture Induction at V6





29.4/22.8 C (85/73 F) D/N 12 hour photoperiod at V6 Fertilizer 15-5-15 at 1,000 µS Even moisture then decrease Trim excessive growth





29.4/22.8 C (85/73 F) D/N 12 hour photoperiod Fertilizer 15-5-15 at 1,000 μS R6 (Pod yellowing) reduce water until 3-5% brown pods then irrigation off





29.4/22.8 C (85/73 F) D/N 12 hour photoperiod 5-10 days after irrigation off Pods open when squeezed



# Soybean R0 Plant Production: Post-Induction Production Suggested watering schedule with peat-based media

- 400 ml per minute with weighted emitters
- Wet/Dry cycles after transplant to promote root development
- Even moisture after well rooted

Time (DAP)	Approx. developmental stage	Approx. Irrigation Time	Days
43 - 49	V6 – Reduce light to 12 hours per day. Induction started.	30 sec, one time (8 am)	Every day (ED)
50 - 56		30 sec, two times (8 am, 4 pm)	Every day (ED)
55 - 63	R1	45 sec, two times (8 am, 4 pm)	Every day (ED)
64 - 70		30 sec, three times (8 am, 12, pm, 4 pm)	Every day (ED)
71 - 77		30 sec, three times (8 am, 12, pm, 4 pm)	Every day (ED)
78 - 84		30 sec, three times (8 am, 12, pm, 4 pm)	Every day (ED)
85 - 91		30 sec, three times (8 am, 12, pm, 4 pm)	Every day (ED)
92 - 98	R5 to R6 - Begin decreasing water.	30 sec, three times (8 am, 12, pm, 4 pm)	Every day (ED)
99 - 106		30 sec, two times (8 am, 4 pm)	Every day (ED)
107 - 110		30 sec, one time (8 am)	Every day (ED)
111 - 117	R8 - Cut Stem, Stop Irrigation	30 sec, one time (8 am) then None	Every day (ED)
118 - 124	R8, Dry - Ready to Thresh	None	Every day (ED)




## Soybean R0 Plant Production: Mature Seed Path



Harvest

29.4/22.8 C (85/73 F) D/N 12 hour photoperiod 5-10 days after irrigation off Pods open when squeezed



**Threshing** 





### Soybean R0 Plant Summary: Williams 82 Germplasm

- R0 plants should be isolated from all other soybean plantings
- Environmental management early in crop cycle impacts later developmental stages
  - Atypical phenotypes should be removed as soon as detected
  - Williams 82 is sensitive to overwatering during lag and rapid growth phase
  - Williams 82 is sensitive to excessive salts in media. Avoid high EC levels.
- Soybeans are photoperiodic
  - > 12 hour photoperiod = vegetative for Williams 82
  - < 12 hour photoperiod = reproductive for Williams 82</li>
- Short-day induction (10 to 12 hour photoperiod) is necessary for flowering
  - Vegetative growth before induction determines final seed yield



#### **DISCLAIMER**

THE INFORMATION CONTAINED HEREIN IS EXPERIMENTAL IN NATURE AND IS PROVIDED "AS IS". BAYER MAKES NO REPRESENTATIONS AND EXTENDS NO WARRANTIES OF ANY KIND, EITHER EXPRESSED OR IMPLIED, AS TO THE MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE, OR THAT THE USE OF THE INFORMATION WILL NOT INFRINGE ANY THIRD-PARTY PATENT, COPYRIGHT, TRADEMARK, OR OTHER PROPRIETARY RIGHTS.



# Thank you!

Any questions?

