## Bài 1: Cấu hình Router cơ bản Nội dung:

- Hiểu được cách kết nối, tổ chức của một broadcast domain
- Cấu hình gán IP address cho Interface của Router
- Cấu hình cho phép kết nối tới Router từ xa thông qua Telnet
- Cấu hình bảo mật truy cập router
- Cấu hình các tham số cơ bản khác cho router
- Xem xét các thông số cơ bản của router bằng các lệnh "show"



Device	Interface	IP Address	Subnet Mask	Def. Gateway
R1	Fa0/0	192.168.1.1	255.255.255.0	N/A
	S0/0/0	192.168.2.1	255.255.255.0	N/A
R2	Fa0/0	192.168.3.1	255.255.255.0	N/A
	S0/0/0	192.168.2.2	255.255.255.0	N/A
PC1	N/A	192.168.1.10	255.255.255.0	192.168.1.1
PC2	N/A	192.168.3.10	255.255.255.0	192.168.3.1

- 1. Kết nối Router, PC, Switch như hình vẽ
- 2. Thực hiện Console tới router bằng cáp console và phần mềm Hyper Terminal
- **3.** Thực hiện xóa cấu hình khởi động của router và khởi động lại router như bên dưới, sau khi khởi động lại Router, chọn "**NO**" để vào User mode

## Router>enable

Router#

## Router#erase startup-config

Erasing the nvram filesystem will remove all files! Continue? [confirm] [OK]

Erase of nvram: complete

Router#

Router#reload

System configuration has been modified. Save? [yes/no]: no Proceed with reload? [confirm]

Would you like to enter the initial configuration dialog? [yes/no]: no Would you like to terminate autoinstall? [yes]: [Press Return] Press Enter to accept default.

Press RETURN to get started!