

The Rust Language

Nicholas Matsakis Mozilla Research nmatsakis@mozilla.com Felix S. Klock II Mozilla Research pnkfelix@mozilla.com

1. ABSTRACT

Rust is a new programming language for developing reliable and efficient systems. It is designed to support concurrency and parallelism in building applications and libraries that take full advantage of modern hardware. Rust's static type system is safe¹ and expressive and provides strong guarantees about isolation, concurrency, and memory safety.

Rust also offers a clear performance model, making it easier to predict and reason about program efficiency. One important way it accomplishes this is by allowing fine-grained control over memory representations, with direct support for stack allocation and contiguous record storage. The language balances such controls with the absolute requirement for safety: Rust's type system and runtime guarantee the absence of data races, buffer overflows, stack overflows, and accesses to uninitialized or deallocated memory.

Categories and Subject Descriptors

D.3.0 [E.2]: Programming Language Standards

Keywords

Rust, Systems programming, Memory management, Affine type systems

2. MEMORY MANIPULATION IN RUST

Rust is a new programming language targeting systemslevel applications. Like C++, Rust is designed to map directly to hardware, giving users control over the running time and memory usage of their programs. This implies, for example, that all Rust types can be allocated on the stack and that Rust never requires the use of a garbage collector or other runtime. Unlike C++, however, Rust also offers strong safety guarantees: pure Rust programs are guaran-

Permission to make digital or hard copies of all or part of this work for personal or classroom use is granted without fee provided that copies are not made or distributed for profit or commercial advantage and that copies bear this notice and the full citation on the first page. Copyrights for components of this work owned by others than ACM must be honored. Abstracting with credit is permitted. To copy otherwise, or republish, to post on servers or to redistribute to lists, requires prior specific permission and/or a fee. Request permissions from permissions@acm.org.

HILT 2014, October 18–21, 2014, Portland, OR, USA.
Copyright 2014 ACM 978-1-4503-3217-0/14/10 ...\$15.00.

http://dx.doi.org/10.1145/2663171.2663188.

teed to be free of memory errors (dangling pointers, double frees) as well as data races.

To control aliasing and ensure type soundness, Rust incorporates a notion of ownership into its type system. The unique owner of an object can hand that ownership off to new owner; but the owner may also hand off borrowed references to (or into) the object. These so-called borrows obey lexical scope, ensuring that when the original reference goes out of scope, there will not be any outstanding borrowed references to the object (otherwise known as "dangling pointers"). This also implies that when the owner goes out of scope or is otherwise deallocated, the referenced object can be deallocated at the same time. Rust leverages the latter property by adding support for user-defined destructors, enabling RAII² patterns as popularized by C++.

There are two flavors of borrows: mutable and immutable. Mutable references have a uniqueness property: There can be at most one active mutable borrow of a given piece of state (the owner itself is not allowed to mutate the object for the duration of the mutable borrow, nor are any of the inactive mutable borrows). Immutable references, on the other hand, can be freely copied, and their referents can be the source for new immutable borrows (subject to the restriction that all borrows still respect the lexical scope of the object's owner).

Rust functions can manipulate objects that are owned by local variables arbitrarily far up the control stack. Such functions need to support operations like *ptr1 = *ptr2; (writing the dereferenced value of ptr2 into the memory referenced by ptr1), but must also respect the rules: such assignment statements must be prohibited from injecting dangling pointers.

A function that manipulates borrowed references needs to constrain its input parameters to ensure that executing the function body will not break the rules. Rust has an optional explicit syntax for describing the *lifetime* bounds associated with a reference. Lifetime bounds mix together with *lifetime-polymorphism* (analogous to *type-polymorphism*) to provide functions the expressive power needed to manipulate memory references, without breaking type safety.

¹Type soundness has not yet been formally proven for Rust, but type soundness is an explicit design goal for the language.

²RAII: "Resource Acquisition Is Initialization"