

PSAppDeployToolkit Administrator Guide

[PowerShell App Deployment Toolkit Website](#)

Introduction

Toolkit Overview

The PowerShell App Deployment Toolkit provides a set of functions to perform common application deployment tasks and to interact with the user during a deployment. It simplifies the complex scripting challenges of deploying applications in the enterprise, provides a consistent deployment experience and improves installation success rates.

The PowerShell App Deployment Toolkit can be used to replace your WiseScript, VBScript and Batch script wrappers with one versatile, re-usable and extensible tool.

Features

- **Easy To Use** - Any PowerShell beginner can use the template and the functions provided with the Toolkit to perform application deployments.
- **Consistent** - Provides a consistent look and feel for all application deployments, regardless of complexity.
- **Powerful** - Provides a set of functions to perform common deployment tasks, such as installing or removing multiple applications, prompting users to close applications, setting registry keys, copying files, etc.
- **User Interface** - Provides user interaction through , customizable user interface dialog boxes, progress dialogs and balloon tip notifications that can all be branded with custom logo and banner.
- **Localized** - The UI is localized in several languages and more can easily be added using the XML configuration file.
- **Integration** - Integrates well with Microsoft MEMCM / SCCM / Configuration Manager, providing installation and uninstall deployment types with options on how to handle exit codes, such as suppressing reboots or returning a fast retry code.
- **Update-able** - The logic engine and functions are separated from per-application scripts, so that you can update the toolkit when a new version is released and maintain backwards compatibility with your deployment scripts.
- **Extensible** - The Toolkit can be easily extended to add custom scripts and functions.
- **Helpful** - The Toolkit provides detailed logging of all actions performed and even includes a graphical console to browse the help documentation for the Toolkit functions.

System Requirements and Support

The v3 release of the PowerShell App Deployment Toolkit has been developed (and tested) to work with a wide range of Operating Systems from Windows XP to Windows 10 (and their Windows Server equivalents) in order to provide enterprise-wide compatibility.

The system requirements are as follows:

- PowerShell 2.0

- Windows NT 5.1 and above

While we have attempted to maintain this backwards compatibility through the life cycle of the toolkit, the degree of testing performed across older Operating Systems such as XP and Vista is limited as the bulk of testing is performed on the latest OS versions. However, the toolkit has widespread adoption in the enterprise from SMEs to large multinationals so there is safety in numbers and the assurance that the toolkit has been put through its paces VERY extensively on a large number of Windows clients around the globe.

We have no way of knowing exactly how many Windows clients it has been used on, but sometime in 2016 we were aware of the PowerShell App Deployment Toolkit being used to deploy software on a rough count of 3.5 million endpoints (based on companies we know using it and their total number of staff, or where we have explicitly given that number for a company).

Donations

We have invested our spare time in the creation and ongoing development, maintenance and support of this community tool on a voluntary basis - it is not part of our day jobs. Donations to the project are welcome, please visit the following page for details on making a contribution:

<http://psappdeploytoolkit.com/donate>

Licensing

PowerShell App Deployment Toolkit - Provides a set of functions to perform common application deployment tasks on Windows.

Copyright (C) 2020 - Sean Lillis / Dan Cunningham.

This program is free software: you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation, either version 3 of the License, or any later version. This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this program. If not, see <http://www.gnu.org/licenses/>.

Toolkit Functionality

User Experience Features

- An interface to prompt the user to close specified applications that are open prior to starting the application deployment. The user is prompted to save their documents and has the option to close the programs themselves, have the toolkit close the programs, or optionally defer. Optionally, a countdown can be displayed until the applications are automatically closed.
- The ability to allow the user to defer an installation X number of times, X number of days or until a deadline date is reached.
- The ability to prevent the user from launching the applications that need to be closed while the application installation is in progress.
- An indeterminate progress dialog with customizable message text that can be updated throughout the deployment.
- A restart prompt with an option to restart later or restart now and a countdown to automatic restart.

- The ability to notify the user if disk space requirements are not met.
- Custom dialog boxes with options to customize title, text, buttons & icon.
- Balloon tip notifications to indicate the beginning and end of an installation and the success or failure of an installation.
- Branding of the above UI components using a custom logo icon and banner for your own Organization.
- The ability to run in interactive, silent (no dialogs) or non-interactive mode (default for running MEMCM task sequence or session 0).
- The UI is localized into several languages and more can be easily added using the XML configuration file.

Custom PowerShell Cmdlets to simplify deployments

- Provides extensive logging of both the Toolkit functions and any MSI installation / uninstallation.
- Provides the ability to execute any type of setup (MSI or EXEs) and handle the return codes.
- Mass remove MSI applications with a partial match (e.g. remove all versions of all MSI applications which match "Office")
- Perform MEMCM actions such as Machine and User Policy Refresh, Inventory Update and Software Update
- Supports installation of applications on Citrix / Remote Desktop Session Host Servers
- Update Group Policy
- Copy / Delete Files
- Get / Set / Remove Registry Keys and Values
- Get / Set INI File Keys and Values
- Check File versions
- Pin or Unpin applications to the Start Menu or Task Bar
- Create Start Menu Shortcuts
- Register / Unregister DLL files
- Refresh desktop icons / environment variables
- Test network connectivity
- Test power connectivity
- Check whether a PowerPoint slide show is running in full screen presentation mode

MEMCM / SCCM / Config Manager Integration

- Handles MEMCM exit codes, including time sensitive dialogs supporting "MEMCM Fast Retry" - providing more accurate Reporting (no more Failed due to timeout errors).
- Ability to prevent reboot codes (3010) from being passed back to MEMCM, which would cause a reboot prompt.
- Supports the MEMCM application model by providing an install and uninstall deployment type for every deployment script.
- Bundle multiple application installations to overcome the supported limit of 5 applications in the MEMCM application dependency chain.
- Compared to compiled deployment packages, e.g. WiseScript, the Toolkit utilizes the MEMCM cache correctly and MEMCM Distribution Point bandwidth more efficiently by using loose files.

Help

- A graphical console to easily browse the Toolkit Cmdlet documentation.
 - Further documentation available on GitHub Wiki.
 - Complete documentation included as PDF for use on e-readers / offline.
-

Toolkit Composition

Files Structure

The toolkit is comprised of the following files:

File Name	Description
<i>Deploy-Application.ps1</i>	Performs the actual install / uninstall and is the only file that needs to be modified, depending on your level of customization.
<i>Deploy-Application.exe</i>	An optional executable that can be used to launch the <i>Deploy-Application.ps1</i> script without opening a PowerShell console window. Supports passing command-line parameters to the script.
<i>AppDeployToolkitMain.ps1</i>	Contains all of the functions and logic used by the installation script. By Separating the logic from the installation script, we can obfuscate away the complex code and make enhancements independently of the installation scripts that contain per-application actions.
<i>AppDeployToolkitConfig.xml</i>	Contains configurable options referenced by the <i>AppDeployToolkitMain.ps1</i> script, such as MSI switches and User Interface messages, which are customizable and localized in several languages. This is intended to be a static file that is configured once, not on a per-application basis.
<i>AppDeployToolkitExtensions.ps1</i>	This is an optional PowerShell script that can be used to extend the toolkit functionality with custom functions. It is automatically dot-sourced by the <i>AppDeployToolkitMain.ps1</i> script.
<i>AppDeployToolkitHelp.ps1</i>	This is a script that displays a help console to browse the functions included in the Toolkit and copy and paste examples in to your deployment script.

Folders Structure

The Root folder contains the *Deploy-Application.exe* and *Deploy-Application.ps1* files. The *Deploy-Application.ps1* file is the only file that should be modified on a per-application basis.

The directories below contain the installation files and supporting files referenced by the toolkit.

Folder Name	Description
<i>AppDeployToolkit</i>	Contains the Toolkit dependency files.
<i>Files</i>	Contains the primary installation files, e.g. MSI file.
<i>SupportFiles</i>	Contains any supporting resources or assets, e.g. files you need to copy to the target machine using the Toolkit during deployment.

Toolkit User Interface

The user interface consists of several components detailed below. The user interface can be branded with a custom logo and banner.

All of the UI components include message text that is customizable in the *AppDeployToolkitConfig.xml*. The UI has been localized in 11 different languages: English, French, Spanish, Portuguese, German, Italian, Dutch, Swedish, Danish, Norwegian and Japanese. Additional languages can be easily added in the XML configuration file.


The language used by the Toolkit UI is selected automatically based on the language culture of the operating system, so the same *AppDeployToolkitConfig.xml* file can be used in a multi-language environment.

The user interface can be suppressed by specifying the deploy mode parameter as follows:

```
Deploy-Application.ps1 -DeployMode "Silent"
```

Installation Progress

The installation progress message displays an indeterminate progress ring to indicate an installation is in progress and display status messages to the end user. This is invoked using the `Show-InstallationProgress` Function.




The progress message can be dynamically updated to indicate the stage of the installation or to display custom messages to the user, using the `Show-InstallationProgress` function.





Installation Welcome Prompt


The application welcome prompt can be used to display applications that need to be closed, an option to defer and a countdown to closing applications automatically. Use the `Show-InstallationWelcome` function to display the prompts shown below.



Welcome prompt with close programs option and defer option:



Welcome prompt with close programs options and countdown to automatic closing of applications:




Welcome prompt with just a defer option:



Block Application Execution

If the block execution option is enabled (see `Show-InstallationWelcome` function), the user will be prompted that they cannot launch the specified application(s) while the installation is in progress. The application will be unblocked again once the installation has completed.




Disk Space Requirements

If the `checkDiskSpace` parameter is used with the `show-InstallationWelcome` function and the disk space requirements are not met, the following prompt will be displayed and the installation will not proceed.




Custom Installation Prompt

A custom prompt with the toolkit branding can be used to display messages and interact with the user using the `show-InstallationPrompt` function. The title and text is customizable and up to 3 customizable buttons can be included on the prompt as well as optional system icons, e.g.




Additionally, the prompt can be displayed asynchronously, e.g. to display a message at the end of the installation but allow the installation to return the exit code to the parent process without waiting for the user to respond to the message.




Installation Restart Prompt

A restart prompt can be displayed with a countdown to automatic restart using the `show-InstallationRestartPrompt`. Since the restart prompt is executed in a separate PowerShell session, the toolkit will still return the appropriate exit code to the parent process.




Balloon Tip Notifications

Balloon tip notifications are displayed in the system tray automatically at the beginning and end of the installation. These can be turned off in the XML configuration.




Custom Dialog box

A generic dialog box to display custom messages to the user without the toolkit branding using the function `Show-DialogBox`. This can be customized with different system icons and buttons.



Toolkit Help Console

The PowerShell App Deployment Toolkit Help Console. This is a separate script and can be invoked by running `AppDeployToolkitHelp.ps1`



Using The Toolkit

The `Deploy-Application.ps1` script is the only one you need to modify to deploy your application.

The script is broken down into the following sections:

Initialization - Variables such as App Vendor, App Name, App Version

Pre-Installation - Close applications, uninstall or clean-up previous versions

Installation - Install the primary application, or components of the application

Post-Installation - Drop additional files, registry tweaks

Uninstallation - Uninstall/rollback the changes performed in the install section.

Deploying an Application

There are two ways to launch the toolkit for deployment of applications.

- Launch `Deploy-Application.ps1` PowerShell script as administrator.
- Launch `Deploy-Application.exe` as administrator. This will launch the `Deploy-Application.ps1` PowerShell script without opening a PowerShell command window. Note, if the x86 PowerShell is required (for example, if CAPICOM or another x86 library is needed), launch `Deploy-Application.exe /32`.

Examples

Deploy an application for installation

```
Deploy-Application.ps1
```

Deploy an application for uninstallation in silent mode

```
Deploy-Application.ps1 -DeploymentType 'Uninstall' -DeployMode 'Silent'
```

Deploy an application for uninstallation using PowerShell x86, suppressing the PowerShell console window and deploying in silent mode.

```
Deploy-Application.exe /32 -DeploymentType 'Uninstall' -DeployMode 'Silent'
```

Deploy an application for installation, suppressing the PowerShell console window and allowing reboot codes to be returned to the parent process.

```
Deploy-Application.exe -AllowRebootPassThru
```

Deploy an application with a custom name instead of *Deploy-Application.ps1*.

```
Deploy-Application.exe 'Custom-Script.ps1'
```

Remove an application with a custom name and custom location for the script file.

```
Deploy-Application.exe -Command 'C:\Testing\Custom-Script.ps1' -DeploymentType 'Uninstall'
```

Toolkit Parameters

The following parameters are accepted by *Deploy-Application.ps1*:

DeploymentType

Specify whether to install or uninstall the application.

```
-DeploymentType 'Install' ## default
```

```
-DeploymentType 'Uninstall'
```

DeployMode

Specify the installation will be run in Interactive, Silent or NonInteractive mode:

- Interactive = Shows dialogs
- NonInteractive = Very silent, i.e. no blocking apps. This is automatically set if it is detected that the process is not running in the user session and it is not possible for anyone to provide input using a mouse or keyboard.
- Silent = No dialogs (progress and balloon tip notifications are suppressed)

```
-DeployMode 'Interactive' ## default
```

```
-DeployMode 'Silent'
```

```
-DeployMode 'NonInteractive'
```

AllowRebootPassthru

Specify whether to allow the 3010 exit code (reboot required) to be passed back to the parent process (e.g. MEMCM) if detected during an installation. If a 3010 code is passed to MEMCM, the MEMCM client will display a reboot prompt. If set to false, the 3010 return code will be replaced by a "0" (successful, no restart required).

```
-AllowRebootPassThru $true ## default
```

```
-AllowRebootPassThru $false
```

TerminalServerMode

Changes to user install mode and back to user execute mode for installing/uninstalling applications on Remote Desktop Session Host/Citrix servers

```
-TerminalServerMode $true ## default
```

```
-TerminalServerMode $false
```

DisableLogging

Disables logging to file for the script.

```
-DisableLogging
```

This is a switch parameter, so setting this enables it. When not present, the default is false.

Customizing the Toolkit

Aside from customizing the *Deploy-Application.ps1* script to deploy your application, no configuration is necessary out of the box. The following components can be configured as required:

AppDeployToolkitConfig.xml

Configure the default UI messages, MSI parameters, log file location, whether Admin rights should be required, whether log files should be compressed, log style (CMTrace or Legacy), max log size, whether debug messages should be logged, whether log entries should be written to the console, whether toolkit should re-launch as elevated logged-on console user when in SYSTEM context, whether toolkit should fall back to SYSTEM context if failure to launch toolkit as user, and whether toolkit should attempt to launch as a non-console logged on user (e.g. user logged on via terminal services) when in SYSTEM context.

AppDeployToolkitLogo.ico

To brand the balloon notifications and UI window title bars with your own custom/corporate logo, replace the *AppDeployToolkitLogo.ico* file with your own .ico file (retaining the file name)

AppDeployToolkitBanner.png

To brand the toolkit UI prompts with your own custom/corporate banner, replace the *AppDeployToolkitBanner.png* file with your own .png file (retaining the file name). The file must be in PNG format and must be 450 x 50 in size.

Logging

The toolkit generates extensive logging for all toolkit and MSI operations.

The default log directory for the toolkit and MSI log files can be specified in the XML configuration file. The default directory is *C:\Windows\Logs\Software*.

The toolkit log file is named after the application with _PSAppDeployToolkit appended to the end, e.g.

- *Oracle_JavaRuntime_1.7.0.17_EN_01_PSAppDeployToolkit.log*

All MSI actions are logged and the log file is named according to the MSI file used on the command line, with the action appended to the log file name. For uninstallations, the MSI product code is resolved to the MSI application name and version to keep the same log file format, e.g.

- *Oracle_JavaRuntimeEnvironmentx86_1.7.0.17_EN_01_Install.log*
- *Oracle_JavaRuntimeEnvironmentx86_1.7.0.17_EN_01_Repair.log*
- *Oracle_JavaRuntimeEnvironmentx86_1.7.0.17_EN_01_Patch.log*
- *Oracle_JavaRuntimeEnvironmentx86_1.7.0.17_EN_01_Uninstall.log*

Log Compression

One of the Toolkit Options in the *AppDeployToolkitConfig.xml* file is CompressLogs. Enabling this option will create a temporary logging folder where you can save all of the log files you want to include in the single ZIP file that will be created from this folder.

To enable the CompressLogs, set the follow option in *AppDeployToolkitConfig.xml* to True:

```
<Toolkit_CompressLogs>True</Toolkit_CompressLogs>
```

When set to True, the following happens:

- Both toolkit and MSI logs are temporally placed in \$envTemp\$installName which gets cleaned up at the end of the install.
- At the end of the install / uninstall, the logs are compressed into a new zip file which is placed in the LogFolder location in the config file.
- The Zip file name indicates whether it is an Install / Uninstall and has the timestamp in the filename so previous logs do not get overwritten.
- If your package creates other log files, you can send them to the temporary logging folder at \$envTemp\$installName.

Zero-Configuration MSI Deployment

The toolkit has a zero-config MSI install feature which allows you to quickly execute an installation with zero configuration of the *Deploy-Application.ps1* file. To use this feature:

1. Place your MSI file into the *Files* directory of the toolkit. This method only support the installation of one MSI, so if more than one MSI is found, then only the first one is selected.
2. If you have an MST file, then place it into the *Files* directory of the toolkit. The MST file must have the same name as the MSI file. For example, if your MSI file name is *test01.msi*, then the MST file must be named *test01.mst*.
3. If you have any MSP files, then place it into the *Files* directory of the toolkit. You can place more than one MSP file in the folder, but you must name the files in alphabetical order to control the order in which they are installed. MSP file will be installed in alphabetical order.

Example Deployments using the Toolkit


Adobe Reader - Deployment Script

In this example, we will build an Adobe Reader installation which provides the following benefits over using a standard MSI based MEMCM deployment:

- The ability to defer the installation up to 3 times
- The ability to close any applications that could cause errors during the installation
- Verification that the required disk space is available
- Full removal of any previous version of Adobe Reader (to prevent issues sometimes seen when doing an MSI upgrade, i.e. Missing previous installation source files)
- Installation of any subsequent patches required after the base MSI installation

This example is provided as a script with the toolkit, in the *Examples* folder.

- Copy the application source files in to the *Files* directory, e.g.



- Customize the *Deploy-Application.ps1* script using the example code below
- Install the application by running:

```
Deploy-Application.exe
```

- Uninstall the application by running:

```
Deploy-Application.exe -DeploymentType "Uninstall"
```

Initialization

Populate these variables with the application and script details:

```
$appVendor = 'Adobe'  
$appName = 'Reader'  
$appVersion = '11.0.3'  
$appArch = ''  
$appLang = 'EN'  
$appRevision = '01'  
$appScriptVersion = '1.0.0'  
$appScriptDate = '08/07/2013'  
$appScriptAuthor = 'Your Name'
```

Pre-Install

Copy the following into the Pre-Install section:

```
## Prompt the user to close the following applications if they are running and  
## allow the option to defer the installation up to 3 times:  
Show-InstallationWelcome -CloseApps 'iexplore,AcroRd32,cidaemon' -AllowDefer -  
DeferTimes 3  
  
## Show Progress Message (with the default message)  
Show-InstallationProgress  
  
## Remove any previous versions of Adobe Reader  
Remove-MSIApplications -Name 'Adobe Reader'
```

Installation

Copy the following into the Installation section:

```
## Install the base MSI and apply a transform  
Execute-MSI -Action Install -Path 'Adobe\Reader\_11.0.0\_EN.msi' -Transform  
'Adobe\Reader\_11.0.0\_EN\_01.mst'  
  
## Install the patch  
Execute-MSI -Action Patch -Path 'Adobe\Reader\_11.0.3\_EN.msp'
```

Post-Installation

Copy the following into the Post-Install section:

```
## No actions required here
```

Uninstallation

Copy the following into the Uninstallation section:

```

## Prompt the user to close the following applications if they are running:
Show-InstallationWelcome -CloseApps 'iexplore,AcroRd32,cidaemon'


## Show Progress Message (with a message to indicate the application is being
uninstalled)
Show-InstallationProgress -StatusMessage "Uninstalling Application
$installTitle. Please wait..."

## Remove this version of Adobe Reader
Execute-MSI -Action Uninstall -Path '{AC76BA86-7AD7-1033-7B44-AB0000000001}'


```

Adobe Reader - MEMCM Package Deployment


- Copy the installation files to a network location accessible by MEMCM.
- Create a new Package:




- Set the package source folder accordingly:




- Accept the defaults for the rest of the package (or modify according to your environment)
- Distribute the content of the package to the relevant Distribution Points
- Create a new Program for the package:




- Accept the defaults for the requirements of the program (or modify according to your environment)
- On the Environment page, ensure you use a combination of settings that allows the user to interact with the application. Failure to do so will result in the application installing silently:




- Accept the defaults for the rest of the program (or modify according to your environment)
- Create a new Advertisement for the Package and set your target collection accordingly:



- Set a recurring schedule for the Mandatory Assignment. This dictates how frequently the application should attempt to install. Additionally, ensure that "Rerun if failed previous attempt" is enabled. These settings are required when using the deferral system and ensure that if a user defers the install, the install will retry after the specified interval:




- When prompted with the following dialog box, select Yes:




- Accept the defaults for the rest of the advertisement (or modify according to your environment). The deployment should start on your target machines shortly.

Adobe Reader - MEMCM Application Model Deployment

- Copy the installation files to a network location accessible by MEMCM.
- Create a new Application and manually specify the application information:




- Populate the application details accordingly:




- Populate the application catalog details if required

- Add a new Deployment Type and manually specify the deployment type information:



- Populate the deployment type details accordingly:




- Set the content location. Additionally, set the Install and Uninstall programs accordingly. They should be:

```
Deploy-Application.exe -DeploymentType "Install"
```


And:

```
Deploy-Application.exe -DeploymentType "Uninstall"
```


respectively.




- Create a new detection rule. Specify the base MSI product code and modify the Version to be the same as the final version after all patches are installed:




- On the User Experience page, ensure you use a combination of settings that allows the user to interact with the application. Failure to do so will result in the application installing silently:




- Leave the requirements page blank (or modify according to your environment)
- Leave the software dependencies page blank (or modify according to your environment)
- Accept the defaults to create the Application
- Deploy the Application:




- Select the relevant Distribution Points:




- Configure deployment settings according to whether it should be a mandatory or app catalogue based deployment:



- Specify the deployment schedule:



- Specify User notification settings. In order to prevent excess noise, we recommend only showing notifications for computer restarts:



- Accept the defaults for the rest of the Deployment (or modify according to your environment)

Important note regarding MEMCM Application Model and Deferrals

The MEMCM Application Model does not have the flexibility to schedule Mandatory Assignments on a recurring schedule like MEMCM packages do. Instead, this is determined by the frequency of Software Deployment evaluation cycle in the MEMCM Agent Custom Settings. You can modify this to reduce the time from the default of once a day, however this may increase the load on your MEMCM servers and clients, and is not configurable on a per application basis:

Office 2013 SP1 - Advanced Deployment Script

This example is provided as a script with the toolkit, in the *Examples* folder. This provides a number of benefits over the standard Microsoft Office Setup Bootstrapper:

- A component based architecture so that core products can be installed, and subsequent components can be installed using the same package with different command-line switches
- The ability to defer the installation up to 3 times
- The ability to close any applications that could cause errors during the installation
- Verification that the required disk space is available
- Full removal of any previous version of Microsoft Office 2007, 2010 or 2013
- Installation of any subsequent patches required after the base installation
- Activation of Microsoft Office components

Note: Office requires a number of modifications in order to install. Please refer to Microsoft's documentation on configuration. This installation script tries to take a lot of work out of the process for you, but you still need to know what you're doing in order to set it up correctly.

The folder structure is laid out as follows:

- *Files*
 - Office installation files should be placed here
 - Office Configuration MSP created with the Office Customisation Tool should be placed in the *Config* subfolder and be named *Office2013ProPlus.MSP*. Modify the script accordingly if you wish to change. For a basic MSP, you should probably configure Access, Word, Excel and PowerPoint to be the only core applications to install. We can add everything else as components.
 - Customised *Config.xml* file should be edited in *ProPlus.WW* subfolder. At a minimum, you should modify the settings as follows:
 - Display Level = "none"
 - CompletionNotice = "no"
 - SuppressModal = "yes"
 - NoCancel = "yes"
 - AcceptEula = "yes"
 - Security updates and service pack extracted MSPs should be placed in the *Updates* subfolder.
 - Contains custom *Config.XML* files which are used to add specific components that might be considered unnecessary in a standard Office install, but could be added later using command-line switches
 - Contains Office Scrub tools for Office 2007, 2010 and 2013
- *SupportFiles*
 - Contains custom *Config.XML* files which are used to add specific components that might be considered unnecessary in a standard Office install, but could be added later using command-line switches
 - Contains Office Scrub tools for Office 2007, 2010 and 2013

Once the folder structure is laid out correctly and the custom *Deploy-Application.ps1* is added (as well as the AppDeployToolkit files themselves), the following command-lines are valid:

- Installs Office 2013 with core products

```
Deploy-Application.exe
```

- Installs Office 2013 with core products and InfoPath

```
Deploy-Application.exe -AddInfoPath
```

- Installs InfoPath to an existing Office 2013 installation

```
Deploy-Application.exe -AddComponentsOnly -AddInfoPath
```

Reference - Toolkit Exit Codes

The toolkit has a number of internal exit codes for any issues that may occur.

Exit Code	Description
60000-68999	Reserved for built-in exit codes in <i>Deploy-Application.ps1</i> , <i>Deploy-Application.exe</i> , and <i>AppDeployToolkitMain.ps1</i> .
69000 - 69999	Recommended for user customized exit codes in <i>Deploy-Application.ps1</i> .
70000 - 79999	Recommended for user customized exit codes in <i>Deploy-Application.ps1</i> .
60001	An error occurred in <i>Deploy-Application.ps1</i> . Check your script syntax use.
60002	Administrator privileges required for <code>Execute-ProcessAsUser</code> function.
60003	Failure when loading .NET Winforms / WPF Assemblies.
60004	Failure when displaying the Blocked Application dialog.
60005	AllowSystemInteractionFallback option was not selected in the config XML file, so toolkit will not fall back to SYSTEM context with no interaction.
60006	Failed to export the schedule task XML file in <code>Execute-ProcessAsUser</code> function.
60007	<i>Deploy-Application.ps1</i> failed to dot source <i>AppDeployToolkitMain.ps1</i> either because it could not be found or there was an error while it was being dot sourced.
60008	The <code>-UserName</code> parameter in the <code>Execute-ProcessAsUser</code> function has a default value that is empty because no logged in users were detected when the toolkit was launched.
60009	<i>Deploy-Application.exe</i> failed before <i>PowerShell.exe</i> process could be launched.
60013	If <code>Execute-Process</code> function captures an exit code out of range for int32 then return this custom exit code.

Reference - Toolkit Variables

The toolkit has a number of internal variables which can be used in your script. Outlined below are each of them:

Variable	Description
Toolkit Name	
\$appDeployToolkitName	Short-name of toolkit without spaces
\$appDeployMainScriptFriendlyName	Full name of toolkit including spaces
Script Info	
\$appDeployMainScriptVersion	Version number of the toolkit
\$appDeployMainScriptMinimumConfigVersion	Minimum version of the config XML file required by the toolkit
\$appDeployMainScriptDate	Date toolkit was last modified
\$appDeployMainScriptParameters	Contains all parameters and values specified when toolkit was launched
Datetime and Culture	
\$currentDateTime	Current date & time when the toolkit was launched
\$currentTime	Current time when toolkit was launched
\$currentDate	Current date when toolkit was launched
\$currentTimeZoneBias	TimeZone bias based on the current date/time
\$culture	Object which contains all of the current Windows culture settings
\$currentLanguage	Current Windows two letter ISO language name (e.g. EN, FR, DE, JA etc)
\$currentUILanguage	Current Windows two letter UI ISO language name (e.g. EN, FR, DE, JA etc)
Environment Variables	(path examples are for Windows 7 and higher)
\$envHost	Object that contains details about the current PowerShell console
\$envShellFolders	Object that contains properties from registry path: <i>HKEY SOFTWARE\Microsoft\Windows\CurrentVersion\Explorer\User Shell Folders</i>
\$envAllUserProfile	%ALLUSERSPROFILE% e.g. C:\ProgramData
\$envAppData	%APPDATA% e.g. C:\Users\%USERNAME%\AppData\Roaming
\$envArchitecture	%PROCESSOR_ARCHITECTURE% e.g. AMD64\IA64\x86 - This doesn't tell you the architecture of the processor but only of the current process, so it returns "x86" for a 32-bit WOW process running on 64-bit Windows.
\$envCommonProgramFiles	%COMMONPROGRAMFILES% e.g. C:\Program Files\Common Files
\$envCommonProgramFilesX86	%COMMONPROGRAMFILES(x86)% e.g. C:\Program Files (x86)\Common Files
\$envCommonDesktop	e.g. C:\Users\Public\Desktop
\$envCommonDocuments	e.g. C:\Users\Public\Documents
\$envCommonStartMenuPrograms	e.g. C:\ProgramData\Microsoft\Windows\Start Menu\Programs
\$envCommonStartMenu	e.g. C:\ProgramData\Microsoft\Windows\Start Menu
\$envCommonStartUp	e.g. C:\ProgramData\Microsoft\Windows\Start Menu
\$envCommonTemplates	e.g. C:\ProgramData\Microsoft\Windows\Templates
\$envComputerName	\$COMPUTERNAME% e.g. Computer1
\$envComputerNameFQDN	Fully qualified computer name e.g. computer1.conto.contoso.com
\$envHomeDrive	%HOMEDRIVE% e.g. C:
\$envHomePath	%HOMEPATH% C:\Users\%USERNAME%

Variable	Description
\$envHomeShare	%HOMESHARE% (Used instead of HOMEDRIVE if the home directory uses UNC paths.)
\$envLocalAppData	%LOCALAPPDATA% e.g. C:\Users\%USERNAME%\AppData\Local
\$envLogicalDrives	An array containing all of the logical drives on the system.
\$envProgramFiles	%PROGRAMFILES% e.g. C:\Program Files
\$envProgramFilesX86	%ProgramFiles(x86)% e.g. C:\Program Files (x86) (Only on 64 bit systems, is used to store 32 bit programs.)
\$envProgramData	%PROGRAMDATA% e.g. C:\ProgramData
\$envPublic	%PUBLIC% e.g. C:\Users\Public
\$envSystemDrive	%SYSTEMDRIVE% e.g. C:
\$envSystemRAM	System RAM as an integer
\$envSystemRoot	%SYSTEMROOT% e.g. C:\Windows
\$envTemp	Checks for the existence of environment variables in the following order and uses the first path found: - The path specified by the TMP environment variable. - The path specified by the TEMP (e.g. C:\Users\%USERNAME%\AppData\Local\Temp) environment variable. - The path specified by the USERPROFILE environment variable. - The Windows root (C:\Windows) directory.
\$envUserCookies	C:\Users\%USERNAME%\AppData\Local\Microsoft\Windows\INetCookies
\$envUserDesktop	C:\Users\%USERNAME%\Desktop
\$envUserFavorites	C:\Users\%USERNAME%\Favorites
\$envUserInternetCache	C:\Users\%USERNAME%\AppData\Local\Microsoft\Windows\INetCache
\$envUserInternetHistory	C:\Users\%USERNAME%\AppData\Local\Microsoft\Windows\History
\$envUserMyDocuments	C:\Users\%USERNAME%\Documents
\$envUserName	%USERNAME%
\$envUserProfile	%USERPROFILE% e.g. %SystemDrive%\Users\%USERNAME%
\$envUserSendTo	C:\Users\%USERNAME%\AppData\Roaming\Microsoft\Windows\SendTo
\$envUserStartMenu	C:\Users\%USERNAME%\AppData\Roaming\Microsoft\Windows\Start Menu
\$envUserStartMenuPrograms	C:\Users\%USERNAME%\AppData\Roaming\Microsoft\Windows\Start Menu\Programs
\$envUserStartUp	C:\Users\%USERNAME%\AppData\Roaming\Microsoft\Windows\Start Menu\Programs\Startup
\$envSystem32Directory	C:\WINDOWS\system32
\$envWinDir	%WINDIR% e.g. C:\Windows
Domain Membership	
\$IsMachinePartOfDomain	Is machine joined to a domain (e.g. \$true/\$false)
\$envMachineWorkgroup	If machine not joined to domain, what is the WORKGROUP it belongs to?
\$envMachineADDomain	Root AD domain name for machine (e.g. domain.contoso.com)
\$envLogonServer	FQDN of %LOGONSERVER% used for authenticating logged in user
\$MachineDomainController	FQDN of an AD domain controller used for authentication

Variable	Description
\$envMachineDNSDomain	Full Domain name for machine (e.g. <name>.conto.contoso.com)
\$envUserDNSDomain	%USERDNSDOMAIN%. Root AD domain name for user (e.g. <name>.<suffix>.contoso.com)
\$envUserDomain	%USERDOMAIN% (e.g. <name>.<suffix>.CONTOSO.<tld>)
<i>Operating System</i>	
\$envOS	Object that contains details about the operating system
\$envOSName	Name of the operating system (e.g. Microsoft Windows 8.1 Pro)
\$envOSServicePack	Latest service pack installed on the system (e.g. Service Pack 3)
\$envOSVersion	Full version number of the OS (e.g. {major}.{minor}.{build}.{revision})
\$envOSVersionMajor	Major portion of the OS version number (e.g. {major}.{minor}.{build}.{revision})
\$envOSVersionMinor	Minor portion of the OS version number (e.g. {major}.{minor}.{build}.{revision})
\$envOSVersionBuild	Build portion of the OS version number (e.g. {major}.{minor}.{build}.{revision})
\$envOSVersionRevision	Revision portion of the OS version number (e.g. {major}.{minor}.{build}.{revision})
\$envOSProductType	OS product type represented as an integer (e.g. 1/2/3)
\$IsServerOS	Is server OS? (e.g. \$true/\$false)
\$IsDomainControllerOS	Is domain controller OS? (e.g. \$true/\$false)
\$IsWorkStationOS	Is workstation OS? (e.g. \$true/\$false)
\$envOSProductName	OS product type name (e.g. Server/Domain Controller/Workstation/Unknown)
\$Is64Bit	Is this a 64-bit OS? (e.g. \$true/\$false)
\$envOSArchitecture	Represents the OS architecture (e.g. 32-Bit/64-Bit)
<i>Current Process Architecture</i>	
\$Is64BitProcess	Is the current process 64-bits? (e.g. \$true/\$false)
\$psArchitecture	Represents the current process architecture (e.g. x86/x64)
<i>PowerShell And CLR (.NET) Versions</i>	
\$envPSVersionTable	Object containing PowerShell version details from PS variable \$PSVersionTable
\$envPSVersion	Full version number of PS (e.g. {major}.{minor}.{build}.{revision})
\$envPSVersionMajor	Major portion of PS version number (e.g. {major}.{minor}.{build}.{revision})
\$envPSVersionMinor	Minor portion of PS version number (e.g. {major}.{minor}.{build}.{revision})
\$envPSVersionBuild	Build portion of PS version number (e.g. {major}.{minor}.{build}.{revision})
\$envPSVersionRevision	Revision portion of PS version number (e.g. {major}.{minor}.{build}.{revision})
\$envCLRVersion	Full version number of .NET used by PS (e.g. {major}.{minor}.{build}.{revision})
\$envCLRVersionMajor	Major portion of PS .NET version number (e.g. {major}.{minor}.{build}.{revision})
\$envCLRVersionMinor	Minor portion of PS .NET version number (e.g. {major}.{minor}.{build}.{revision})
\$envCLRVersionBuild	Build portion of PS .NET version number (e.g. {major}.{minor}.{build}.{revision})
\$envCLRVersionRevision	Revision portion of PS .NET version number (e.g. {major}.{minor}.{build}.{revision})
<i>Permissions/Accounts</i>	
\$CurrentProcessToken	Object that represents the current processes Windows Identity user token. Contains all details regarding user permissions.
\$CurrentProcessSID	Object that represents the current process account SID (e.g. S-1-5-32-544)
\$ProcessNTAccount	Current process NT Account (e.g. NT AUTHORITY\SYSTEM)

Variable	Description
\$ProcessNTAccountSID	Current process account SID (e.g. S-1-5-32-544)
\$IsAdmin	Is the current process running with elevated admin privileges? (e.g. \$true/\$false)
\$IsLocalSystemAccount	Is the current process running under the SYSTEM account? (e.g. \$true/\$false)
\$IsLocalServiceAccount	Is the current process running under LOCAL SERVICE account? (e.g. \$true/\$false)
\$IsNetworkServiceAccount	Is the current process running under the NETWORK SERVICE account? (e.g. \$true/\$false)
\$IsServiceAccount	Is the current process running as a service? (e.g. \$true/\$false)
\$IsProcessUserInteractive	Is the current process able to display a user interface?
\$LocalSystemNTAccount	Localized NT account name of the SYSTEM account (e.g. NT AUTHORITY\SYSTEM)
\$SessionZero	Is the current process currently in session zero? In session zero isolation, process is not able to display a user interface. (e.g. \$true/\$false)
Script Name and Script Paths	
\$scriptPath	Fully qualified path of the toolkit e.g. C:\Testing\AppDeployToolkit\AppDeployToolkitMain.ps1
\$scriptName	Name of toolkit without file extension e.g. AppDeployToolkitMain
\$scriptFileName	Name of toolkit file e.g. AppDeployToolkitMain.ps1
\$scriptRoot	Folder that the toolkit is located in. e.g. C:\Testing\AppDeployToolkit
\$invokingScript	Fully qualified path of the script that invoked the toolkit e.g. C:\Testing\Deploy-Application.ps1
\$scriptParentPath	If toolkit was invoked by another script: contains folder that the invoking script is located in.
	If toolkit was not invoked by another script: contains parent folder of the toolkit.
App Deploy Script Dependency Files	
\$appDeployLogoIcon	Path to the logo icon file for the toolkit e.g. \$scriptRoot\AppDeployToolkitLogo.ico
\$appDeployLogoBanner	Path to the logo banner file for the toolkit e.g. \$scriptRoot\AppDeployToolkitBanner.png
\$appDeployConfigFile	Path to the config XML file for the toolkit e.g. \$scriptRoot\AppDeployToolkitConfig.xml
\$appDeployToolkitDotSourceExtensions	Name of the optional extensions file for the toolkit e.g. AppDeployToolkitExtensions.ps1
\$xmlConfigFile	Contains the entire contents of the XML config file
\$configConfigVersion	Version number of the config XML file
\$configConfigDate	Last modified date of the config XML file
Script Directories	
\$dirFiles	<i>Files</i> sub-directory of the toolkit
\$dirSupportFiles	<i>SupportFiles</i> sub-directory of the toolkit
\$dirAppDeployTemp	Toolkit temp directory. Configured in XML Config file option Toolkit_TempPath. e.g. Toolkit_TempPath\$appDeployToolkitName
Script Naming Convention	
\$appVendor	Name of the manufacturer that created the package being deployed (e.g. Microsoft)
\$appName	Name of the application being packaged (e.g. Office 2010)
\$appVersion	Version number of the application being packaged (e.g. 14.0)

Variable	Description
\$appLang	UI language of the application being packaged (e.g. EN)
\$appRevision	Revision number of the package (e.g. 01)
\$appArch	Architecture of the application being packaged (e.g. x86/x64)
\$installTitle	Combination of the most important details about the application being packaged (e.g. "\$appVendor \$appName \$appVersion")
\$installName	Combination of any of the following details which were provided: \$appVendor + _ + \$appName + _ + \$appVersion + _ + \$appArch + _ + \$appLang + _ + \$appRevision
Executables	
\$exeWusa	Name of system utility that installs Standalone Windows Updates e.g. <i>wusa.exe</i>
\$exeMsieexec	Name of system utility that install Windows Installer files e.g. <i>msieexec.exe</i>
\$exeSchTasks	Path of system utility that allows management of scheduled tasks e.g. <i>\$env:WinDir\System32\schtasks.exe</i>
RegEx Patterns	
\$MSIProductCodeRegExPattern	Contains the regex pattern used to detect a MSI product code.
Registry Keys	
\$regKeyApplications	Array containing the path to the 32-bit and 64-bit portions of the registry that contain information about programs installed on the system. <i>HKLM:SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall</i>
\$regKeyLotusNotes	Contains the registry path that stores information about a Lotus Notes installation. <i>HKLM:SOFTWARE\Lotus\Notes</i> <i>HKLM:SOFTWARE\Wow6432Node\Lotus\Notes</i>
\$regKeyAppExecution	Contains the registry path where application execution can be blocked by configuring the 'Debugger' value.
	HKLM:SOFTWARE\Microsoft\Windows NT\CurrentVersion\Image File Execution Options
\$regKeyDeferHistory	The path in the registry where the defer history for the package being installed is stored.
	\$configToolkitRegPath + \$appDeployToolkitName\DeferHistory\$installName
COM Objects	
\$Shell	Represents and allows use of the WScript.Shell COM object
\$ShellApp	Represents and allows use of the Shell.Application COM object
<i>Log File</i>	
\$logName	Name of the script log file: \$installName + " + \$appDeployToolkitName + " + \$deploymentType + '.log'
\$logTempFolder	Temporary log file directory used if the option to compress log files was selected in the config XML file: \$env:Temp\\$installName
\$configToolkitLogDir	Path to log directory defined in XML config file
\$DisableScriptLogging	Dot source this ScriptBlock to disable logging messages to the log file.
\$RevertScriptLogging	Dot source this ScriptBlock to revert script logging back to its original setting.
<i>Script Parameters</i>	
\$deployAppScriptParameters	Non-default parameters that Deploy-Application.ps1 was launched with
\$appDeployMainScriptParameters	Non-default parameters that AppDeployToolkitMain.ps1 was launched with

Variable	Description
\$appDeployExtScriptParameters	Non-default parameters that AppDeployToolkitExtensions.ps1 was launched with
Logged On Users	
\$LoggedOnUserSessions	Object that contains account and session details for all users
\$usersLoggedIn	Array that contains all of the NTAccount names of logged in users
\$CurrentLoggedInUserSession	Object that contains account and session details for the current process if it is running as a logged in user.
	This is the object from \$LoggedOnUserSessions where the IsCurrentSession property is \$true.
\$CurrentConsoleUserSession	Objects that contains the account and session details of the console user (user with control of the physical monitor, keyboard, and mouse).
	This is the object from \$LoggedOnUserSessions where the IsConsoleSession property is \$true.
\$RunAsActiveUser	The active console user. If no console user exists but users are logged in, such as on terminal servers, then the first logged-in non-console user.
Miscellaneous	
\$dpiPixels	DPI Scale (property only exists if DPI scaling has been changed on the system at least once)
\$runningTaskSequence	Is the current process running in a SCCM task sequence? (e.g. \$true/\$false)
\$IsTaskSchedulerHealthy	Are the task scheduler services in a healthy state? (e.g. \$true/\$false)
\$invalidFileNameChars	Array of all invalid file name characters used to sanitize variables which may be used to create file names.
\$useDefaultMsi	A Zero-Config MSI installation was detected.

Reference - Toolkit Functions

Block-AppExecution

SYNOPSIS

Block the execution of an application(s)

SYNTAX

```
Block-AppExecution [-ProcessName] <String[]> [<CommonParameters>]
```

DESCRIPTION

This function is called when you pass the -BlockExecution parameter to the Stop-RunningApplications function.

It does the following:

1. Makes a copy of this script in a temporary directory on the local machine.
2. Checks for an existing scheduled task from previous failed installation attempt where apps were blocked and if found, calls the Unblock-AppExecution function to restore the original IFEO registry keys. This is to prevent the function from overriding the backup of the original IFEO options.
3. Creates a scheduled task to restore the IFEO registry key values in case the script is terminated uncleanly by calling the local temporary copy of this script with the parameter -

- CleanupBlockedApps.
4. Modifies the "Image File Execution Options" registry key for the specified process(s) to call this script with the parameter -ShowBlockedAppDialog.
 5. When the script is called with those parameters, it will display a custom message to the user to indicate that execution of the application has been blocked while the installation is in progress. The text of this message can be customized in the XML configuration file.

EXAMPLES

EXAMPLE 1

```
Block-AppExecution -ProcessName ('winword', 'excel')
```

PARAMETERS

-ProcessName

Name of the process or processes separated by commas

```
Type: String[]
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly. It is used when the -BlockExecution parameter is specified with the Show-InstallationWelcome function to block applications.

RELATED LINKS

<http://psappdeploytoolkit.com>

Close-InstallationProgress

SYNTAX

```
Close-InstallationProgress [<CommonParameters>]
```

DESCRIPTION

Closes the dialog created by Show-InstallationProgress.

This function is called by the Exit-Script function to close a running instance of the progress dialog if found.

EXAMPLES

EXAMPLE 1

```
Close-InstallationProgress
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Convert-RegistryPath

SYNOPSIS

Converts the specified registry key path to a format that is compatible with built-in PowerShell cmdlets.

SYNTAX

```
Convert-RegistryPath [-Key] <String> [[-SID] <String>] [[-  
DisableFunctionLogging] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Converts the specified registry key path to a format that is compatible with built-in PowerShell cmdlets.

Converts registry key hives to their full paths.

Example: HKLM is converted to "Registry::HKEY_LOCAL_MACHINE".

EXAMPLES

EXAMPLE 1

```
Convert-RegistryPath -Key  
'HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\windows\CurrentVersion\Uninstall\  
\{1AD147D0-BE0E-3D6C-AC11-64F6DC4163F1}'
```

EXAMPLE 2

```
Convert-RegistryPath -Key  
'HKLM:SOFTWARE\Microsoft\windows\CurrentVersion\Uninstall\{1AD147D0-BE0E-3D6C-  
AC11-64F6DC4163F1}'
```

PARAMETERS

-Key

Path to the registry key to convert (can be a registry hive or fully qualified path)

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-SID

The security identifier (SID) for a user.

Specifying this parameter will convert a HKEY_CURRENT_USER registry key to the HKEY_USERS\$SID format.

Specify this parameter from the Invoke-HKCURegistrySettingsForAllUsers function to read/edit HKCU registry settings for all users on the system.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 2  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-DisableFunctionLogging

Disables logging of this function.

Default: \$true

```
Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 3  
Default value: True  
Accept pipeline input: False  
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

ConvertTo-NTAccountOrSID

SYNOPSIS

Convert between NT Account names and their security identifiers (SIDs).

SYNTAX

NTAccountToSID

```
ConvertTo-NTAccountOrSID -AccountName <String> [<CommonParameters>]
```

SIDToNTAccount

```
ConvertTo-NTAccountOrSID -SID <String> [<CommonParameters>]
```

WellKnownName

```
ConvertTo-NTAccountOrSID -WellKnownSIDName <String> [-WellKnownToNTAccount] [<CommonParameters>]
```

DESCRIPTION

Specify either the NT Account name or the SID and get the other.
Can also convert well known sid types.

EXAMPLES

EXAMPLE 1

```
ConvertTo-NTAccountOrSID -AccountName 'CONTOSO\User1'
```

Converts a Windows NT Account name to the corresponding SID

EXAMPLE 2

```
ConvertTo-NTAccountOrSID -SID 'S-1-5-21-1220945662-2111687655-725345543-  
14012660'
```

Converts a Windows NT Account SID to the corresponding NT Account Name

EXAMPLE 3

```
ConvertTo-NTAccountOrSID -WellKnownSIDName 'Networkservicesid'
```

Converts a Well Known SID name to a SID

PARAMETERS

-AccountName

The Windows NT Account name specified in <domain>\<username> format.
Use fully qualified account names (e.g., <domain>\<username>) instead of isolated names (e.g., <username>) because they are unambiguous and provide better performance.

```
Type: String  
Parameter Sets: NTAccountToSID  
Aliases:  
  
Required: True  
Position: Named  
Default value: None  
Accept pipeline input: True (ByPropertyName)  
Accept wildcard characters: False
```

-SID

The Windows NT Account SID.

```
Type: String
Parameter Sets: SIDToNTAccount
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: True (ByPropertyName)
Accept wildcard characters: False
```

-WellKnownSIDName

Specify the Well Known SID name translate to the actual SID (e.g., LocalServiceSid).

To get all well known SIDs available on system:

```
[enum]::GetNames([Security.Principal.WellKnownSidType])
```

```
Type: String
Parameter Sets: WellKnownName
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: True (ByPropertyName)
Accept wildcard characters: False
```

-WellKnownToNTAccount

Convert the Well Known SID to an NTAccount name

```
Type: SwitchParameter
Parameter Sets: WellKnownName
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.
The conversion can return an empty result if the user account does not exist anymore or if translation fails.

<http://blogs.technet.com/b/askds/archive/2011/07/28/troubleshooting-sid-translation-failures-from-the-obvious-to-the-not-so-obvious.aspx>

RELATED LINKS

<http://psappdeploytoolkit.com>

List of Well Known SIDs: [http://msdn.microsoft.com/en-us/library/system.security.principal.wellknownsidtype\(v=vs.110\).aspx](http://msdn.microsoft.com/en-us/library/system.security.principal.wellknownsidtype(v=vs.110).aspx)

Copy-File

SYNOPSIS

Copy a file or group of files to a destination path.

SYNTAX

```
Copy-File [-Path] <String[]> [-Destination] <String> [-Recurse] [-Flatten] [[-ContinueOnError] <Boolean>] [[-ContinueFileCopyOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Copy a file or group of files to a destination path.

EXAMPLES

EXAMPLE 1

```
Copy-File -Path "$dirSupportFiles\MyApp.ini" -Destination "$envWinDir\MyApp.ini"
```

EXAMPLE 2

```
Copy-File -Path "$dirSupportFiles\*.*" -Destination "$envTemp\tempfiles"
```

Copy all of the files in a folder to a destination folder.

PARAMETERS

-Path

Path of the file to copy.

```
Type: String[]
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Destination

Destination Path of the file to copy.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Recurse

Copy files in subdirectories.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-Flatten

Flattens the files into the root destination directory.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

This will continue the deployment script, but will not continue copying files if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueFileCopyOnError

Continue copying files if an error is encountered.

This will continue the deployment script and will warn about files that failed to be copied.

Default is: \$false.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Disable-TerminalServerInstallMode

SYNOPSIS

Changes to user install mode for Remote Desktop Session Host/Citrix servers.

SYNTAX

```
Disable-TerminalServerInstallMode [[-ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Changes to user install mode for Remote Desktop Session Host/Citrix servers.

EXAMPLES

EXAMPLE 1

```
Disable-TerminalServerInstallMode
```

PARAMETERS

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 1  
Default value: True  
Accept pipeline input: False  
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Enable-TerminalServerInstallMode

SYNOPSIS

Changes to user install mode for Remote Desktop Session Host/Citrix servers.

SYNTAX

```
Enable-TerminalServerInstallMode [[-ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Changes to user install mode for Remote Desktop Session Host/Citrix servers.

EXAMPLES

EXAMPLE 1

```
Enable-TerminalServerInstallMode
```

PARAMETERS

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 1  
Default value: True  
Accept pipeline input: False  
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Execute-MSI

SYNOPSIS

Executes msiexec.exe to perform the following actions for MSI & MSP files and MSI product codes: install, uninstall, patch, repair, active setup.

SYNTAX

```
Execute-MSI [[-Action] <String>] [-Path] <string> [[-Transform] <string>] [[-Parameters] <String>]
  [[-AddParameters] <String>] [-SecureParameters] [[-Patch] <string>] [[-LoggingOptions] <String>]
  [[-private:LogName] <String>] [[-WorkingDirectory] <string>] [-SkipMSIAalreadyInstalledCheck]
  [-IncludeUpdatesAndHotfixes] [-Nowait] [-PassThru] [[-IgnoreExitCodes] <String>]
  [[-PriorityClass] <ProcessPriorityClass>] [[-ExitOnProcessFailure] <Boolean>]
  [[-RepairFromSource] <Boolean>]
  [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Executes msiexec.exe to perform the following actions for MSI & MSP files and MSI product codes: install, uninstall, patch, repair, active setup.

If the -Action parameter is set to "Install" and the MSI is already installed, the function will exit.

Sets default switches to be passed to msiexec based on the preferences in the XML configuration file.

Automatically generates a log file name and creates a verbose log file for all msiexec operations.

Expects the MSI or MSP file to be located in the "Files" sub directory of the App Deploy Toolkit.

Expects transform files to be in the same directory as the MSI file.

EXAMPLES

EXAMPLE 1

```
Execute-MSI -Action 'Install' -Path 'Adobe_FlashPlayer_11.2.202.233_x64_EN.msi'
```

Installs an MSI

EXAMPLE 2

```
Execute-MSI -Action 'Install' -Path 'Adobe_FlashPlayer_11.2.202.233_x64_EN.msi'
  -Transform 'Adobe_FlashPlayer_11.2.202.233_x64_EN_01.mst' -Parameters '/QN'
```

Installs an MSI, applying a transform and overriding the default MSI toolkit parameters

EXAMPLE 3

```
[psobject]$ExecuteMSIResult = Execute-MSI -Action 'Install' -Path
  'Adobe_FlashPlayer_11.2.202.233_x64_EN.msi' -PassThru
```

Installs an MSI and stores the result of the execution into a variable by using the -PassThru option

EXAMPLE 4

```
Execute-MSI -Action 'Uninstall' -Path '{26923b43-4d38-484f-9b9e-de460746276c}'
```

Uninstalls an MSI using a product code

EXAMPLE 5

```
Execute-MSI -Action 'Patch' -Path 'Adobe_Reader_11.0.3_EN.msp'
```

Installs an MSP

PARAMETERS

-Action

The action to perform.

Options: Install, Uninstall, Patch, Repair, ActiveSetup.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: Install
Accept pipeline input: False
Accept wildcard characters: False
```

-Path

The path to the MSI/MSP file or the product code of the installed MSI.

```
Type: String
Parameter Sets: (All)
Aliases: FilePath

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Transform

The name of the transform file(s) to be applied to the MSI.

The transform file is expected to be in the same directory as the MSI file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Parameters

Overrides the default parameters specified in the XML configuration file.
Install default is: "REBOOT=ReallySuppress /QB!".
Uninstall default is: "REBOOT=ReallySuppress /QN".

```
Type: String
Parameter Sets: (All)
Aliases: Arguments

Required: False
Position: 4
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-AddParameters

Adds to the default parameters specified in the XML configuration file.
Install default is: "REBOOT=ReallySuppress /QB!".
Uninstall default is: "REBOOT=ReallySuppress /QN".

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-SecureParameters

Hides all parameters passed to the MSI or MSP file from the toolkit Log file.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-Patch

The name of the patch (msp) file(s) to be applied to the MSI for use with the "Install" action.
The patch file is expected to be in the same directory as the MSI file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-LoggingOptions

Overrides the default logging options specified in the XML configuration file.
Default options are: "/L*v".

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 7
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-private:LogName

Overrides the default logfile name.

```
Type: String
Parameter Sets: (All)
Aliases: LogName

Required: False
Position: 8
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-WorkingDirectory

Overrides the working directory.
The working directory is set to the location of the MSI file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 9
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-SkipMSIAalreadyInstalledCheck

Skips the check to determine if the MSI is already installed on the system.
Default is: \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-IncludeUpdatesAndHotfixes

Include matches against updates and hotfixes in results.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-NoWait

Immediately continue after executing the process.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-PassThru

Returns ExitCode, STDOut, and STDErr output from the process.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-IgnoreExitCodes

List the exit codes to ignore or * to ignore all exit codes.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 10
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-PriorityClass

Specifies priority class for the process.

Options: Idle, Normal, High, AboveNormal, BelowNormal, RealTime.

Default: Normal

```
Type: ProcessPriorityClass
Parameter Sets: (All)
Aliases:
Accepted values: Normal, Idle, High, RealTime, BelowNormal, AboveNormal

Required: False
Position: 11
Default value: Normal
Accept pipeline input: False
Accept wildcard characters: False
```

-ExitOnProcessFailure

Specifies whether the function should call Exit-Script when the process returns an exit code that is considered an error/failure.

Default: \$true

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 12
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-RepairFromSource

Specifies whether we should repair from source.

Also rewrites local cache.

Default: \$false

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 13
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error occurred while trying to start the process.

Default: \$false.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 14
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Execute-MSP

SYNOPSIS

Reads SummaryInfo targeted product codes in MSP file and determines if the MSP file applies to any installed products

If a valid installed product is found, triggers the Execute-MSI function to patch the installation.

Uses default config MSI parameters.

SYNTAX

```
Execute-MSP [-Path] <String> [[-AddParameters] <string>] [<CommonParameters>]
```

EXAMPLES

EXAMPLE 1

```
Execute-MSP -Path 'Adobe_Reader_11.0.3_EN.msp'
```

PARAMETERS

-Path

Path to the msp file

```
Type: String
Parameter Sets: (All)
Aliases: FilePath

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-AddParameters

Additional parameters

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Execute-Process

SYNOPSIS

Execute a process with optional arguments, working directory, window style.

SYNTAX

```
Execute-Process [-Path] <String> [[-Parameters] <String[]>] [-SecureParameters]
    [[-windowStyle] <ProcessWindowStyle>] [-CreateNoWindow] [[-WorkingDirectory]
    <String>] [-Nowait] [-PassThru]
    [-WaitForMsiExec] [[-MsiExecWaitTime] <Int32>] [[-IgnoreExitCodes] <String>]
    [[-PriorityClass] <ProcessPriorityClass>] [[-ExitOnProcessFailure] <Boolean>]
    [[-UseShellExecute] <Boolean>]
    [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Executes a process, e.g.

a file included in the Files directory of the App Deploy Toolkit, or a file on the local machine.

Provides various options for handling the return codes (see Parameters).

EXAMPLES

EXAMPLE 1

```
Execute-Process -Path 'uninstall_flash_player_64bit.exe' -Parameters
    '/uninstall' -windowStyle 'Hidden'
```

If the file is in the "Files" directory of the App Deploy Toolkit, only the file name needs to be specified.

EXAMPLE 2

```
Execute-Process -Path "$dirFiles\Bin\setup.exe" -Parameters '/S' -windowStyle
    'Hidden'
```

EXAMPLE 3

```
Execute-Process -Path 'setup.exe' -Parameters '/s' -IgnoreExitCodes '1,2'
```

EXAMPLE 4

```
Execute-Process -Path 'setup.exe' -Parameters "-s -f2`"$configToolkitLogDir\$installName.log`""
```

Launch InstallShield "setup.exe" from the ".\Files" sub-directory and force log files to the logging folder.

EXAMPLE 5

```
Execute-Process -Path 'setup.exe' -Parameters "/s /v`"ALLUSERS=1 /qn /L*`"$configToolkitLogDir\$installName.log`"""
```

Launch InstallShield "setup.exe" with embedded MSI and force log files to the logging folder.

PARAMETERS

-Path

Path to the file to be executed.

If the file is located directly in the "Files" directory of the App Deploy Toolkit, only the file name needs to be specified.

Otherwise, the full path of the file must be specified.

If the file is in a subdirectory of "Files", use the "\$dirFiles" variable as shown in the example.

```
Type: String  
Parameter Sets: (All)  
Aliases: FilePath  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Parameters

Arguments to be passed to the executable

```
Type: String[]  
Parameter Sets: (All)  
Aliases: Arguments  
  
Required: False  
Position: 2  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-SecureParameters

Hides all parameters passed to the executable from the Toolkit log file

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-WindowStyle

Style of the window of the process executed.

Options: Normal, Hidden, Maximized, Minimized.

Default: Normal.

Note: Not all processes honor WindowStyle.

WindowStyle is a recommendation passed to the process.

They can choose to ignore it.

Only works for native Windows GUI applications.

If the WindowStyle is set to Hidden, UseShellExecute should be set to \$true.

```
Type: ProcesswindowStyle
Parameter Sets: (All)
Aliases:

Accepted values: Normal, Hidden, Minimized, Maximized

Required: False
Position: 3
Default value: Normal
Accept pipeline input: False
Accept wildcard characters: False
```

-CreateNoWindow

Specifies whether the process should be started with a new window to contain it.

Only works for Console mode applications.

UseShellExecute should be set to \$false.

Default is false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-WorkingDirectory

The working directory used for executing the process.
Defaults to the directory of the file being executed.
Parameter UseShellExecute affects this parameter.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 4  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-NoWait

Immediately continue after executing the process.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

-PassThru

If NoWait is not specified, returns an object with ExitCode, STDOut and STDErr output from the process.
If NoWait is specified, returns an object with Id, Handle and ProcessName.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

-WaitForMsiExec

Sometimes an EXE bootstrapper will launch an MSI install.
In such cases, this variable will ensure that
this function waits for the msieexec engine to become available before starting the install.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-MsiExecWaitTime

Specify the length of time in seconds to wait for the msieexec engine to become available.
Default: 600 seconds (10 minutes).

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: $configMSIMutexWaitTime
Accept pipeline input: False
Accept wildcard characters: False
```

-IgnoreExitCodes

List the exit codes to ignore or * to ignore all exit codes.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-PriorityClass

Specifies priority class for the process.
Options: Idle, Normal, High, AboveNormal, BelowNormal, RealTime.
Default: Normal

```
Type: ProcessPriorityClass
Parameter Sets: (All)
Aliases:
Accepted values: Normal, Idle, High, RealTime, BelowNormal, AboveNormal

Required: False
Position: 7
Default value: Normal
Accept pipeline input: False
Accept wildcard characters: False
```

-ExitOnProcessFailure

Specifies whether the function should call Exit-Script when the process returns an exit code that is considered an error/failure.

Default: \$true

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 8
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-UseShellExecute

Specifies whether to use the operating system shell to start the process.

\$true if the shell should be used when starting the process; \$false if the process should be created directly from the executable file.

The word "Shell" in this context refers to a graphical shell (similar to the Windows shell) rather than command shells (for example, bash or sh) and lets users launch graphical applications or open documents.

It lets you open a file or a url and the Shell will figure out the program to open it with.

The WorkingDirectory property behaves differently depending on the value of the UseShellExecute property.

When UseShellExecute is true, the WorkingDirectory property specifies the location of the executable.

When UseShellExecute is false, the WorkingDirectory property is not used to find the executable. Instead, it is used only by the process that is started and has meaning only within the context of the new process.

If you set UseShellExecute to \$true, there will be no available output from the process.

Default: \$false

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 9
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error occurred while trying to start the process.

Default: \$false.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 10
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Execute-ProcessAsUser

SYNOPSIS

Execute a process with a logged in user account, by using a scheduled task, to provide interaction with user in the SYSTEM context.

SYNTAX

```
Execute-ProcessAsUser [[-UserName] <String>] [-Path] <String> [[-Parameters]
<String>] [-SecureParameters]
[[[-RunLevel] <String>] [-Wait] [-PassThru] [[-WorkingDirectory] <String>] [[-
ContinueOnError] <Boolean>]
[<CommonParameters>]
```

DESCRIPTION

Execute a process with a logged in user account, by using a scheduled task, to provide interaction with user in the SYSTEM context.

EXAMPLES

EXAMPLE 1

```
Execute-ProcessAsUser -UserName 'CONTOSO\User' -Path "$PSHOME\powershell.exe" -
Parameters "-Command & { & `C:\Test\Script.ps1`"; Exit `$LastExitCode }" -Wait
```

Execute process under a user account by specifying a username under which to execute it.

EXAMPLE 2

```
Execute-ProcessAsUser -Path "$PSHOME\powershell.exe" -Parameters "-Command & { &
`"C:\Test\Script.ps1`"; Exit `"$LastExitCode }" -Wait
```

Execute process under a user account by using the default active logged in user that was detected when the toolkit was launched.

PARAMETERS

-UserName

Logged in Username under which to run the process from.

Default is: The active console user.

If no console user exists but users are logged in, such as on terminal servers, then the first logged-in non-console user.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: $RunAsActiveUser.NTAccount
Accept pipeline input: False
Accept wildcard characters: False
```

-Path

Path to the file being executed.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Parameters

Arguments to be passed to the file being executed.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-SecureParameters

Hides all parameters passed to the executable from the Toolkit log file.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-RunLevel

Specifies the level of user rights that Task Scheduler uses to run the task.

The acceptable values for this parameter are:

- HighestAvailable: Tasks run by using the highest available privileges (Admin privileges for Administrators).
Default Value.
- LeastPrivilege: Tasks run by using the least-privileged user account (LUA) privileges.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: HighestAvailable
Accept pipeline input: False
Accept wildcard characters: False
```

-Wait

Wait for the process, launched by the scheduled task, to complete execution before accepting more input.

Default is \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-PassThru

Returns the exit code from this function or the process launched by the scheduled task.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-WorkingDirectory

Set working directory for the process.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ContinueOnError

Continue if an error is encountered.

Default is \$true.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: True
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Exit-Script

SYNTAX

```
Exit-Script [[-ExitCode] <Int32>] [<CommonParameters>]
```

DESCRIPTION

Always use when exiting the script to ensure cleanup actions are performed.

EXAMPLES

EXAMPLE 1

```
Exit-Script -ExitCode 0
```

EXAMPLE 2

```
Exit-Script -ExitCode 1618
```

PARAMETERS

-ExitCode

The exit code to be passed from the script to the parent process, e.g.
SCCM

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-DeferHistory

SYNOPSIS

Get the history of deferrals from the registry for the current application, if it exists.

SYNTAX

```
Get-DeferHistory [<CommonParameters>]
```

DESCRIPTION

Get the history of deferrals from the registry for the current application, if it exists.

EXAMPLES

EXAMPLE 1

```
Get-DeferHistory
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-FileVersion

SYNOPSIS

Gets the version of the specified file

SYNTAX

```
Get-FileVersion [-File] <String> [-ProductVersion] [[-ContinueOnError]
<Boolean>] [<CommonParameters>]
```

DESCRIPTION

Gets the version of the specified file

EXAMPLES

EXAMPLE 1

```
Get-FileVersion -File "$env:ProgramFiles(x86)\Adobe\Reader
11.0\Reader\AcroRd32.exe"
```

PARAMETERS

-File

Path of the file

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ProductVersion

Switch that makes the command return ProductVersion instead of FileVersion

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: True
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-FreeDiskSpace

SYNOPSIS

Retrieves the free disk space in MB on a particular drive (defaults to system drive)

SYNTAX

```
Get-FreeDiskSpace [[-Drive] <String>] [[-ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Retrieves the free disk space in MB on a particular drive (defaults to system drive)

EXAMPLES

EXAMPLE 1

```
Get-FreeDiskSpace -Drive 'C:'
```

PARAMETERS

-Drive

Drive to check free disk space on

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: $env:SystemDrive
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-HardwarePlatform

SYNOPSIS

Retrieves information about the hardware platform (physical or virtual)

SYNTAX

```
Get-HardwarePlatform [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Retrieves information about the hardware platform (physical or virtual)

EXAMPLES

EXAMPLE 1

```
Get-HardwarePlatform
```

PARAMETERS

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 1  
Default value: True  
Accept pipeline input: False  
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-IniValue

SYNOPSIS

Parses an INI file and returns the value of the specified section and key.

SYNTAX

```
Get-IniValue [-FilePath] <String> [-Section] <String> [-Key] <String> [[-  
ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Parses an INI file and returns the value of the specified section and key.

EXAMPLES

EXAMPLE 1

```
Get-IniValue -FilePath "$env:ProgramFiles(x86)\IBM\Notes\notes.ini" -Section  
'Notes' -Key 'KeyFileName'
```

PARAMETERS

-FilePath

Path to the INI file.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Section

Section within the INI file.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 2  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Key

Key within the section of the INI file.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 3  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-InstalledApplication

SYNOPSIS

Retrieves information about installed applications.

SYNTAX

```
Get-InstalledApplication [[-Name] <String[]>] [-Exact] [-wildCard] [-RegEx] [[-ProductCode] <String>]
[-IncludeUpdatesAndHotfixes] [<CommonParameters>]
```

DESCRIPTION

Retrieves information about installed applications by querying the registry.

You can specify an application name, a product code, or both.

Returns information about application publisher, name & version, product code, uninstall string, install source, location, date, and application architecture.

EXAMPLES

EXAMPLE 1

```
Get-InstalledApplication -Name 'Adobe Flash'
```

EXAMPLE 2

```
Get-InstalledApplication -ProductCode '{1AD147D0-BE0E-3D6C-AC11-64F6DC4163F1}'
```

PARAMETERS

-Name

The name of the application to retrieve information for.

Performs a contains match on the application display name by default.

```
Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Exact

Specifies that the named application must be matched using the exact name.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-WildCard

Specifies that the named application must be matched using a wildcard search.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-RegEx

Specifies that the named application must be matched using a regular expression search.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ProductCode

The product code of the application to retrieve information for.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-IncludeUpdatesAndHotfixes

Include matches against updates and hotfixes in results.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-LoggedOnUser

SYNOPSIS

Get session details for all local and RDP logged on users.

SYNTAX

```
Get-Loggedonuser [<CommonParameters>]
```

DESCRIPTION

Get session details for all local and RDP logged on users using Win32 APIs.

Get the following session details:

NTAccount, SID, UserName, DomainName, SessionId, SessionName, ConnectState,
IsCurrentSession, IsConsoleSession, IsUserSession, IsActiveUserSession
IsRdpSession, IsLocalAdmin, LogonTime, IdleTime, DisconnectTime, ClientName,
ClientProtocolType, ClientDirectory, ClientBuildNumber

EXAMPLES

EXAMPLE 1

```
Get-Loggedonuser
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

Description of ConnectState property:

Value	Description
-------	-------------

Active	A user is logged on to the session.
--------	-------------------------------------

ConnectQuery	The session is in the process of connecting to a client.
--------------	--

Connected	A client is connected to the session.
-----------	---------------------------------------

Disconnected	The session is active, but the client has disconnected from it.
--------------	---

Down	The session is down due to an error.
------	--------------------------------------

Idle	The session is waiting for a client to connect.
------	---

Initializing The session is initializing.
Listening The session is listening for connections.
Reset The session is being reset.
Shadowing This session is shadowing another session.

Description of IsActiveUserSession property:
If a console user exists, then that will be the active user session.
If no console user exists but users are logged in, such as on terminal servers, then the first logged-in non-console user that is either 'Active' or 'Connected' is the active user.

Description of IsRdpSession property:
Gets a value indicating whether the user is associated with an RDP client session.

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-MsiExitCodeMessage

SYNOPSIS

Get message for MSI error code

SYNTAX

```
Get-MsiExitCodeMessage [-MsiExitCode] <Int32> [<CommonParameters>]
```

DESCRIPTION

Get message for MSI error code by reading it from msimsg.dll

EXAMPLES

EXAMPLE 1

```
Get-MsiExitCodeMessage -MsiExitCode 1618
```

PARAMETERS

-MsiExitCode

{} The MSI Exit Code to resolve {}

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

[http://msdn.microsoft.com/en-us/library/aa368542\(v=vs.85\).aspx](http://msdn.microsoft.com/en-us/library/aa368542(v=vs.85).aspx)
<http://psappdeploytoolkit.com>

Get-MsiTableProperty

SYNOPSIS

Get all of the properties from a Windows Installer database table or the Summary Information stream and return as a custom object.

SYNTAX

TableInfo (Default)

```
Get-MsiTableProperty -Path <String> [-TransformPath <String[]>] [-Table <String>]
[-TablePropertyNameColumnNum <Int32>] [-TablePropertyValueColumnNum <Int32>] [-ContinueOnError <Boolean>]
[<CommonParameters>]
```

SummaryInfo

```
Get-MsiTableProperty -Path <String> [-TransformPath <String[]>] [-GetSummaryInformation]
[-ContinueOnError <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Use the Windows Installer object to read all of the properties from a Windows Installer database table or the Summary Information stream.

EXAMPLES

EXAMPLE 1

```
Get-MsiTableProperty -Path 'C:\Package\AppDeploy.msi' -TransformPath
'C:\Package\AppDeploy.mst'
```

Retrieve all of the properties from the default 'Property' table.

EXAMPLE 2

```
Get-MsiTableProperty -Path 'C:\Package\AppDeploy.msi' -TransformPath  
'C:\Package\AppDeploy.mst' -Table 'Property' | Select-Object -ExpandProperty  
ProductCode
```

Retrieve all of the properties from the 'Property' table and then pipe to Select-Object to select the ProductCode property.

EXAMPLE 3

```
Get-MsiTableProperty -Path 'C:\Package\AppDeploy.msi' -GetSummaryInformation
```

Retrieves the Summary Information for the Windows Installer database.

PARAMETERS

-Path

The fully qualified path to an database file.
Supports .msi and .msp files.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-TransformPath

The fully qualified path to a list of MST file(s) which should be applied to the MSI file.

```
Type: String[]  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Table

The name of the the MSI table from which all of the properties must be retrieved.
Default is: 'Property'.

```
Type: String
Parameter Sets: TableInfo
Aliases:

Required: False
Position: Named
Default value: $(If ([IO.Path]::GetExtension($Path) -eq '.msi') { 'Property' }
Else { 'MsiPatchMetadata' })
Accept pipeline input: False
Accept wildcard characters: False
```

-TablePropertyNameColumnNum

Specify the table column number which contains the name of the properties.
Default is: 1 for MSIs and 2 for MSPs.

```
Type: Int32
Parameter Sets: TableInfo
Aliases:

Required: False
Position: Named
Default value: $(If ([IO.Path]::GetExtension($Path) -eq '.msi') { 1 } Else { 2 })
Accept pipeline input: False
Accept wildcard characters: False
```

-TablePropertyValueColumnNum

Specify the table column number which contains the value of the properties.
Default is: 2 for MSIs and 3 for MSPs.

```
Type: Int32
Parameter Sets: TableInfo
Aliases:

Required: False
Position: Named
Default value: $(If ([IO.Path]::GetExtension($Path) -eq '.msi') { 2 } Else { 3 })
Accept pipeline input: False
Accept wildcard characters: False
```

-GetSummaryInformation

Retrieves the Summary Information for the Windows Installer database.

Summary Information property descriptions: [https://msdn.microsoft.com/en-us/library/aa372049\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/aa372049(v=vs.85).aspx)

```
Type: SwitchParameter
Parameter Sets: SummaryInfo
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-ObjectProperty

SYNOPSIS

Get a property from any object.

SYNTAX

```
Get-ObjectProperty [-InputObject] <Object> [-PropertyName] <String> [[-ArgumentList] <Object[]>]
[<CommonParameters>]
```

DESCRIPTION

Get a property from any object.

EXAMPLES

EXAMPLE 1

```
Get-ObjectProperty -InputObject $Record -PropertyName 'StringData' -ArgumentList @(1)
```

PARAMETERS

-InputObject

Specifies an object which has properties that can be retrieved.

```
Type: Object
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-PropertyName

Specifies the name of a property to retrieve.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ArgumentList

Argument to pass to the property being retrieved.

```
Type: Object[]
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-PEFileArchitecture

SYNOPSIS

Determine if a PE file is a 32-bit or a 64-bit file.

SYNTAX

```
Get-PEFileArchitecture [-FilePath] <FileInfo[]> [[-ContinueOnError] <Boolean>]  
[-PassThru] [<CommonParameters>]
```

DESCRIPTION

Determine if a PE file is a 32-bit or a 64-bit file by examining the file's image file header.
PE file extensions: .exe, .dll, .ocx, .drv, .sys, .scr, .efi, .cpl, .fon

EXAMPLES

EXAMPLE 1

```
Get-PEFileArchitecture -FilePath "$env:windir\%notepad.exe"
```

PARAMETERS

-FilePath

Path to the PE file to examine.

```
Type: FileInfo[]  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-PassThru

Get the file object, attach a property indicating the file binary type, and write to pipeline

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

Get-PendingReboot

SYNOPSIS

Get the pending reboot status on a local computer.

SYNTAX

```
Get-PendingReboot [<CommonParameters>]
```

DESCRIPTION

Check WMI and the registry to determine if the system has a pending reboot operation from any of the following:

- a) Component Based Servicing (Vista, Windows 2008)
- b) Windows Update / Auto Update (XP, Windows 2003 / 2008)
- c) SCCM 2012 Clients (DetermineIfRebootPending WMI method)
- d) App-V Pending Tasks (global based Appv 5.0 SP2)
- e) Pending File Rename Operations (XP, Windows 2003 / 2008)

EXAMPLES

EXAMPLE 1

```
Get-PendingReboot
```

Returns custom object with following properties:

ComputerName, LastBootUpTime, IsSystemRebootPending, IsCBServicingRebootPending, IsWindowsUpdateRebootPending, IsSCCMClientRebootPending, IsFileRenameRebootPending, PendingFileRenameOperations, ErrorMsg

*Notes: ErrorMsg only contains something if an error occurred

EXAMPLE 2

```
(Get-PendingReboot).IsSystemRebootPending
```

Returns boolean value determining whether or not there is a pending reboot operation.

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-RegistryKey

SYNOPSIS

Retrieves value names and value data for a specified registry key or optionally, a specific value.

SYNTAX

```
Get-RegistryKey [-Key] <String> [[-Value] <String>] [[-SID] <String>] [-  
ReturnEmptyKeyIfExists]  
[-DoNotExpandEnvironmentNames] [[-ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Retrieves value names and value data for a specified registry key or optionally, a specific value. If the registry key does not exist or contain any values, the function will return \$null by default. To test for existence of a registry key path, use built-in Test-Path cmdlet.

EXAMPLES

EXAMPLE 1

```
Get-RegistryKey -Key 'HKLM:SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\  
{1AD147D0-BE0E-3D6C-AC11-64F6DC4163F1}'
```

EXAMPLE 2

```
Get-RegistryKey -Key 'HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows  
NT\CurrentVersion\Image File Execution Options\iexplore.exe'
```

EXAMPLE 3

```
Get-RegistryKey -Key 'HKLM:Software\Wow6432Node\Microsoft\Microsoft SQL Server  
Compact Edition\v3.5' -Value 'Version'
```

EXAMPLE 4

```
Get-RegistryKey -Key  
'HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Session Manager\Environment'  
-Value 'Path' -DoNotExpandEnvironmentNames
```

Returns %ProgramFiles%\Java instead of C:\Program Files\Java

EXAMPLE 5

```
Get-RegistryKey -Key 'HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Example' -Value  
'(Default)'
```

PARAMETERS

-Key

Path of the registry key.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Value

Value to retrieve (optional).

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-SID

The security identifier (SID) for a user.

Specifying this parameter will convert a HKEY_CURRENT_USER registry key to the HKEY_USERS\$SID format.

Specify this parameter from the Invoke-HKCURegistrySettingsForAllUsers function to read/edit HKCU registry settings for all users on the system.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ReturnEmptyKeyIfExists

Return the registry key if it exists but it has no property/value pairs underneath it.

Default is: \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-DoNotExpandEnvironmentNames

Return unexpanded REG_EXPAND_SZ values.
Default is: \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-RunningProcesses

SYNOPSIS

Gets the processes that are running from a custom list of process objects and also adds a property called ProcessDescription.

SYNTAX

```
Get-RunningProcesses [[-ProcessObjects] <PSObject[]>] [-DisableLogging]  
[<CommonParameters>]
```

DESCRIPTION

Gets the processes that are running from a custom list of process objects and also adds a property called ProcessDescription.

EXAMPLES

EXAMPLE 1

```
Get-RunningProcesses -ProcessObjects $ProcessObjects
```

PARAMETERS

-ProcessObjects

Custom object containing the process objects to search for.
If not supplied, the function just returns \$null

```
Type: PSObject[]  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-DisableLogging

Disables Logging

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-SchedulerTask

SYNOPSIS

Retrieve all details for scheduled tasks on the local computer.

SYNTAX

```
Get-SchedulerTask [[-TaskName] <String>] [[-ContinueOnError] <Boolean>]
[<CommonParameters>]
```

DESCRIPTION

Retrieve all details for scheduled tasks on the local computer using schtasks.exe.
All property names have spaces and colons removed.

EXAMPLES

EXAMPLE 1

```
Get-SchedulerTask
```

To display a list of all scheduled task properties.

EXAMPLE 2

```
Get-SchedulerTask | Out-GridView
```

To display a grid view of all scheduled task properties.

EXAMPLE 3

```
Get-SchedulerTask | Select-Object -Property TaskName
```

To display a list of all scheduled task names.

PARAMETERS

-TaskName

Specify the name of the scheduled task to retrieve details for.

Uses regex match to find scheduled task.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-ServiceStartMode

SYNOPSIS

Get the service startup mode.

SYNTAX

```
Get-ServiceStartMode [-Name] <String> [[-ComputerName] <string>] [[-ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Get the service startup mode.

EXAMPLES

EXAMPLE 1

```
Get-ServiceStartMode -Name 'wuauserv'
```

PARAMETERS

-Name

Specify the name of the service.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-ComputerName

Specify the name of the computer.

Default is: the local computer.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: $env:ComputerName
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-UniversalDate

SYNOPSIS

Returns the date/time for the local culture in a universal sortable date time pattern.

SYNTAX

```
Get-UniversalDate [[-DateTime] <String>] [[-ContinueOnError] <Boolean>]
[<CommonParameters>]
```

DESCRIPTION

Converts the current datetime or a datetime string for the current culture into a universal sortable date time pattern, e.g.

2013-08-22 11:51:52Z

EXAMPLES

EXAMPLE 1

```
Get-UniversalDate
```

Returns the current date in a universal sortable date time pattern.

EXAMPLE 2

```
Get-UniversalDate -DateTime '25/08/2013'
```

Returns the date for the current culture in a universal sortable date time pattern.

PARAMETERS

-DateTime

Specify the DateTime in the current culture.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: ((Get-Date -Format
($culture).DateTimeFormat.UniversalDateTimePattern).ToString())
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default: \$false.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-UserProfiles

SYNOPSIS

Get the User Profile Path, User Account Sid, and the User Account Name for all users that log onto the machine and also the Default User (which does not log on).

SYNTAX

```
Get-UserProfiles [[-ExcludeNTAccount] <String[]>] [[-ExcludeSystemProfiles]
<Boolean>] [-ExcludeDefaultUser]
[<CommonParameters>]
```

DESCRIPTION

Get the User Profile Path, User Account Sid, and the User Account Name for all users that log onto the machine and also the Default User (which does not log on).

Please note that the NTAccount property may be empty for some user profiles but the SID and ProfilePath properties will always be populated.

EXAMPLES

EXAMPLE 1

```
Get-UserProfiles
```

Returns the following properties for each user profile on the system: NTAccount, SID, ProfilePath

EXAMPLE 2

```
Get-UserProfiles -ExcludeNTAccount 'CONTOSO\Robot', 'CONTOSO\ntadmin'
```

EXAMPLE 3

```
[string[]]$ProfilePaths = Get-UserProfiles | Select-Object -ExpandProperty
'ProfilePath'
```

Returns the user profile path for each user on the system.
This information can then be used to make modifications under the user profile on the filesystem.

PARAMETERS

-ExcludeNTAccount

Specify NT account names in Domain\Username format to exclude from the list of user profiles.

```
Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ExcludeSystemProfiles

Exclude system profiles: SYSTEM, LOCAL SERVICE, NETWORK SERVICE.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-ExcludeDefaultUser

Exclude the Default User.
Default is: \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Get-WindowTitle

SYNOPSIS

Search for an open window title and return details about the window.

SYNTAX

SearchWinTitle

```
Get-WindowTitle -windowTitle <String> [-DisableFunctionLogging]  
[<CommonParameters>]
```

GetAllWinTitles

```
Get-WindowTitle [-GetAllWindowTitles] [-DisableFunctionLogging]  
[<CommonParameters>]
```

DESCRIPTION

Search for a window title.

If window title searched for returns more than one result, then details for each window will be displayed.

Returns the following properties for each window: WindowTitle, WindowHandle, ParentProcess, ParentProcessMainWindowHandle, ParentProcessId.

Function does not work in SYSTEM context unless launched with "psexec.exe -s -i" to run it as an interactive process under the SYSTEM account.

EXAMPLES

EXAMPLE 1

```
Get-WindowTitle -windowTitle 'Microsoft Word'
```

Gets details for each window that has the words "Microsoft Word" in the title.

EXAMPLE 2

```
Get-WindowTitle -GetAllWindowTitles
```

Gets details for all windows with a title.

EXAMPLE 3

```
Get-WindowTitle -GetAllWindowTitles | Where-Object { ---  
  
external help file: AppDeployToolkitMain-help.xml  
Module Name: AppDeployToolkitMain  
online version: http://psappdeploytoolkit.com  
schema: 2.0.0  
---  
  
### Get-WindowTitle  
  
#### SYNOPSIS  
  
Search for an open window title and return details about the window.  
  
#### SYNTAX  
  
##### SearchWindowTitle
```

Get-WindowTitle -WindowTitle [-DisableFunctionLogging] []

```
##### GetAllWindowTitle
```

Get-WindowTitle [-GetAllWindowTitles] [-DisableFunctionLogging] []

```
#### DESCRIPTION
```

Search **for** a window title.
If window title searched **for** returns **more** than one result, then details **for** each window will be displayed.
Returns the following properties **for** each window: **WindowTitle**, **WindowHandle**, **ParentProcess**, **ParentProcessMainWindowHandle**, **ParentProcessId**.
Function does not work **in** SYSTEM context unless launched with "**psexec.exe -s -i**" to run it as an interactive **process** under the SYSTEM account.

```
#### EXAMPLES
```

```
##### EXAMPLE 1
```

Get-WindowTitle -WindowTitle 'Microsoft Word'

```
Gets details for each window that has the words "Microsoft Word" in the title.
```

```
##### EXAMPLE 2
```

Get-WindowTitle -GetAllWindowTitles

Gets details for all windows with a title.

EXAMPLE 3

```
Get-WindowTitle -GetAllWindowTitles | Where-Object { $_.ParentProcess -eq 'WINWORD' }
```

Get details for all windows belonging to Microsoft Word process with name "WINWORD".

PARAMETERS

-WindowTitle

The title of the application window to search for using regex matching.

```
```yaml
Type: String
Parameter Sets: SearchwinTitle
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

#### -GetAllWindowTitles

Get titles for all open windows on the system.

```
Type: SwitchParameter
Parameter Sets: GetAllWinTitles
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

#### -DisableFunctionLogging

Disables logging messages to the script log file.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

```
```powershell

##### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](http://go.microsoft.com/fwlink/?LinkID=113216).

#### INPUTS

#### OUTPUTS

#### NOTES

#### RELATED LINKS

[http://psappdeploytoolkit.com](http://psappdeploytoolkit.com).ParentProcess -eq 'WINWORD' }
```

Get details for all windows belonging to Microsoft Word process with name "WINWORD".

PARAMETERS

-WindowTitle

The title of the application window to search for using regex matching.

```
Type: String
Parameter Sets: SearchwinTitle
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-GetAllWindowTitles

Get titles for all open windows on the system.

```
Type: SwitchParameter
Parameter Sets: GetAllWinTitles
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-DisableFunctionLogging

Disables logging messages to the script log file.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Install-MSUpdates

SYNOPSIS

Install all Microsoft Updates in a given directory.

SYNTAX

```
Install-MSUpdates [-Directory] <String> [<CommonParameters>]
```

DESCRIPTION

Install all Microsoft Updates of type ".exe", ".msu", or ".msp" in a given directory (recursively search directory).

EXAMPLES

EXAMPLE 1

```
Install-MSUpdates -Directory "$dirFiles\MSUpdates"
```

PARAMETERS

-Directory

Directory containing the updates.

```
Type: String
Parameter Sets: (A11)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Install-SCCMSoftwareUpdates

SYNOPSIS

Scans for outstanding SCCM updates to be installed and installs the pending updates.

SYNTAX

```
Install-SCCMSoftwareUpdates [[-SoftwareUpdatesScanwaitInSeconds] <Int32>]
    [[-waitForPendingUpdatesTimeout] <TimeSpan>] [[-ContinueOnError] <Boolean>]
    [<CommonParameters>]
```

DESCRIPTION

Scans for outstanding SCCM updates to be installed and installs the pending updates.

Only compatible with SCCM 2012 Client or higher.

This function can take several minutes to run.

EXAMPLES

EXAMPLE 1

```
Install-SCCMSoftwareUpdates
```

PARAMETERS

-SoftwareUpdatesScanWaitInSeconds

The amount of time to wait in seconds for the software updates scan to complete.
Default is: 180 seconds.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: 180
Accept pipeline input: False
Accept wildcard characters: False
```

-WaitForPendingUpdatesTimeout

The amount of time to wait for missing and pending updates to install before exiting the function.
Default is: 45 minutes.

```
Type: TimeSpan
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: $(New-TimeSpan -Minutes 45)
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Invoke-HKCURRegistrySettingsForAllUsers

SYNOPSIS

Set current user registry settings for all current users and any new users in the future.

SYNTAX

```
Invoke-HKCURRegistrySettingsForAllUsers [-RegistrySettings] <ScriptBlock> [[-UserProfiles] <PSObject[]>] [<CommonParameters>]
```

DESCRIPTION

Set HKCU registry settings for all current and future users by loading their NTUSER.dat registry hive file, and making the modifications.

This function will modify HKCU settings for all users even when executed under the SYSTEM account.

To ensure new users in the future get the registry edits, the Default User registry hive used to provision the registry for new users is modified.

This function can be used as an alternative to using ActiveSetup for registry settings.

The advantage of using this function over ActiveSetup is that a user does not have to log off and log back on before the changes take effect.

EXAMPLES

EXAMPLE 1

```
[scriptblock]$HKCURRegistrySettings = {
```

```
Set-RegistryKey -Key 'HKCU\Software\Microsoft\Office\14.0\Common' -Name 'qmenable' -Value 0  
-Type DWord -SID $UserProfile.SID  
Set-RegistryKey -Key 'HKCU\Software\Microsoft\Office\14.0\Common' -Name  
'updatereliabilitydata' -Value 1 -Type DWord -SID $UserProfile.SID  
}  
Invoke-HKCURRegistrySettingsForAllUsers -RegistrySettings $HKCURRegistrySettings
```

PARAMETERS

-RegistrySettings

Script block which contains HKCU registry settings which should be modified for all users on the system.

Must specify the -SID parameter for all HKCU settings.

```
Type: ScriptBlock
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-UserProfiles

Specify the user profiles to modify HKCU registry settings for.

Default is all user profiles except for system profiles.

```
Type: PSScriptObject[]
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: (Get-UserProfiles)
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Invoke-ObjectMethod

SYNOPSIS

Invoke method on any object.

SYNTAX

Positional (Default)

```
Invoke-ObjectMethod [-InputObject] <Object> [-MethodName] <String> [[-ArgumentList] <Object[]>]  
[<CommonParameters>]
```

Named

```
Invoke-ObjectMethod [-InputObject] <Object> [-MethodName] <String> [-Parameter]  
<Hashtable>  
[<CommonParameters>]
```

DESCRIPTION

Invoke method on any object with or without using named parameters.

EXAMPLES

EXAMPLE 1

```
$shellApp = New-Object -ComObject 'Shell.Application'
```

```
$null = Invoke-ObjectMethod -InputObject $shellApp -MethodName 'MinimizeAll'  
Minimizes all windows.
```

EXAMPLE 2

```
$shellApp = New-Object -ComObject 'Shell.Application'
```

```
$null = Invoke-ObjectMethod -InputObject $shellApp -MethodName 'Explore' -Parameter  
@{'vDir'='C:\Windows'}  
Opens the C:\Windows folder in a Windows Explorer window.
```

PARAMETERS

-InputObject

Specifies an object which has methods that can be invoked.

Type: Object
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-MethodName

Specifies the name of a method to invoke.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ArgumentList

Argument to pass to the method being executed.

Allows execution of method without specifying named parameters.

```
Type: Object[]
Parameter Sets: Positional
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Parameter

Argument to pass to the method being executed.

Allows execution of method by using named parameters.

```
Type: Hashtable
Parameter Sets: Named
Aliases:

Required: True
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Invoke-RegisterOrUnregisterDLL

SYNOPSIS

Register or unregister a DLL file.

SYNTAX

```
Invoke-RegisterOrUnregisterDLL [-FilePath] <string> [[-DLLAction] <string>] [[-ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Register or unregister a DLL file using regsvr32.exe.

Function can be invoked using alias: 'Register-DLL' or 'Unregister-DLL'.

EXAMPLES

EXAMPLE 1

```
Register-DLL -FilePath "C:\Test\DtTLSFileToDMSComp.dll"
```

Register DLL file using the "Register-DLL" alias for this function

EXAMPLE 2

```
UnRegister-DLL -FilePath "C:\Test\DtTLSFileToDMSComp.dll"
```

Unregister DLL file using the "Unregister-DLL" alias for this function

EXAMPLE 3

```
Invoke-RegisterOrUnregisterDLL -FilePath "C:\Test\DtTLSFileToDMSComp.dll" -  
DLLAction 'Register'
```

Register DLL file using the actual name of this function

PARAMETERS

-FilePath

Path to the DLL file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-DLLAction

Specify whether to register or unregister the DLL.

Optional if function is invoked using 'Register-DLL' or 'Unregister-DLL' alias.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Invoke-SCCMTask

SYNOPSIS

Triggers SCCM to invoke the requested schedule task id.

SYNTAX

```
Invoke-SCCMTask [-ScheduleID] <String> [[-ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Triggers SCCM to invoke the requested schedule task id.

EXAMPLES

EXAMPLE 1

```
Invoke-SCCMTask 'SoftwareupdatesScan'
```

EXAMPLE 2

```
Invoke-SCCMTask
```

PARAMETERS

-ScheduleID

Name of the schedule id to trigger.

Options: HardwareInventory, SoftwareInventory, HeartbeatDiscovery, SoftwareInventoryFileCollection, RequestMachinePolicy, EvaluateMachinePolicy, LocationServicesCleanup, SoftwareMeteringReport, SourceUpdate, PolicyAgentCleanup, RequestMachinePolicy2, CertificateMaintenance, PeerDistributionPointStatus, PeerDistributionPointProvisioning, ComplianceIntervalEnforcement, SoftwareUpdatesAgentAssignmentEvaluation, UploadStateMessage, StateMessageManager, SoftwareUpdatesScan, AMTProvisionCycle, UpdateStorePolicy, StateSystemBulkSend, ApplicationManagerPolicyAction, PowerManagementStartSummarizer

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

New-Folder

SYNOPSIS

Create a new folder.

SYNTAX

```
New-Folder [-Path] <String> [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Create a new folder if it does not exist.

EXAMPLES

EXAMPLE 1

```
New-Folder -Path "$env:winDir\System32"
```

PARAMETERS

-Path

Path to the new folder to create.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

New-MsiTransform

SYNOPSIS

Create a transform file for an MSI database.

SYNTAX

```
New-MsiTransform [-MsiPath] <String> [[-ApplyTransformPath] <String>] [[-  
NewTransformPath] <String>]  
[-TransformProperties] <Hashtable> [[-ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Create a transform file for an MSI database and create/modify properties in the Properties table.

EXAMPLES

EXAMPLE 1

```
[hashtable]$TransformProperties = {  
  
'ALLUSERS' = '1'  
'AgreeToLicense' = 'Yes'  
'REBOOT' = 'ReallySuppress'  
'RebootYesNo' = 'No'  
'ROOTDRIVE' = 'C:'  
}  
New-MsiTransform -MsiPath 'C:\Temp\PSADTInstall.msi' -TransformProperties  
$TransformProperties
```

PARAMETERS

-MsiPath

Specify the path to an MSI file.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-ApplyTransformPath

Specify the path to a transform which should be applied to the MSI database before any new properties are created or modified.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-NewTransformPath

Specify the path where the new transform file with the desired properties will be created.
If a transform file of the same name already exists, it will be deleted before a new one is created.
Default is: a) If -ApplyTransformPath was specified but not -NewTransformPath, then
<ApplyTransformPath>.new.mst
b) If only -MsiPath was specified, then <MsiPath>.mst

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-TransformProperties

Hashtable which contains calls to Set-MsiProperty for configuring the desired properties which should be included in new transform file.

Example hashtable: [hashtable]\$TransformProperties = @{ 'ALLUSERS' = '1' }

```
Type: Hashtable
Parameter Sets: (All)
Aliases:

Required: True
Position: 4
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: True
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

New-Shortcut

SYNOPSIS

Creates a new .lnk or .url type shortcut

PSCX Cmdlet: Creates shell shortcuts.

SYNTAX

```
New-Shortcut [-Path] <String> [-TargetPath] <String> [[-Arguments] <String>] [[-IconLocation] <String>]
    [[-IconIndex] <String>] [[-Description] <String>] [[-WorkingDirectory]
<String>] [[-WindowSize] <String>]
    [-RunAsAdmin] [[-Hotkey] <String>] [[-ContinueOnError] <Boolean>]
    [<CommonParameters>]
```

DESCRIPTION

Creates a new shortcut .lnk or .url file, with configurable options

Creates shell shortcuts.

EXAMPLES

EXAMPLE 1

```
New-Shortcut -Path "$env:ProgramData\Microsoft\Windows\Start Menu\My Shortcut.lnk" -TargetPath "$env:winDir\system32\notepad.exe" -IconLocation "$env:winDir\system32\notepad.exe" -Description 'Notepad' -WorkingDirectory "$env:HomeDrive\$env:HomePath"
```

PARAMETERS

-Path

Path to save the shortcut

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-TargetPath

Target path or URL that the shortcut launches

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Arguments

Arguments to be passed to the target path

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-IconLocation

Location of the icon used for the shortcut

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-IconIndex

Executables, DLLs, ICO files with multiple icons need the icon index to be specified

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Description

Description of the shortcut

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-WorkingDirectory

Working Directory to be used for the target path

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 7
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-WindowState

Windows style of the application.

Options: Normal, Maximized, Minimized.

Default is: Normal.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 8
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-RunAsAdmin

Set shortcut to run program as administrator.

This option will prompt user to elevate when executing shortcut.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-Hotkey

Create a Hotkey to launch the shortcut, e.g.

"CTRL+SHIFT+F"

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 9
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 10
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

New-ZipFile

SYNOPSIS

Create a new zip archive or add content to an existing archive.

SYNTAX

CreateFromDirectory (Default)

```
New-ZipFile [-DestinationArchiveDirectoryPath] <String> [-
DestinationArchiveFileName] <String>
[-SourceDirectoryPath] <String[]> [-RemoveSourceAfterArchiving] [-
overwriteArchive]
[[[-ContinueOnError] <Boolean>] [<CommonParameters>]]
```

CreateFromFile

```
New-ZipFile [-DestinationArchiveDirectoryPath] <String> [-
DestinationArchiveFileName] <String>
[-SourceFilePath] <String[]> [-RemoveSourceAfterArchiving] [-overwriteArchive]
[[[-ContinueOnError] <Boolean>]
 [<CommonParameters>]]
```

DESCRIPTION

Create a new zip archive or add content to an existing archive by using the Shell object .CopyHere method.

EXAMPLES

EXAMPLE 1

```
New-ZipFile -DestinationArchiveDirectoryPath 'E:\Testing' -  
DestinationArchiveFileName 'TestingLogs.zip' -SourceDirectory 'E:\Testing\Logs'
```

PARAMETERS

-DestinationArchiveDirectoryPath

The path to the directory path where the zip archive will be saved.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-DestinationArchiveFileName

The name of the zip archive.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 2  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-SourceDirectoryPath

The path to the directory to be archived, specified as absolute paths.

```
Type: String[]  
Parameter Sets: CreateFromDirectory  
Aliases:  
  
Required: True  
Position: 3  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-SourceFilePath

The path to the file to be archived, specified as absolute paths.

```
Type: String[]
Parameter Sets: CreateFromFile
Aliases:

Required: True
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-RemoveSourceAfterArchiving

Remove the source path after successfully archiving the content.

Default is: \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-OverWriteArchive

Overwrite the destination archive path if it already exists.

Default is: \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Remove-File

SYNOPSIS

Removes one or more items from a given path on the filesystem.

SYNTAX

Path

```
Remove-File -Path <String[]> [-Recurse] [-ContinueOnError <Boolean>]
[<CommonParameters>]
```

LiteralPath

```
Remove-File -LiteralPath <String[]> [-Recurse] [-ContinueOnError <Boolean>]
[<CommonParameters>]
```

DESCRIPTION

Removes one or more items from a given path on the filesystem.

EXAMPLES

EXAMPLE 1

```
Remove-File -Path 'C:\Windows\Downloaded Program Files\Temp.inf'
```

EXAMPLE 2

```
Remove-File -LiteralPath 'C:\Windows\Downloaded Program Files' -Recurse
```

PARAMETERS

-Path

Specifies the path on the filesystem to be resolved.

The value of Path will accept wildcards.

Will accept an array of values.

Type: String[]

Parameter Sets: Path

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-LiteralPath

Specifies the path on the filesystem to be resolved.

The value of LiteralPath is used exactly as it is typed; no characters are interpreted as wildcards.

Will accept an array of values.

Type: String[]

Parameter Sets: LiteralPath

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-Recurse

Deletes the files in the specified location(s) and in all child items of the location(s).

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Remove-Folder

SYNOPSIS

Remove folder and files if they exist.

SYNTAX

```
Remove-Folder [-Path] <String> [-DisableRecursion] [[-ContinueOnError]
<Boolean>] [<CommonParameters>]
```

DESCRIPTION

Remove folder and all files with or without recursion in a given path.

EXAMPLES

EXAMPLE 1

```
Remove-Folder -Path "$env:winDir\Downloaded Program Files"
```

PARAMETERS

-Path

Path to the folder to remove.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-DisableRecursion

Disables recursion while deleting.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 2  
Default value: True  
Accept pipeline input: False  
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Remove-InvalidFileNameChars

SYNOPSIS

Remove invalid characters from the supplied string.

SYNTAX

```
Remove-InvalidFileNameChars [-Name] <String> [<CommonParameters>]
```

DESCRIPTION

Remove invalid characters from the supplied string and returns a valid filename as a string.

EXAMPLES

EXAMPLE 1

```
Remove-InvalidFileNameChars -Name "Filename/\1"
```

PARAMETERS

-Name

Name of the file to parse

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This function always returns a string however it can be empty if the name only contains invalid characters.

Do not use this command for an entire path as " is not a valid filename character.

RELATED LINKS

<http://psappdeploytoolkit.com>

Remove-MSIApplications

SYNOPSIS

Removes all MSI applications matching the specified application name.

SYNTAX

```
Remove-MSIApplications [-Name] <String> [-Exact] [-WildCard] [[-Parameters]
<String>]
[[[-AddParameters] <String>] [[-FilterApplication] <Array>] [[-
ExcludeFromUninstall] <Array>]
[-IncludeUpdatesAndHotfixes] [[-LoggingOptions] <string>] [[-private:LogName]
<String>] [-PassThru]
[[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Removes all MSI applications matching the specified application name.

Enumerates the registry for installed applications matching the specified application name and uninstalls that application using the product code, provided the uninstall string matches "msiexec".

EXAMPLES

EXAMPLE 1

```
Remove-MSIApplications -Name 'Adobe Flash'
```

Removes all versions of software that match the name "Adobe Flash"

EXAMPLE 2

```
Remove-MSIApplications -Name 'Adobe'
```

Removes all versions of software that match the name "Adobe"

EXAMPLE 3

```
Remove-MSIApplications -Name 'Java 8 Update' -FilterApplication  
('Is64BitApplication', $false, 'Exact'), ('Publisher', 'oracle corporation',  
'Exact')
```

Removes all versions of software that match the name "Java 8 Update" where the software is 32-bits and the publisher is "Oracle Corporation".

EXAMPLE 4

```
Remove-MSIApplications -Name 'Java 8 Update' -FilterApplication (, ('Publisher',  
'oracle corporation', 'Exact')) -ExcludeFromUninstall (, ('DisplayName', 'Java 8  
update 45', 'Contains'))
```

Removes all versions of software that match the name "Java 8 Update" and also have "Oracle Corporation" as the Publisher; however, it does not uninstall "Java 8 Update 45" of the software.
NOTE: if only specifying a single row in the two-dimensional arrays, the array must have the extra parentheses and leading comma as in this example.

EXAMPLE 5

```
Remove-MSIApplications -Name 'Java 8 Update' -ExcludeFromUninstall (,  
( 'DisplayName', 'Java 8 Update 45', 'Contains'))
```

Removes all versions of software that match the name "Java 8 Update"; however, it does not uninstall "Java 8 Update 45" of the software.

NOTE: if only specifying a single row in the two-dimensional array, the array must have the extra parentheses and leading comma as in this example.

EXAMPLE 6

```
Remove-MSIApplications -Name 'Java 8 Update' -ExcludeFromUninstall
```

```
('Is64BitApplication', $true, 'Exact'),  
( 'DisplayName', 'Java 8 Update 45', 'Exact'),  
( 'DisplayName', 'Java 8 Update 4*', 'WildCard'),  
( 'DisplayName', 'Java \d Update \d{3}', 'RegEx'),  
( 'DisplayName', 'Java 8 Update', 'Contains')
```

Removes all versions of software that match the name "Java 8 Update"; however, it does not uninstall 64-bit versions of the software, Update 45 of the software, or any Update that starts with 4.

PARAMETERS

-Name

The name of the application to uninstall.

Performs a contains match on the application display name by default.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Exact

Specifies that the named application must be matched using the exact name.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-WildCard

Specifies that the named application must be matched using a wildcard search.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-Parameters

Overrides the default parameters specified in the XML configuration file.

Uninstall default is: "REBOOT=ReallySuppress /QN".

```
Type: String
Parameter Sets: (All)
Aliases: Arguments

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-AddParameters

Adds to the default parameters specified in the XML configuration file.
Uninstall default is: "REBOOT=ReallySuppress /QN".

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-FilterApplication

Two-dimensional array that contains one or more (property, value, match-type) sets that should be used to filter the list of results returned by Get-InstalledApplication to only those that should be uninstalled.

Properties that can be filtered upon: ProductCode, DisplayName, DisplayVersion, UninstallString, InstallSource, InstallLocation, InstallDate, Publisher, Is64BitApplication

```
Type: Array
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: @(@(())
Accept pipeline input: False
Accept wildcard characters: False
```

-ExcludeFromUninstall

Two-dimensional array that contains one or more (property, value, match-type) sets that should be excluded from uninstall if found.

Properties that can be excluded: ProductCode, DisplayName, DisplayVersion, UninstallString, InstallSource, InstallLocation, InstallDate, Publisher, Is64BitApplication

```
Type: Array
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: @(@(())
Accept pipeline input: False
Accept wildcard characters: False
```

-IncludeUpdatesAndHotfixes

Include matches against updates and hotfixes in results.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-LoggingOptions

Overrides the default logging options specified in the XML configuration file.

Default options are: "/L*v".

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-private:LogName

Overrides the default logfile name

```
Type: String
Parameter Sets: (All)
Aliases: LogName

Required: False
Position: 7
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-PassThru

Returns ExitCode, STDOut, and STDErr output from the process.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error occurred while trying to start the processes.

Default: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 8
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

More reading on how to create arrays if having trouble with -FilterApplication or -ExcludeFromUninstall parameter: <http://blogs.msdn.com/b/powershell/archive/2007/01/23/array-literals-in-powershell.aspx>

RELATED LINKS

<http://psappdeploytoolkit.com>

Remove-RegistryKey

SYNOPSIS

Deletes the specified registry key or value.

SYNTAX

```
Remove-RegistryKey [-Key] <String> [[-Name] <String>] [-Recurse] [[-SID]
<String>]
[[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Deletes the specified registry key or value.

EXAMPLES

EXAMPLE 1

```
Remove-RegistryKey -Key
'HKEY_CURRENT_USER\Software\Microsoft\Windows\CurrentVersion\RunOnce'
```

EXAMPLE 2

```
Remove-RegistryKey -Key 'HKLM:SOFTWARE\Microsoft\Windows\CurrentVersion\Run' -
Name 'RunAppInstall'
```

PARAMETERS

-Key

Path of the registry key to delete.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Name

Name of the registry value to delete.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Recurse

Delete registry key recursively.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-SID

The security identifier (SID) for a user.

Specifying this parameter will convert a HKEY_CURRENT_USER registry key to the HKEY_USERS\$SID format.

Specify this parameter from the Invoke-HKCURegistrySettingsForAllUsers function to read/edit HKCU registry settings for all users on the system.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Resolve-Error

SYNOPSIS

Enumerate error record details.

SYNTAX

```
Resolve-Error [[-ErrorRecord] <Array>] [[-Property] <String[]>] [-GetErrorRecord] [-GetErrorInvocation] [-GetErrorException] [-GetErrorInnerException] [<CommonParameters>]
```

DESCRIPTION

Enumerate an error record, or a collection of error record, properties.

By default, the details for the last error will be enumerated.

EXAMPLES

EXAMPLE 1

```
Resolve-Error
```

EXAMPLE 2

```
Resolve-Error -Property *
```

EXAMPLE 3

```
Resolve-Error -Property InnerException
```

EXAMPLE 4

```
Resolve-Error -GetErrorInvocation:$false
```

PARAMETERS

-ErrorRecord

The error record to resolve.

The default error record is the latest one: \$global:Error[0].

This parameter will also accept an array of error records.

```
Type: Array
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False
```

-Property

The list of properties to display from the error record.

Use "*" to display all properties.

Default list of error properties is: Message, FullyQualifiedErrorId, ScriptStackTrace, PositionMessage, InnerException

```
Type: String[]
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value:
('Message', 'InnerException', 'FullyQualifiedErrorId', 'ScriptStackTrace', 'Position
Message')
Accept pipeline input: False
Accept wildcard characters: False
```

-GetErrorRecord

Get error record details as represented by \$_.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-GetErrorInvocation

Get error record invocation information as represented by \$_.InvocationInfo.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-GetErrorException

Get error record exception details as represented by `$_.Exception`.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-GetErrorInnerException

Get error record inner exception details as represented by `$_.Exception.InnerException`.

Will retrieve all inner exceptions if there is more than one.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Send-Keys

SYNOPSIS

Send a sequence of keys to one or more application windows.

SYNTAX

```
Send-Keys [[-WindowTitle] <String>] [-GetAllWindowsTitles] [[-WindowHandle]
<IntPtr>] [[-Keys] <String>]
[[-WaitSeconds] <Int32>] [<CommonParameters>]
```

DESCRIPTION

Send a sequence of keys to one or more application window.

If window title searched for returns more than one window, then all of them will receive the sent keys.

Function does not work in SYSTEM context unless launched with "psexec.exe -s -i" to run it as an interactive process under the SYSTEM account.

EXAMPLES

EXAMPLE 1

```
Send-Keys -WindowTitle 'foobar - Notepad' -Key 'Hello world'
```

Send the sequence of keys "Hello world" to the application titled "foobar - Notepad".

EXAMPLE 2

```
Send-Keys -WindowTitle 'foobar - Notepad' -Key 'Hello world' -WaitSeconds 5
```

Send the sequence of keys "Hello world" to the application titled "foobar - Notepad" and wait 5 seconds.

EXAMPLE 3

```
Send-Keys -WindowHandle ([IntPtr]17368294) -Key 'Hello world'
```

Send the sequence of keys "Hello world" to the application with a Window Handle of '17368294'.

PARAMETERS

-WindowTitle

The title of the application window to search for using regex matching.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-GetAllWindowTitles

Get titles for all open windows on the system.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-WindowHandle

Send keys to a specific window where the Window Handle is already known.

```
Type: IntPtr
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Keys

The sequence of keys to send.

Info on Key input at: [http://msdn.microsoft.com/en-us/library/System.Windows.Forms.SendKeys\(v=vs.100\).aspx](http://msdn.microsoft.com/en-us/library/System.Windows.Forms.SendKeys(v=vs.100).aspx)

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-WaitSeconds

An optional number of seconds to wait after the sending of the keys.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

[http://msdn.microsoft.com/en-us/library/System.Windows.Forms.SendKeys\(v=vs.100\).aspx](http://msdn.microsoft.com/en-us/library/System.Windows.Forms.SendKeys(v=vs.100).aspx)
<http://psappdeploytoolkit.com>

Set-ActiveSetup

SYNOPSIS

Creates an Active Setup entry in the registry to execute a file for each user upon login.

SYNTAX

Create

```
Set-ActiveSetup -StubExePath <String> [-Arguments <String>] [-Description
<String>] [-Key <String>]
[-Version <String>] [-Locale <String>] [-DisableActiveSetup] [-
ExecuteForCurrentUser <Boolean>]
[-ContinueOnError <Boolean>] [<CommonParameters>]
```

Purge

```
Set-ActiveSetup [-Key <String>] [-PurgeActiveSetupKey] [-ContinueOnError
<Boolean>] [<CommonParameters>]
```

DESCRIPTION

Active Setup allows handling of per-user changes registry/file changes upon login.
A registry key is created in the HKLM registry hive which gets replicated to the HKCU hive when a user logs in.
If the "Version" value of the Active Setup entry in HKLM is higher than the version value in HKCU, the file referenced in "StubPath" is executed.

This Function:

- Creates the registry entries in HKLM:SOFTWARE\Microsoft\Active Setup\Installed Components\$installName.
- Creates StubPath value depending on the file extension of the \$StubExePath parameter.
- Handles Version value with YYYYMMDDHHMMSS granularity to permit re-installs on the same day and still trigger Active Setup after Version increase.
- Copies/overwrites the StubPath file to \$StubExePath destination path if file exists in 'Files' subdirectory of script directory.
- Executes the StubPath file for the current user as long as not in Session 0 (no need to logout/login to trigger Active Setup).

EXAMPLES

EXAMPLE 1

```
Set-ActiveSetup -StubExePath 'C:\Users\Public\Company\ProgramUserConfig.vbs' -Arguments '/silent' -Description 'Program User Config' -Key 'ProgramUserConfig' -Locale 'en'
```

EXAMPLE 2

```
Set-ActiveSetup -StubExePath "$env:windir\regedit.exe" -Arguments "/s`%"SystemDrive%"\\Program Files (x86)\\PS App Deploy\\PSAppDeployHKCUsettings.reg`"" -Description 'PS App Deploy Config' -Key 'PS_App_Deploy_Config' -ContinueOnError $true
```

EXAMPLE 3

```
Set-ActiveSetup -Key 'ProgramUserConfig' -PurgeActiveSetupKey
```

Deletes "ProgramUserConfig" active setup entry from all registry hives.

PARAMETERS

-StubExePath

Full destination path to the file that will be executed for each user that logs in.
If this file exists in the 'Files' subdirectory of the script directory, it will be copied to the destination path.

```
Type: String
Parameter Sets: Create
Aliases:

Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Arguments

Arguments to pass to the file being executed.

```
Type: String
Parameter Sets: Create
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Description

Description for the Active Setup.

Users will see "Setting up personalized settings for: \$Description" at logon.

Default is: \$installName.

```
Type: String
Parameter Sets: Create
Aliases:

Required: False
Position: Named
Default value: $installName
Accept pipeline input: False
Accept wildcard characters: False
```

-Key

Name of the registry key for the Active Setup entry.

Default is: \$installName.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: $installName
Accept pipeline input: False
Accept wildcard characters: False
```

-Version

Optional.

Specify version for Active setup entry.

Active Setup is not triggered if Version value has more than 8 consecutive digits.

Use commas to get around this limitation.

```
Type: String
Parameter Sets: Create
Aliases:

Required: False
Position: Named
Default value: ((Get-Date -Format 'yyMM,ddHH,mmss')).ToString()
Accept pipeline input: False
Accept wildcard characters: False
```

-Locale

Optional.

Arbitrary string used to specify the installation language of the file being executed.

Not replicated to HKCU.

```
Type: String
Parameter Sets: Create
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-DisableActiveSetup

Disables the Active Setup entry so that the StubPath file will not be executed.

```
Type: SwitchParameter
Parameter Sets: Create
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-PurgeActiveSetupKey

Remove Active Setup entry from HKLM registry hive.

Will also load each logon user's HKCU registry hive to remove Active Setup entry.

```
Type: SwitchParameter
Parameter Sets: Purge
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ExecuteForCurrentUser

Specifies whether the StubExePath should be executed for the current user.
Since this user is already logged in, the user won't have the application started without logging out and logging back in.
Default: \$True

```
Type: Boolean
Parameter Sets: Create
Aliases:

Required: False
Position: Named
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

Original code borrowed from: Denis St-Pierre (Ottawa, Canada), Todd MacNaught (Ottawa, Canada)

RELATED LINKS

<http://psappdeploytoolkit.com>

Set-DeferHistory

SYNOPSIS

Set the history of deferrals in the registry for the current application.

SYNTAX

```
Set-DeferHistory [[-deferTimesRemaining] <string>] [[-deferDeadline] <String>]  
[<CommonParameters>]
```

DESCRIPTION

Set the history of deferrals in the registry for the current application.

EXAMPLES

EXAMPLE 1

```
Set-DeferHistory
```

PARAMETERS

-deferTimesRemaining

The number of deferrals remaining

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-deferDeadline

The deadline for deferral

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Set-IniValue

SYNOPSIS

Opens an INI file and sets the value of the specified section and key.

SYNTAX

```
Set-IniValue [-FilePath] <String> [-Section] <String> [-Key] <String> [-Value]
<Object>
[[[-ContinueOnError] <Boolean>] [<CommonParameters>]]
```

DESCRIPTION

Opens an INI file and sets the value of the specified section and key.

EXAMPLES

EXAMPLE 1

```
Set-IniValue -FilePath "$env:ProgramFilesx86\IBM\Notes\notes.ini" -Section
'Notes' -Key 'KeyFileName' -Value 'MyFile.ID'
```

PARAMETERS

-FilePath

Path to the INI file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Section

Section within the INI file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Key

Key within the section of the INI file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Value

Value for the key within the section of the INI file.

To remove a value, set this variable to \$null.

```
Type: Object
Parameter Sets: (All)
Aliases:

Required: True
Position: 4
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Set-ItemPermission

SYNOPSIS

Allow you to easily change permissions on files or folders

SYNTAX

EnableInheritance

```
Set-ItemPermission [-Path] <String> [-EnableInheritance] [<CommonParameters>]
```

DisableInheritance

```
Set-ItemPermission [-Path] <String> [-User] <string[]> [-Permission] <String[]>
  [[-PermissionType] <String>]
  [[-Inheritance] <String[]>] [[-Propagation] <String>] [[-Method] <String>]
  [<CommonParameters>]
```

EXAMPLES

EXAMPLE 1

```
will grant FullControl permissions to 'John' and 'Users' on 'C:\Temp' and its
files and folders children.
```

```
PS C:>Set-ItemPermission -Path "C:\Temp" -User "DOMAIN\John", "BUILTIN\Utilisateurs" -
Permission FullControl -Inheritance ObjectInherit,ContainerInherit
```

EXAMPLE 2

```
will grant Read permissions to 'John' on 'C:\Temp\pic.png'
```

```
PS C:>Set-ItemPermission -Path "C:\Temp\pic.png" -User "DOMAIN\John" -Permission Read
```

EXAMPLE 3

```
will remove all permissions to 'John' on 'C:\Temp\Private'
```

```
PS C:>Set-ItemPermission -Path "C:\Temp\Private" -User "DOMAIN\John" -Permission None -
Method RemoveAll
```

PARAMETERS

-Path

Path to the folder or file you want to modify (ex: C:\Temp)

```
Type: String
Parameter Sets: (All)
Aliases: File, Folder

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-User

One or more user names (ex: BUILTIN\Users, DOMAIN\Admin) to give the permissions to.
If you want to use SID, prefix it with an asterisk * (ex: *S-1-5-18)

Type: String[]
Parameter Sets: DisableInheritance
Aliases: Username, Users, SID, Usernames

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Permission

Permission or list of permissions to be set/added/removed/replaced.
To see all the possible permissions go to '<http://technet.microsoft.com/fr-fr/library/ff730951.aspx>'.

Permission DeleteSubdirectoriesAndFiles does not apply to files.

Type: String[]
Parameter Sets: DisableInheritance
Aliases: Acl, Grant, Permissions, Deny

Required: True
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-PermissionType

Sets Access Control Type of the permissions.
Allowed options: Allow, Deny Default: Allow

Type: String
Parameter Sets: DisableInheritance
Aliases: AccessControlType

Required: False
Position: 4
Default value: Allow
Accept pipeline input: False
Accept wildcard characters: False

-Inheritance

Sets permission inheritance.

Does not apply to files.

Multiple options can be specified.

Allowed options: ObjectInherit, ContainerInherit, None Default: None

None - The permission entry is not inherited by child objects, ObjectInherit - The permission entry is inherited by child leaf objects.

ContainerInherit - The permission entry is inherited by child container objects.

```
Type: String[]
Parameter Sets: DisableInheritance
Aliases:

Required: False
Position: 5
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Propagation

Sets how to propagate inheritance.

Does not apply to files.

Allowed options: None, InheritOnly, NoPropagateInherit Default: None

None - Specifies that no inheritance flags are set.

NoPropagateInherit - Specifies that the permission entry is not propagated to child objects.

InheritOnly - Specifies that the permission entry is propagated only to child objects.

This includes both container and leaf child objects.

```
Type: String
Parameter Sets: DisableInheritance
Aliases:

Required: False
Position: 6
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Method

Specifies which method will be used to apply the permissions.

Allowed options: Add, Set, Reset.

Add - adds permissions rules but it does not remove previous permissions, Set - overwrites matching permission rules with new ones, Reset - removes matching permissions rules and then adds permission rules, Remove - Removes matching permission rules, RemoveSpecific - Removes specific permissions, RemoveAll - Removes all permission rules for specified user/s

Default: Add

```
Type: String
Parameter Sets: DisableInheritance
Aliases: ApplyMethod, ApplicationMethod

Required: False
Position: 7
Default value: Add
Accept pipeline input: False
Accept wildcard characters: False
```

-EnableInheritance

Enables inheritance on the files/folders.

```
Type: SwitchParameter
Parameter Sets: EnableInheritance
Aliases:

Required: True
Position: 2
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

Original Author : Julian DA CUNHA - dacunha.julian@gmail.com, used with permission

RELATED LINKS

<http://psappdeploytoolkit.com>

Set-MsiProperty

SYNOPSIS

Set a property in the MSI property table.

SYNTAX

```
Set-MsiProperty [-DataBases] <__ComObject> [-PropertyName] <String> [-
PropertyValue] <String>
[[[-ContinueOnError]] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Set a property in the MSI property table.

EXAMPLES

EXAMPLE 1

```
Set-MsiProperty -DataBases $TempMsiPathDatabase -PropertyName 'ALLUSERS' -
PropertyValue '1'
```

PARAMETERS

-DataBase

Specify a ComObject representing an MSI database opened in view/modify/update mode.

```
Type: __ComObject
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-PropertyName

The name of the property to be set/modified.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-PropertyValue

The value of the property to be set/modified.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: True
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Set-PinnedApplication

SYNOPSIS

Pins or unpins a shortcut to the start menu or task bar.

SYNTAX

```
Set-PinnedApplication [-Action] <String> [-FilePath] <String>
[<CommonParameters>]
```

DESCRIPTION

Pins or unpins a shortcut to the start menu or task bar.

This should typically be run in the user context, as pinned items are stored in the user profile.

EXAMPLES

EXAMPLE 1

```
Set-PinnedApplication -Action 'PintoStartMenu' -FilePath
"$env:ProgramFilesX86\IBM\Lotus\Notes\notes.exe"
```

EXAMPLE 2

```
Set-PinnedApplication -Action 'UnpinfromTaskbar' -FilePath  
"$env:ProgramFiles(x86)\IBM\Lotus\Notes\notes.exe"
```

PARAMETERS

-Action

Action to be performed.

Options: 'PintoStartMenu','UnpinfromStartMenu','PintoTaskbar','UnpinfromTaskbar'.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

-FilePath

Path to the shortcut file to be pinned or unpinned.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 2

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

Windows 10 logic borrowed from Stuart Pearson (<https://pinto10blog.wordpress.com/2016/09/10/pinto10/>)

RELATED LINKS

<http://psappdeploytoolkit.com>

Set-RegistryKey

SYNOPSIS

Creates a registry key name, value, and value data; it sets the same if it already exists.

SYNTAX

```
Set-RegistryKey [-Key] <String> [[-Name] <String>] [[-Value] <Object>] [[-Type]
<RegistryValuekind>]
[[-SID] <String>] [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Creates a registry key name, value, and value data; it sets the same if it already exists.

EXAMPLES

EXAMPLE 1

```
Set-RegistryKey -Key $blockedAppPath -Name 'Debugger' -Value
$blockedAppDebuggerValue
```

EXAMPLE 2

```
Set-RegistryKey -Key 'HKEY_LOCAL_MACHINE\SOFTWARE' -Name 'Application' -Type
'Dword' -Value '1'
```

EXAMPLE 3

```
Set-RegistryKey -Key
'HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\RunOnce' -Name
'Debugger' -Value $blockedAppDebuggerValue -Type String
```

EXAMPLE 4

```
Set-RegistryKey -Key 'HKCU\Software\Microsoft\Example' -Name 'Data' -Value
(0x01,0x01,0x01,0x01,0x01,0x01,0x01,0x01,0x01,0x01,0x01,0x02,0x01,0x01,0x01
,0x01,0x01,0x01,0x02,0x01,0x01,0x01,0x01,0x01,0x01,0x00,0x01,0x01,0x01
,0x02,0x02,0x02) -Type 'Binary'
```

EXAMPLE 5

```
Set-RegistryKey -Key 'HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Example' -Value
'(Default)'
```

PARAMETERS

-Key

The registry key path.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Name

The value name.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Value

The value data.

```
Type: Object
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Type

The type of registry value to create or set.

Options: 'Binary','DWord','ExpandString','MultiString','None','QWord','String','Unknown'.

Default: String.

Dword should be specified as a decimal.

```
Type: RegistryValueKind
Parameter Sets: (All)
Aliases:

Accepted values: Unknown, String, ExpandString, Binary, Dword, Multistring,
Qword, None

Required: False
Position: 4
Default value: String
Accept pipeline input: False
Accept wildcard characters: False
```

-SID

The security identifier (SID) for a user.

Specifying this parameter will convert a HKEY_CURRENT_USER registry key to the HKEY_USERS\$SID format.

Specify this parameter from the Invoke-HKCURegistrySettingsForAllUsers function to read/edit HKCU registry settings for all users on the system.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Set-ServiceStartMode

SYNOPSIS

Set the service startup mode.

SYNTAX

```
Set-ServiceStartMode [-Name] <String> [[-ComputerName] <string>] [-StartMode]
<String>
[[[-ContinueOnError] <Boolean>] [<CommonParameters>]]
```

DESCRIPTION

Set the service startup mode.

EXAMPLES

EXAMPLE 1

```
Set-ServiceStartMode -Name 'wuauserv' -StartMode 'Automatic (Delayed start)'
```

PARAMETERS

-Name

Specify the name of the service.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ComputerName

Specify the name of the computer.

Default is: the local computer.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: $env:ComputerName
Accept pipeline input: False
Accept wildcard characters: False
```

-StartMode

Specify startup mode for the service.

Options: Automatic, Automatic (Delayed Start), Manual, Disabled, Boot, System.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 3
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Show-BalloonTip

SYNOPSIS

Displays a balloon tip notification in the system tray.

SYNTAX

```
Show-BalloonTip [-BalloonTipText] <String> [[-BalloonTipTitle] <String>] [[-BalloonTipIcon] <ToolTipIcon>] [[-BalloonTipTime] <Int32>] [<CommonParameters>]
```

DESCRIPTION

Displays a balloon tip notification in the system tray.

EXAMPLES

EXAMPLE 1

```
Show-BalloonTip -BalloonTipText 'Installation Started' -BalloonTipTitle 'Application Name'
```

EXAMPLE 2

```
Show-BalloonTip -BalloonTipIcon 'Info' -BalloonTipText 'Installation Started' -BalloonTipTitle 'Application Name' -BalloonTipTime 1000
```

PARAMETERS

-BalloonTipText

Text of the balloon tip.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-BalloonTipTitle

Title of the balloon tip.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: $installTitle
Accept pipeline input: False
Accept wildcard characters: False
```

-BalloonTipIcon

Icon to be used.

Options: 'Error', 'Info', 'None', 'Warning'.

Default is: Info.

```
Type: ToolTipIcon
Parameter Sets: (All)
Aliases:
Accepted values: None, Info, Warning, Error

Required: False
Position: 3
Default value: Info
Accept pipeline input: False
Accept wildcard characters: False
```

-BalloonTipTime

Time in milliseconds to display the balloon tip.

Default: 500.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: 10000
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Show-DialogBox

SYNOPSIS

Display a custom dialog box with optional title, buttons, icon and timeout.

Show-InstallationPrompt is recommended over this function as it provides more customization and uses consistent branding with the other UI components.

SYNTAX

```
Show-DialogBox [-Text] <String> [-Title <String>] [-Buttons <String>] [-DefaultButton <String>] [-Icon <String>] [-Timeout <String>] [-TopMost <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Display a custom dialog box with optional title, buttons, icon and timeout.

The default button is "OK", the default Icon is "None", and the default Timeout is none.

EXAMPLES

EXAMPLE 1

```
Show-DialogBox -Title 'Installed Complete' -Text 'Installation has completed.  
Please click OK and restart your computer.' -Icon 'Information'
```

EXAMPLE 2

```
Show-DialogBox -Title 'Installation Notice' -Text 'Installation will take  
approximately 30 minutes. Do you wish to proceed?' -Buttons 'OKCancel' -  
DefaultButton 'Second' -Icon 'Exclamation' -Timeout 600 -Topmost $false
```

PARAMETERS

-Text

Text in the message dialog box

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Title

Title of the message dialog box

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: $installTitle
Accept pipeline input: False
Accept wildcard characters: False
```

-Buttons

Buttons to be included on the dialog box.

Options: OK, OKCancel, AbortRetryIgnore, YesNoCancel, YesNo, RetryCancel, CancelTryAgainContinue.

Default: OK.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: OK
Accept pipeline input: False
Accept wildcard characters: False
```

-DefaultButton

The Default button that is selected.

Options: First, Second, Third.

Default: First.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: First
Accept pipeline input: False
Accept wildcard characters: False
```

-Icon

Icon to display on the dialog box.
Options: None, Stop, Question, Exclamation, Information.
Default: None.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-Timeout

Timeout period in seconds before automatically closing the dialog box with the return message "Timeout".
Default: UI timeout value set in the config XML file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: $configInstallationUITimeout
Accept pipeline input: False
Accept wildcard characters: False
```

-TopMost

Specifies whether the message box is a system modal message box and appears in a topmost window.
Default: \$true.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: True
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Show-InstallationProgress

SYNOPSIS

Displays a progress dialog in a separate thread with an updateable custom message.

SYNTAX

```
Show-InstallationProgress [[-StatusMessage] <String>] [[-WindowLocation]
<String>] [[-TopMost] <Boolean>]
[<CommonParameters>]
```

DESCRIPTION

Create a WPF window in a separate thread to display a marquee style progress ellipse with a custom message that can be updated.

The status message supports line breaks.

The first time this function is called in a script, it will display a balloon tip notification to indicate that the installation has started (provided balloon tips are enabled in the configuration).

EXAMPLES

EXAMPLE 1

```
Show-InstallationProgress
```

Uses the default status message from the XML configuration file.

EXAMPLE 2

```
Show-InstallationProgress -StatusMessage 'Installation in Progress...'
```

EXAMPLE 3

```
Show-InstallationProgress -StatusMessage "Installation in Progress...`nThe  
installation may take 20 minutes to complete."
```

EXAMPLE 4

```
Show-InstallationProgress -StatusMessage 'Installation in Progress...' -  
WindowLocation 'BottomRight' -TopMost $false
```

PARAMETERS

-StatusMessage

The status message to be displayed.

The default status message is taken from the XML configuration file.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 1  
Default value: $configProgressMessageInstall  
Accept pipeline input: False  
Accept wildcard characters: False
```

-WindowLocation

The location of the progress window.

Default: just below top, centered.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 2  
Default value: Default  
Accept pipeline input: False  
Accept wildcard characters: False
```

-TopMost

Specifies whether the progress window should be topmost.

Default: \$true.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: True
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Show-InstallationPrompt

SYNOPSIS

Displays a custom installation prompt with the toolkit branding and optional buttons.

SYNTAX

```
Show-InstallationPrompt [[-Title] <String>] [[-Message] <string>] [[-MessageAlignment] <String>]
[[[-ButtonRightText] <String>] [[-ButtonLeftText] <string>] [[-ButtonMiddleText] <String>] [[-Icon] <String>]
[-Nowait] [-PersistPrompt] [[-Minimizewindows] <Boolean>] [[-Timeout] <Int32>]
[[-ExitOnTimeout] <Boolean>]
[<CommonParameters>]
```

DESCRIPTION

Any combination of Left, Middle or Right buttons can be displayed.

The return value of the button clicked by the user is the button text specified.

EXAMPLES

EXAMPLE 1

```
Show-InstallationPrompt -Message 'Do you want to proceed with the installation?'
-ButtonRightText 'Yes' -ButtonLeftText 'No'
```

EXAMPLE 2

```
Show-InstallationPrompt -Title 'Funny Prompt' -Message 'How are you feeling today?' -ButtonRightText 'Good' -ButtonLeftText 'Bad' -ButtonMiddleText 'Indifferent'
```

EXAMPLE 3

```
Show-InstallationPrompt -Message 'You can customize text to appear at the end of an install, or remove it completely for unattended installations.' -Icon Information -NoWait
```

PARAMETERS

-Title

Title of the prompt.

Default: the application installation name.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 1  
Default value: $installTitle  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Message

Message text to be included in the prompt

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 2  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-MessageAlignment

Alignment of the message text.

Options: Left, Center, Right.

Default: Center.

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: Center
Accept pipeline input: False
Accept wildcard characters: False

-ButtonRightText

Show a button on the right of the prompt with the specified text

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ButtonLeftText

Show a button on the left of the prompt with the specified text

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-ButtonMiddleText

Show a button in the middle of the prompt with the specified text

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Icon

Show a system icon in the prompt.

Options: Application, Asterisk, Error, Exclamation, Hand, Information, None, Question, Shield, Warning, WinLogo.

Default: None.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 7
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-NoWait

Specifies whether to show the prompt asynchronously (i.e. allow the script to continue without waiting for a response).

Default: \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-PersistPrompt

Specify whether to make the prompt persist in the center of the screen every couple of seconds, specified in the AppDeployToolkitConfig.xml.

The user will have no option but to respond to the prompt - resistance is futile!

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-MinimizeWindows

Specifies whether to minimize other windows when displaying prompt.

Default: \$false.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 8
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-Timeout

Specifies the time period in seconds after which the prompt should timeout.
Default: UI timeout value set in the config XML file.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 9
Default value: $configInstallationUITimeout
Accept pipeline input: False
Accept wildcard characters: False
```

-ExitOnTimeout

Specifies whether to exit the script if the UI times out.
Default: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 10
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Show-InstallationRestartPrompt

SYNOPSIS

Displays a restart prompt with a countdown to a forced restart.

SYNTAX

```
Show-InstallationRestartPrompt [[-CountdownSeconds] <Int32>] [[-CountdownNoHideSeconds] <Int32>]  
[[-NoSilentRestart] <Boolean>] [-NoCountdown] [[-silentCountdownSeconds] <Int32>] [<CommonParameters>]
```

DESCRIPTION

Displays a restart prompt with a countdown to a forced restart.

EXAMPLES

EXAMPLE 1

```
Show-InstallationRestartPrompt -Countdownseconds 600 -CountdownNoHideSeconds 60
```

EXAMPLE 2

```
Show-InstallationRestartPrompt -NoCountdown
```

EXAMPLE 3

```
Show-InstallationRestartPrompt -Countdownseconds 300 -NoSilentRestart $false -  
SilentCountdownSeconds 10
```

PARAMETERS

-CountdownSeconds

Specifies the number of seconds to countdown before the system restart.

Default: 60

Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: 60
Accept pipeline input: False
Accept wildcard characters: False

-CountdownNoHideSeconds

Specifies the number of seconds to display the restart prompt without allowing the window to be hidden.

Default: 30

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: 30
Accept pipeline input: False
Accept wildcard characters: False
```

-NoSilentRestart

Specifies whether the restart should be triggered when Deploy mode is silent or very silent.

Default: \$true

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-NoCountdown

Specifies not to show a countdown, just the Restart Now and Restart Later buttons.

The UI will restore/reposition itself persistently based on the interval value specified in the config file.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-SilentCountdownSeconds

Specifies number of seconds to countdown for the restart when the toolkit is running in silent mode and NoSilentRestart is \$false.

Default: 5

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: 5
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

Be mindful of the countdown you specify for the reboot as code directly after this function might NOT be able to execute - that includes logging.

RELATED LINKS

<http://psappdeploytoolkit.com>

Show-InstallationWelcome

SYNOPSIS

Show a welcome dialog prompting the user with information about the installation and actions to be performed before the installation can begin.

SYNTAX

None (Default)

```
Show-InstallationWelcome [-CloseApps <String>] [-silent] [-CloseAppsCountdown <Int32>]
[-ForceCloseAppsCountdown <Int32>] [-PromptToSave] [-PersistPrompt] [-BlockExecution] [-AllowDefer]
[-AllowDeferCloseApps] [-DeferTimes <Int32>] [-DeferDays <Int32>] [-DeferDeadline <String>]
[-Minimizewindows <Boolean>] [-TopMost <Boolean>] [-ForceCountdown <Int32>] [-CustomText] [<CommonParameters>]
```

CheckDiskSpaceParameterSet

```
Show-Installationwelcome [-CloseApps <String>] [-silent] [-CloseAppsCountdown <Int32>]
[-ForceCloseAppsCountdown <Int32>] [-PromptToSave] [-PersistPrompt] [-BlockExecution] [-AllowDefer]
[-AllowDeferCloseApps] [-DeferTimes <Int32>] [-DeferDays <Int32>] [-DeferDeadline <String>] [-CheckDiskSpace]
[-RequiredDiskSpace <Int32>] [-MinimizeWindows <Boolean>] [-TopMost <Boolean>]
[-ForceCountdown <Int32>]
[-CustomText] [<CommonParameters>]
```

DESCRIPTION

The following prompts can be included in the welcome dialog:

- a) Close the specified running applications, or optionally close the applications without showing a prompt (using the -Silent switch).
- b) Defer the installation a certain number of times, for a certain number of days or until a deadline is reached.
- c) Countdown until applications are automatically closed.
- d) Prevent users from launching the specified applications while the installation is in progress.

Notes:

The process descriptions are retrieved from WMI, with a fall back on the process name if no description is available.

Alternatively, you can specify the description yourself with a '=' symbol - see examples.

The dialog box will timeout after the timeout specified in the XML configuration file (default 1 hour and 55 minutes) to prevent SCCM installations from timing out and returning a failure code to SCCM.

When the dialog times out, the script will exit and return a 1618 code (SCCM fast retry code).

EXAMPLES

EXAMPLE 1

```
Show-Installationwelcome -CloseApps 'iexplore,winword,excel'
```

Prompt the user to close Internet Explorer, Word and Excel.

EXAMPLE 2

```
Show-Installationwelcome -CloseApps 'winword,excel' -silent
```

Close Word and Excel without prompting the user.

EXAMPLE 3

```
Show-Installationwelcome -CloseApps 'winword,excel' -BlockExecution
```

Close Word and Excel and prevent the user from launching the applications while the installation is in progress.

EXAMPLE 4

```
Show-InstallationWelcome -CloseApps 'winword=Microsoft Office Word,excel=Microsoft Office Excel' -CloseAppsCountdown 600
```

Prompt the user to close Word and Excel, with customized descriptions for the applications and automatically close the applications after 10 minutes.

EXAMPLE 5

```
Show-InstallationWelcome -CloseApps 'winword,msaccess,excel' -PersistPrompt
```

Prompt the user to close Word, MSAccess and Excel.

By using the PersistPrompt switch, the dialog will return to the center of the screen every couple of seconds, specified in the AppDeployToolkitConfig.xml, so the user cannot ignore it by dragging it aside.

EXAMPLE 6

```
Show-InstallationWelcome -AllowDefer -DeferDeadline '25/08/2013'
```

Allow the user to defer the installation until the deadline is reached.

EXAMPLE 7

```
Show-InstallationWelcome -CloseApps 'winword,excel' -BlockExecution -AllowDefer -DeferTimes 10 -DeferDeadline '25/08/2013' -CloseAppsCountdown 600
```

Close Word and Excel and prevent the user from launching the applications while the installation is in progress.

Allow the user to defer the installation a maximum of 10 times or until the deadline is reached, whichever happens first.

When deferral expires, prompt the user to close the applications and automatically close them after 10 minutes.

PARAMETERS

-CloseApps

Name of the process to stop (do not include the .exe).

Specify multiple processes separated by a comma.

Specify custom descriptions like this: "winword=Microsoft Office Word,excel=Microsoft Office Excel"

Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

-Silent

Stop processes without prompting the user.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-CloseAppsCountdown

Option to provide a countdown in seconds until the specified applications are automatically closed.

This only takes effect if deferral is not allowed or has expired.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

-ForceCloseAppsCountdown

Option to provide a countdown in seconds until the specified applications are automatically closed regardless of whether deferral is allowed.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

-PromptToSave

Specify whether to prompt to save working documents when the user chooses to close applications by selecting the "Close Programs" button.

Option does not work in SYSTEM context unless toolkit launched with "psexec.exe -s -i" to run it as an interactive process under the SYSTEM account.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-PersistPrompt

Specify whether to make the prompt persist in the center of the screen every couple of seconds, specified in the AppDeployToolkitConfig.xml.

The user will have no option but to respond to the prompt.

This only takes effect if deferral is not allowed or has expired.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-BlockExecution

Option to prevent the user from launching the process/application during the installation.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-AllowDefer

Enables an optional defer button to allow the user to defer the installation.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-AllowDeferCloseApps

Enables an optional defer button to allow the user to defer the installation only if there are running applications that need to be closed.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-DeferTimes

Specify the number of times the installation can be deferred.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

-DeferDays

Specify the number of days since first run that the installation can be deferred.

This is converted to a deadline.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

-DeferDeadline

Specify the deadline date until which the installation can be deferred.

Specify the date in the local culture if the script is intended for that same culture.

If the script is intended to run on EN-US machines, specify the date in the format: "08/25/2013" or "08-25-2013" or "08-25-2013 18:00:00"

If the script is intended for multiple cultures, specify the date in the universal sortable date/time format: "2013-08-22 11:51:52Z"

The deadline date will be displayed to the user in the format of their culture.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-CheckDiskSpace

Specify whether to check if there is enough disk space for the installation to proceed. If this parameter is specified without the RequiredDiskSpace parameter, the required disk space is calculated automatically based on the size of the script source and associated files.

```
Type: SwitchParameter
Parameter Sets: CheckDiskSpaceParameterSet
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-RequiredDiskSpace

Specify required disk space in MB, used in combination with CheckDiskSpace.

```
Type: Int32
Parameter Sets: CheckDiskSpaceParameterSet
Aliases:

Required: False
Position: Named
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

-MinimizeWindows

Specifies whether to minimize other windows when displaying prompt.
Default: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-TopMost

Specifies whether the windows is the topmost window.

Default: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-ForceCountdown

Specify a countdown to display before automatically proceeding with the installation when a deferral is enabled.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

-CustomText

Specify whether to display a custom message specified in the XML file.

Custom message must be populated for each language section in the XML.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Show-WelcomePrompt

SYNOPSIS

Called by Show-InstallationWelcome to prompt the user to optionally do the following:

- 1) Close the specified running applications.
- 2) Provide an option to defer the installation.
- 3) Show a countdown before applications are automatically closed.

SYNTAX

```
Show-WelcomePrompt [[-ProcessDescriptions] <String>] [[-CloseAppsCountdown]
<Int32>]
[[[-ForceCloseAppsCountdown] <Boolean>] [[-PersistPrompt] <Boolean>] [-
AllowDefer] [[-DeferTimes] <String>]
[[[-DeferDeadline] <String>] [[-MinimizeWindows] <Boolean>] [[-TopMost]
<Boolean>] [[-ForceCountdown] <Int32>]
[-CustomText] [<CommonParameters>]
```

DESCRIPTION

The user is presented with a Windows Forms dialog box to close the applications themselves and continue or to have the script close the applications for them.

If the -AllowDefer option is set to true, an optional "Defer" button will be shown to the user.

If they select this option, the script will exit and return a 1618 code (SCCM fast retry code).

The dialog box will timeout after the timeout specified in the XML configuration file (default 1 hour and 55 minutes) to prevent SCCM installations from timing out and returning a failure code to SCCM.

When the dialog times out, the script will exit and return a 1618 code (SCCM fast retry code).

EXAMPLES

EXAMPLE 1

```
Show-WelcomePrompt -ProcessDescriptions 'Lotus Notes, Microsoft Word' -
CloseAppsCountdown 600 -AllowDefer -DeferTimes 10
```

PARAMETERS

-ProcessDescriptions

The descriptive names of the applications that are running and need to be closed.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-CloseAppsCountdown

Specify the countdown time in seconds before running applications are automatically closed when deferral is not allowed or expired.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

-ForceCloseAppsCountdown

Specify whether to show the countdown regardless of whether deferral is allowed.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-PersistPrompt

Specify whether to make the prompt persist in the center of the screen every couple of seconds, specified in the AppDeployToolkitConfig.xml.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-AllowDefer

Specify whether to provide an option to defer the installation.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-DeferTimes

Specify the number of times the user is allowed to defer.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-DeferDeadline

Specify the deadline date before the user is allowed to defer.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-MinimizeWindows

Specifies whether to minimize other windows when displaying prompt.

Default: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 7
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-TopMost

Specifies whether the windows is the topmost window.

Default: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 8
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-ForceCountdown

Specify a countdown to display before automatically proceeding with the installation when a deferral is enabled.

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 9
Default value: 0
Accept pipeline input: False
Accept wildcard characters: False
```

-CustomText

Specify whether to display a custom message specified in the XML file.

Custom message must be populated for each language section in the XML.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.
It is used by the Show-InstallationWelcome prompt to display a custom prompt.

RELATED LINKS

<http://psappdeploytoolkit.com>

Start-ServiceAndDependencies

SYNOPSIS

Start Windows service and its dependencies.

SYNTAX

```
Start-ServiceAndDependencies [-Name] <String> [[-ComputerName] <String>] [-SkipServiceExistsTest]
[-SkipDependentServices] [[-PendingStatusWait] <TimeSpan>] [-PassThru] [[-ContinueOnError] <Boolean>]
[<CommonParameters>]
```

DESCRIPTION

Start Windows service and its dependencies.

EXAMPLES

EXAMPLE 1

```
Start-ServiceAndDependencies -Name 'wuauserv'
```

PARAMETERS

-Name

Specify the name of the service.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ComputerName

Specify the name of the computer.

Default is: the local computer.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: $env:ComputerName
Accept pipeline input: False
Accept wildcard characters: False
```

-SkipServiceExistsTest

Choose to skip the test to check whether or not the service exists if it was already done outside of this function.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-SkipDependentServices

Choose to skip checking for and starting dependent services.

Default is: \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-PendingStatusWait

The amount of time to wait for a service to get out of a pending state before continuing.
Default is 60 seconds.

```
Type: TimeSpan
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: (New-TimeSpan -Seconds 60)
Accept pipeline input: False
Accept wildcard characters: False
```

-PassThru

Return the System.ServiceProcess.ServiceController service object.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Stop-ServiceAndDependencies

SYNOPSIS

Stop Windows service and its dependencies.

SYNTAX

```
Stop-ServiceAndDependencies [-Name] <String> [[-ComputerName] <String>] [-SkipServiceExistsTest] [-SkipDependentServices] [[-PendingStatusWait] <TimeSpan>] [-PassThru] [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Stop Windows service and its dependencies.

EXAMPLES

EXAMPLE 1

```
Stop-ServiceAndDependencies -Name 'wuauserv'
```

PARAMETERS

-Name

Specify the name of the service.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-ComputerName

Specify the name of the computer.

Default is: the local computer.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: $env:ComputerName
Accept pipeline input: False
Accept wildcard characters: False
```

-SkipServiceExistsTest

Choose to skip the test to check whether or not the service exists if it was already done outside of this function.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-SkipDependentServices

Choose to skip checking for and stopping dependent services.

Default is: \$false.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-PendingStatusWait

The amount of time to wait for a service to get out of a pending state before continuing.

Default is 60 seconds.

Type: TimeSpan
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: (New-TimeSpan -Seconds 60)
Accept pipeline input: False
Accept wildcard characters: False

-PassThru

Return the System.ServiceProcess.ServiceController service object.

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: True
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Test-Battery

SYNOPSIS

Tests whether the local machine is running on AC power or not.

SYNTAX

```
Test-Battery [-PassThru] [<CommonParameters>]
```

DESCRIPTION

Tests whether the local machine is running on AC power and returns true/false.
For detailed information, use -PassThru option.

EXAMPLES

EXAMPLE 1

```
Test-Battery
```

EXAMPLE 2

```
(Test-Battery -PassThru).IsLaptop
```

Determines if the current system is a laptop or not.

PARAMETERS

-PassThru

Outputs a hashtable containing the following properties:
IsLaptop, IsUsingACPower, ACPowerLineStatus, BatteryChargeStatus, BatteryLifePercent,
BatteryLifeRemaining, BatteryFullLifetime

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Test-IsMutexAvailable

SYNOPSIS

Wait, up to a timeout value, to check if current thread is able to acquire an exclusive lock on a system mutex.

SYNTAX

```
Test-IsMutexAvailable [-MutexName] <String> [[-MutexWaitTimeInMilliseconds]
<Int32>] [<CommonParameters>]
```

DESCRIPTION

A mutex can be used to serialize applications and prevent multiple instances from being opened at the same time.

Wait, up to a timeout (default is 1 millisecond), for the mutex to become available for an exclusive lock.

EXAMPLES

EXAMPLE 1

```
Test-IsMutexAvailable -MutexName 'Global\_\_MSIExecute' -
MutexWaitTimeInMilliseconds 500
```

EXAMPLE 2

```
Test-IsMutexAvailable -MutexName 'Global\_\_MSIExecute' -
MutexWaitTimeInMilliseconds (New-Timespan -Minutes 5).TotalMilliseconds
```

EXAMPLE 3

```
Test-IsMutexAvailable -MutexName 'Global\_\_MSIExecute' -
MutexWaitTimeInMilliseconds (New-Timespan -Seconds 60).TotalMilliseconds
```

PARAMETERS

-MutexName

The name of the system mutex.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-MutexWaitTimeInMilliseconds

The Wait Time in Milliseconds

```
Type: Int32
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: 1
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

[http://msdn.microsoft.com/en-us/library/aa372909\(VS.85\).asp](http://msdn.microsoft.com/en-us/library/aa372909(VS.85).asp)
<http://psappdeploytoolkit.com>

Test-MSUpdates

SYNOPSIS

Test whether a Microsoft Windows update is installed.

SYNTAX

```
Test-MSUpdates [-KBNumber] <String> [[-ContinueOnError] <Boolean>]  
[<CommonParameters>]
```

DESCRIPTION

Test whether a Microsoft Windows update is installed.

EXAMPLES

EXAMPLE 1

```
Test-MSUpdates -KBNumber 'KB2549864'
```

PARAMETERS

-KBNumber

KBNumber of the update.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-ContinueOnError

Suppress writing log message to console on failure to write message to log file.

Default is: \$true.

```
Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 2  
Default value: True  
Accept pipeline input: False  
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Test-NetworkConnection

SYNOPSIS

Tests for an active local network connection, excluding wireless and virtual network adapters.

SYNTAX

```
Test-NetworkConnection [<CommonParameters>]
```

DESCRIPTION

Tests for an active local network connection, excluding wireless and virtual network adapters, by querying the Win32_NetworkAdapter WMI class.

EXAMPLES

EXAMPLE 1

```
Test-NetworkConnection
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Test-PowerPoint

SYNOPSIS

Tests whether PowerPoint is running in either fullscreen slideshow mode or presentation mode.

SYNTAX

```
Test-PowerPoint [<CommonParameters>]
```

DESCRIPTION

Tests whether someone is presenting using PowerPoint in either fullscreen slideshow mode or presentation mode.

EXAMPLES

EXAMPLE 1

```
Test-PowerPoint
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This function can only execute detection logic if the process is in interactive mode.

There is a possibility of a false positive if the PowerPoint filename starts with "PowerPoint Slide Show".

RELATED LINKS

<http://psappdeploytoolkit.com>

Test-RegistryValue

SYNOPSIS

Test if a registry value exists.

SYNTAX

```
Test-RegistryValue [-Key] <Object> [-Value] <Object> [[-SID] <String>]  
[<CommonParameters>]
```

DESCRIPTION

Checks a registry key path to see if it has a value with a given name.

Can correctly handle cases where a value simply has an empty or null value.

EXAMPLES

EXAMPLE 1

```
Test-RegistryValue -Key 'HKLM:SYSTEM\CurrentControlSet\Control\Session Manager'  
-Value 'PendingFileRenameOperations'
```

PARAMETERS

-Key

Path of the registry key.

```
Type: Object  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False
```

-Value

Specify the registry key value to check the existence of.

```
Type: Object  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: 2  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-SID

The security identifier (SID) for a user.

Specifying this parameter will convert a HKEY_CURRENT_USER registry key to the HKEY_USERS\$SID format.

Specify this parameter from the Invoke-HKCURegistrySettingsForAllUsers function to read/edit HKCU registry settings for all users on the system.

Type: String

Parameter Sets: (A11)

Aliases:

Required: False

Position: 3

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

To test if registry key exists, use Test-Path function like so:

```
Test-Path -Path $Key -PathType 'Container'
```

RELATED LINKS

<http://psappdeploytoolkit.com>

Test-ServiceExists

SYNOPSIS

Check to see if a service exists.

SYNTAX

```
Test-ServiceExists [-Name] <String> [[-ComputerName] <String>] [-PassThru] [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Check to see if a service exists (using WMI method because Get-Service will generate ErrorRecord if service doesn't exist).

EXAMPLES

EXAMPLE 1

```
Test-ServiceExists -Name 'wuauserv'
```

EXAMPLE 2

```
Test-ServiceExists -Name 'testservice' -PassThru | Where-Object { ---
```

```
external help file: AppDeployToolkitMain-help.xml
Module Name: AppDeployToolkitMain
online version: http://psappdeploytoolkit.com
schema: 2.0.0
```

```
---
```

```
### Test-ServiceExists
```

```
#### SYNOPSIS
```

Check to see if a service exists.

```
#### SYNTAX
```

```
Test-ServiceExists [-Name] [[-ComputerName] ] [-PassThru] [[-ContinueOnError] ]
```

```
[]
```

```
#### DESCRIPTION
```

Check to see if a service exists (using WMI method because **Get-Service** will generate ErrorRecord if service doesn't exist).

```
#### EXAMPLES
```

```
##### EXAMPLE 1
```

```
Test-ServiceExists -Name 'wuauserv'
```

```
##### EXAMPLE 2
```

```
Test-ServiceExists -Name 'testservice' -PassThru | Where-Object { $_ } | ForEach-Object {
$__.Delete() }
```

```
Check if a service exists and then delete it by using the -PassThru parameter.
```

```
#### PARAMETERS
```

```
##### -Name
```

Specify the name of the service.
Note: Service name can be found by executing "Get-Service | Format-Table -AutoSize -Wrap" or by using the properties screen of a service in services.msc.

```
```yaml
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

### **-ComputerName**

Specify the name of the computer.  
Default is: the local computer.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: $env:ComputerName
Accept pipeline input: False
Accept wildcard characters: False
```

### **-PassThru**

Return the WMI service object.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

### **-ContinueOnError**

Continue if an error is encountered.  
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
```

```

Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```powershell

##### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](http://go.microsoft.com/fwlink/?LinkID=113216).

#### INPUTS

#### OUTPUTS

#### NOTES

#### RELATED LINKS

[http://psappdeploytoolkit.com](http://psappdeploytoolkit.com) } | ForEach-Object { ---


external help file: AppDeployToolkitMain-help.xml
Module Name: AppDeployToolkitMain
online version: http://psappdeploytoolkit.com
schema: 2.0.0
---


### Test-ServiceExists

#### SYNOPSIS

Check to see if a service exists.

#### SYNTAX
```

Test-ServiceExists [-Name] [[-ComputerName]] [-PassThru] [[-ContinueOnError]]
[]

```

#### DESCRIPTION

Check to see if a service exists (using WMI method because Get-Service will generate ErrorRecord if service doesn't exist).

#### EXAMPLES

##### EXAMPLE 1
```

Test-ServiceExists -Name 'wuauserv'

EXAMPLE 2

```
Test-ServiceExists -Name 'testservice' -PassThru | Where-Object { $_ } | ForEach-Object {  
    $_.Delete()  
}
```

Check if a service exists and then delete it by using the `-PassThru` parameter.

PARAMETERS

-Name

Specify the name of the service.

Note: Service name can be found by executing "Get-Service | Format-Table -AutoSize -Wrap" or by using the properties screen of a service in services.msc.

```
```yaml  
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

### **-ComputerName**

Specify the name of the computer.

Default is: the local computer.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: $env:ComputerName
Accept pipeline input: False
Accept wildcard characters: False
```

### **-PassThru**

Return the WMI service object.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## -ContinueOnError

Continue if an error is encountered.  
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```powershell
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](<http://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>.Delete() }

Check if a service exists and then delete it by using the -PassThru parameter.

PARAMETERS

-Name

Specify the name of the service.

Note: Service name can be found by executing "Get-Service | Format-Table -AutoSize -Wrap" or by using the properties screen of a service in services.msc.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

-ComputerName

Specify the name of the computer.

Default is: the local computer.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 2
Default value: $env:ComputerName
Accept pipeline input: False
Accept wildcard characters: False
```

-PassThru

Return the WMI service object.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Unblock-AppExecution

SYNOPSIS

Unblocks the execution of applications performed by the Block-AppExecution function

SYNTAX

```
unblock-AppExecution [<CommonParameters>]
```

DESCRIPTION

This function is called by the Exit-Script function or when the script itself is called with the parameters -CleanupBlockedApps

EXAMPLES

EXAMPLE 1

```
unblock-AppExecution
```

PARAMETERS

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly. It is used when the -BlockExecution parameter is specified with the Show-InstallationWelcome function to undo the actions performed by Block-AppExecution.

RELATED LINKS

<http://psappdeploytoolkit.com>

Update-Desktop

SYNOPSIS

Refresh the Windows Explorer Shell, which causes the desktop icons and the environment variables to be reloaded.

SYNTAX

```
update-Desktop [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Refresh the Windows Explorer Shell, which causes the desktop icons and the environment variables to be reloaded.

EXAMPLES

EXAMPLE 1

```
update-Desktop
```

PARAMETERS

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Update-GroupPolicy

SYNOPSIS

Performs a gpupdate command to refresh Group Policies on the local machine.

SYNTAX

```
Update-GroupPolicy [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Performs a gpupdate command to refresh Group Policies on the local machine.

EXAMPLES

EXAMPLE 1

```
Update-GroupPolicy
```

PARAMETERS

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 1  
Default value: True  
Accept pipeline input: False  
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Update-SessionEnvironmentVariables

SYNOPSIS

Updates the environment variables for the current PowerShell session with any environment variable changes that may have occurred during script execution.

SYNTAX

```
update-SessionEnvironmentVariables [-LoadLoggedOnUserEnvironmentVariables] [[-ContinueOnError] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Environment variable changes that take place during script execution are not visible to the current PowerShell session.

Use this function to refresh the current PowerShell session with all environment variable settings.

EXAMPLES

EXAMPLE 1

```
Update-SessionEnvironmentVariables
```

PARAMETERS

-LoadLoggedOnUserEnvironmentVariables

If script is running in SYSTEM context, this option allows loading environment variables from the active console user.

If no console user exists but users are logged in, such as on terminal servers, then the first logged-in non-console user.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Continue if an error is encountered.

Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 1
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>

Write-FunctionHeaderOrFooter

SYNOPSIS

Write the function header or footer to the log upon first entering or exiting a function.

SYNTAX

Header

```
Write-FunctionHeaderOrFooter -CmdletName <String> -CmdletBoundParameters
<Hashtable> [-Header]
[<CommonParameters>]
```

Footer

```
Write-FunctionHeaderOrFooter -CmdletName <String> [-Footer] [<CommonParameters>]
```

DESCRIPTION

Write the "Function Start" message, the bound parameters the function was invoked with, or the "Function End" message when entering or exiting a function.

Messages are debug messages so will only be logged if LogDebugMessage option is enabled in XML config file.

EXAMPLES

EXAMPLE 1

```
Write-FunctionHeaderOrFooter -CmdletName ${CmdletName} -CmdletBoundParameters  
$PSBoundParameters -Header
```

EXAMPLE 2

```
Write-FunctionHeaderOrFooter -CmdletName ${CmdletName} -Footer
```

PARAMETERS

-CmdletName

The name of the function this function is invoked from.

```
Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-CmdletBoundParameters

The bound parameters of the function this function is invoked from.

```
Type: Hashtable  
Parameter Sets: Header  
Aliases:  
  
Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Header

Write the function header.

```
Type: SwitchParameter  
Parameter Sets: Header  
Aliases:  
  
Required: True  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Footer

Write the function footer.

```
Type: SwitchParameter
Parameter Sets: Footer
Aliases:

Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

This is an internal script function and should typically not be called directly.

RELATED LINKS

<http://psappdeploytoolkit.com>

Write-Log

SYNOPSIS

Write messages to a log file in CMTrace.exe compatible format or Legacy text file format.

SYNTAX

```
Write-Log [-Message] <String[]> [[-Severity] <Int16>] [[-Source] <String>] [[-ScriptSection] <String>]
[[-LogType] <String>] [[-LogFileDirectory] <String>] [[-LogFileName] <String>]
[[-MaxLogFileSizeMB] <Decimal>]
[[-writeHost] <Boolean>] [[-ContinueOnError] <Boolean>] [-PassThru] [-DebugMessage]
[[-LogDebugMessage] <Boolean>] [<CommonParameters>]
```

DESCRIPTION

Write messages to a log file in CMTrace.exe compatible format or Legacy text file format and optionally display in the console.

EXAMPLES

EXAMPLE 1

```
Write-Log -Message "Installing patch MS15-031" -Source 'Add-Patch' -LogType  
'CMTrace'
```

EXAMPLE 2

```
Write-Log -Message "Script is running on windows 8" -Source 'Test-Validos' -  
LogType 'Legacy'
```

PARAMETERS

-Message

The message to write to the log file or output to the console.

```
Type: String[]  
Parameter Sets: (All)  
Aliases: Text  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False
```

-Severity

Defines message type.

When writing to console or CMTrace.exe log format, it allows highlighting of message type.

Options: 1 = Information (default), 2 = Warning (highlighted in yellow), 3 = Error (highlighted in red)

```
Type: Int16  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 2  
Default value: 1  
Accept pipeline input: False  
Accept wildcard characters: False
```

-Source

The source of the message being logged.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 3
Default value: $([string]$parentFunctionName =
[IO.Path]::GetFileNameWithoutExtension((Get-Variable -Name MyInvocation -Scope 1
-ErrorAction SilentlyContinue).Value.MyCommand.Name); If($parentFunctionName)
{$parentFunctionName} Else {'Unknown'})
Accept pipeline input: False
Accept wildcard characters: False
```

-ScriptSection

The heading for the portion of the script that is being executed.
Default is: \$script:installPhase.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 4
Default value: $script:installPhase
Accept pipeline input: False
Accept wildcard characters: False
```

-LogType

Choose whether to write a CMTrace.exe compatible log file or a Legacy text log file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 5
Default value: $configToolkitLogStyle
Accept pipeline input: False
Accept wildcard characters: False
```

-LogFileDirectory

Set the directory where the log file will be saved.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 6
Default value: $(If ($configToolkitCompressLogs) { $logTempFolder } Else {
$configToolkitLogDir })
Accept pipeline input: False
Accept wildcard characters: False
```

-LogFileName

Set the name of the log file.

```
Type: String
Parameter Sets: (All)
Aliases:

Required: False
Position: 7
Default value: $logName
Accept pipeline input: False
Accept wildcard characters: False
```

-MaxLogFileSizeMB

Maximum file size limit for log file in megabytes (MB).

Default is 10 MB.

```
Type: Decimal
Parameter Sets: (All)
Aliases:

Required: False
Position: 8
Default value: $configToolkitLogMaxSize
Accept pipeline input: False
Accept wildcard characters: False
```

-WriteHost

Write the log message to the console.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 9
Default value: $configToolkitLogWriteToHost
Accept pipeline input: False
Accept wildcard characters: False
```

-ContinueOnError

Suppress writing log message to console on failure to write message to log file.
Default is: \$true.

```
Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 10
Default value: True
Accept pipeline input: False
Accept wildcard characters: False
```

-PassThru

Return the message that was passed to the function

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 11
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-DebugMessage

Specifies that the message is a debug message.
Debug messages only get logged if -LogDebugMessage is set to \$true.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: 12
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

-LogDebugMessage

Debug messages only get logged if this parameter is set to \$true in the config XML file.

Type: Boolean
Parameter Sets: (All)
Aliases:

Required: False
Position: 13
Default value: \$configToolkitLogDebugMessage
Accept pipeline input: False
Accept wildcard characters: False

CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about_CommonParameters](#).

INPUTS

OUTPUTS

NOTES

RELATED LINKS

<http://psappdeploytoolkit.com>
