

What is a modified mat nursery


A modified mat nursery establishes seedlings in a layer of soil mix, arranged on a firm surface. Seedlings are ready for planting within 15-20 days after seeding (DAS).

Why use a modified mat nursery

The modified mat nursery uses less land, can be installed closer to the house than traditional field nurseries, and uses less labor for both transporting seedling mats and replanting. As a result, root damage is minimal while separating seedlings.

How to establish a modified mat nursery

- 1. Seed: To plant 1 ha (with 2 seedlings/hill at 20 X 20 cm spacing), use 40-60 kg good quality seeds (i.e., >80% germination and establishment). Note: Good seeds result in lower seed rate, more uniform germination, vigorous seedlings, less replanting, fewer weeds, and 5-20% higher yields.
- **2. Nursery area:** Prepare 100 m² nursery for each 1 ha to be planted. Select a level area near the house and/or a water source. If area is not sufficiently compacted, then spread a plastic sheet or banana leaves on the marked area to prevent roots growing into soil.
- 3. Soil mixture: Four (4) m3 of soil mix is needed for each 100 m2 of nursery. Mix 70-80% soil + 15-20% well-decomposed organic manure + 5-10% rice hull or rice hull ash. Incorporate around 20 kg N/ha (1.5 kg powdered diammonium phosphate or 2.0 kg 15-15-15 powdered NPK fertilizer for every 100 m² of nursery area).



- 5. Laying the soil mixture: Place a wooden/iron frame of 0.5 m long, 1 m wide and 4-cm deep divided into 4 equal segments on the plastic sheet or banana leaves. Fill the frame almost to the top with the soil mixture.
- 6. Sowing: Sow the pre-germinated seeds uniformly and cover them with a thin layer of dry soil. (Approximately 1 seed/cm²)
- 7.Soaking the seedbed: (a) Sprinkle water immediately to soak the bed. (b) Remove the wooden frame and continue the process (i.e., fill soil mix-sow seed-cover seed-water) until the required nursery area is completed.
- 8.Watering: Water the nursery as needed to keep the soil moist. Protect the nursery from heavy rains for the first 5 DAS. If the nursery can be flooded then at 7 DAS, maintain a 1-cm water level around the mats. Drain the water 2 days before removing the seedling mats for transplanting. Prepare a 5cm depth channel all around the bed, irrigate through the channel to keep the bed moist.
- **9.Fertilizer topdressing (optional):** If temperature is favorable and water are adequate, but the seedlings show yellowing (N deficiency). Sprinkle seedlings with 0.5% urea (1.5 kg Urea in 300 l water/ $100m^2$).
- Lifting seedling mats: Seedlings reach sufficient height for planting in 15-20 DAS. Lift the seedling mats and transport them to main field.

























