### **Querying Container Data Objects**

**By Ahmed Baraka** 

#### **Objectives**

In this lecture, you will learn how to perform the following:

- Understand querying container data objects
- Set CONTAINER\_DATA attributes for a common user
- Obtain information about CONTAINER\_DATA attributes set in a multitenant environment
- Remove CONTAINER\_DATA attributes for a user

### What are Container Data Objects?

- Tables or views containing data pertaining to multiple containers
- Examples: V\$, CDB \*, and DBA HIST\* views
- The have a CON ID column:

CON_ID	The Container the Rows Pertain to
0	Whole CDB
1	The root container (CDB\$ROOT)
2	The seed container (PDB\$SEED)
All other IDS	User-created PDBs, application roots, or application seeds

To identify container data objects:

```
SELECT VIEW_NAME FROM CDB_VIEWS WHERE CONTAINER_DATA = 'Y';
SELECT TABLE_NAME FROM CDB_TABLES WHERE CONTAINER_DATA = 'YES';
```

# **Querying Container Data Objects: Default Behavior and Modifying It**

- By default, common users created by the DBA can retrieve rows related to the current container. To view rows of another container, the user must connect to it
- To allow a common user to see the rows of all the PDBs:

```
ALTER USER c##user1 SET CONTAINER_DATA=ALL CONTAINER=CURRENT;
```

To revert it back to the default behavior:

```
ALTER USER c##user1 SET CONTAINER_DATA=DEFAULT CONTAINER=CURRENT;
```

- To allow a common user to see rows of only specific PDBs:
  - The root must always be included

```
ALTER USER c##user1 SET CONTAINER_DATA=(CDB$ROOT,PDB1)
CONTAINER=CURRENT;
```

# Adding and Removing Specific Container from the CONTAINER\_DATA Attributes

• To add specific PDBs to the **CONTAINER DATA** attributes of a user:

```
ALTER USER c##user1 ADD CONTAINER DATA=(PDB3) CONTAINER=CURRENT;
```

 To remove specific PDBs from the CONTAINER\_DATA attributes of a user:

```
ALTER USER c##user1 REMOVE CONTAINER_DATA=(PDB3) CONTAINER=CURRENT;
```

Setting the attributes overwrites the existing ones:

```
ALTER USER c##user1 SET CONTAINER_DATA=(CDB$ROOT, PDB1, PDB2)
CONTAINER=CURRENT;
```

### Setting CONTAINER\_DATA Attributes for Specific Objects

To set CONTAINER\_DATA attributes for specific objects, use the FOR clause:

### To Obtain Information about the CONTAINER\_DATA Attributes Set in a Multitenant Environment

#### Removing CONTAINER\_DATA Attributes for a User

To remove all PDB-level CONTAINER DATA attributes:

```
ALTER USER c##user2 SET CONTAINER_DATA=DEFAULT CONTAINER=CURRENT;
```

- It does not remove the attributes at the object-level
- To remove object-level CONTAINER DATA attributes:

```
ALTER USER c##user2 SET CONTAINER_DATA=DEFAULT FOR V_$SESSION CONTAINER=CURRENT;
```

#### **Summary**

In this lecture, you should have learnt how to perform the following:

- Understand querying container data objects
- Set CONTAINER\_DATA attributes for a common user
- Obtain information about CONTAINER\_DATA attributes set in a multitenant environment
- Remove CONTAINER\_DATA attributes for a user