Creating PDBs More Options

Part III

By Ahmed Baraka

Objectives


By the end of this lecture, you should be able to:

- Relocate a PDB
- Create a proxy PDB
- Create a refreshable PDB

Options for Creating a PDB using CREATE PLUGGABLE DATABASE command

Category	Option	Description
Copying	From the seed	By using the files of the CDB seed or application seed.
	Clone a local PDB	By cloning a source local PDB.
	Clone a remote PDB	By cloning a remote PDB.
	Clone a non-CDB	By cloning a non-CDB.
Plugging In	Plugging in an Unplugged PDB	By plugging in an unplugged PDB
	Adopting a Non-CDB as a PDB (Using the DBMS_PDB)	By creating an unplugged PDB from a non-CDB and then plug the unplugged PDB into the CDB.
Relocating	Relocating a PDB	By moving the files associated with the PDB to a new location.
Proxy PDB	Creating a PDB as a proxy PDB	By referencing a different PDB with a database link

About Relocating a PDB




Relocating a PDB Procedure

- 1. Connect to the root as a common user (SYSOPER)
- 2. Create the database link to the source pdb
- 3. Relocate the PDB. The name of the target pdb must be the same as the name of the source pdb.

```
CREATE PLUGGABLE DATABASE pdb4 FROM pdb4@sourcedb FILE_NAME_CONVERT=('..','..') RELOCATE [AVAILABILITY MAX];
```

4. Open the PDB in read/write mode

About Creating a Proxy PDB



Creating a Proxy PDB Procedure

- 1. Connect to the root as a common user
- 2. Create the database link to the source root or pdb
- 3. Create the Proxy PDB


CREATE PLUGGABLE DATABASE pdb4 AS PROXY FROM srcpdb@sourcedb;

4. Open the PDB in read/write mode


Options for Creating a PDB using CREATE PLUGGABLE DATABASE command

Category	Option	Description
Copying	From the seed	By using the files of the CDB seed or application seed.
	Clone a local PDB	By cloning a source local PDB.
	Clone a remote PDB	By cloning a remote PDB. [refresh mode supported in 12.2]
	Clone a non-CDB	By cloning a non-CDB.
Plugging In	Plugging in an Unplugged PDB	By plugging in an unplugged PDB
	Adopting a Non-CDB as a PDB (Using the DBMS_PDB)	By creating an unplugged PDB from a non-CDB and then plug the unplugged PDB into the CDB.
Relocating	Relocating a PDB	By moving the files associated with the PDB to a new location.
Proxy PDB	Creating a PDB as a proxy PDB	By referencing a different PDB with a database link


Creating a Refreshable PDB




Refreshing a PDB



Refreshing a PDB



Refreshing a PDB



About Refreshable PDB Clones

- Supported only in a CREATE PLUGGABLE DATABASE .. FROM
- Target and source PDBs must be in separate CDBs
- REFRESH MODE options:
 - MANUAL
 - EVERY n MINUTES
 - NONE
- Can be opened only in READ ONLY mode
- Must be closed before refreshing
- New data files added to the source will also get synched

Creating a Refreshable PDB Procedure

- 1. Connect to the root as a common user
- 2. Create the database link to the source root or pdb
- 3. Create the refreshable PDB

CREATE PLUGGABLE DATABASE pdb_rpt FROM pdb_prod@prod_link REFRESH MODE MANUAL;

CREATE PLUGGABLE DATABASE pdb_rpt FROM pdb_prod@prod_link REFRESH MODE EVERY 60 MINUTES;

4. Open the PDB in Read Only mode

Summary

In this lecture, you should have learnt the following:

- Relocate a PDB
- Create a proxy PDB
- Create a refreshable PDB