Actalis Adaptable CA Driver configuration guide

1 Introduction

This document explains how to configure the Actalis Adaptable CA Driver, so to be able to request and manage Actalis certificates from the Venafi TPP Platform. This document assumes that the reader already has a basic understanding of what an "Adaptable CA Driver" is and how it is used. The reader is referred to the Venafi TPP platform's documentation for full details.

2 Configuration

To make the Actalis Adaptable CA Driver available to the Venafi TPP platform, first of all you have to copy the script file **Actalis_Adaptable_Script.ps1** to the **\Venafi\Scripts\AdaptableCA** folder of the Venafi TPP server.

Once the script is uploaded to the target folder, follow the instructions provided in next sections to configure the driver in the Venafi TPP platform.

2.1 Proxy settings

In case the server on which the Venafi TPP platform is installed needs to use a proxy server to open connections to the Internet, it is necessary to insert the proxy settings into the script. To this end, open the script with a plain text editor, locate the line where the variable `$global:proxy_url` is assigned (normally empty) and insert you full proxy URL in the double quotes as in the following example:

```
$global:proxy_url = "http://192.168.123.145:9090" # set proxy url
```

⚠ Finally save the script, of course. Be careful not to alter any other part of the script inadvertently, or you may have hard-to-diagnose malfunctions.

2.2 Custom Fields

In the following we explain how to configure the Custom Fields that are required by the Actalis script.


It should be noted that:

- Custom Field names are case sensitive: they must be configured exactly as shown below;
- the values allowed for List-type Custom Fields must be exactly those indicated below;
- some Custom Field must be flagged as "**Required**", as shown below;
- none of the Custom Fields should be flagged as "**Hidden**".


⚠ Failure to comply with the above instructions may cause the script to malfunction.

The Actalis script requires the following Custom Fields:


- **Actalis_Certificate_Class**: defines what kind of certificate to issue. Below is the image taken from the Venafi TPP platform showing the configuration.



- **Actalis_Validity_In_Months**: defines the certificate duration in months. Below is the image taken from the Venafi TPP platform showing the configuration.



- **Actalis_Reference_Email**: defines the email address used to create the reference user for the provided organization when it doesn't already exist. Below is the image taken from the Venafi TPP platform showing the configuration.



2.3 Certificate credential

A p12 credential is required to access the Actalis CA web services used by the script. This credential is provided by Actalis and should be uploaded to the Venafi TPP platform as a “Certificate Credential”.


⚠ If you have previously received from Actalis a credential for the Test environment, please note that you will need a *different* credential for the Production environment.

2.4 Adaptable CA Template

Below are the configurations needed for the Actalis Adaptable CA Template object.

⚠ Make sure to assign this template to the folder where you want Actalis certificates to be saved.





The Certificate Credential and all the Custom Fields are described above. During this configuration you should assign them to the template. As to the remaining settings, follow this guide:

“Service Address”:

- for Production enter **https://extwebra.actalis.it/entws**
- for Testing enter **https://extwebra-pte.actalis.it/entws**

“PowerShell Script”: the filename of the Actalis Adaptable Script

“Renewal Window”: **30** (days before the certificate expires)

“Allow Reissuance”: **YES** (checked)

“Subject Alt Name Enabled”: **YES** (checked)

“Enable Debug Logging”: **YES** (checked)